

HCL OneTest[™] Server 10.5.0 Documentation September 2022



Special notice

Before using this information and the product it supports, read the information in Notices on page mclxxiii.

Contents

Chapter 1. Release Notes	9
Product description	9
What's new	9
Installing and upgrading	
Known issues	11
Contacting HCL support	11
Chapter 2. System Requirements	13
Hardware	14
Operating systems	
Host prerequisites	
Supported software	16
Chapter 3. Getting Started Guide	
Server overview	
Supported versions of assets and resources	
Suites and tests supported	
HCL OneTest Data overview	23
Task flow: Test runs and results	
Task flow: Server access from desktop clients	
Accessibility features	35
Chapter 4. Administrator Guide	
Installation of the server software	
Installation of the server software on Ubuntu	
Installation of the server software on Azure Kubernetes Service	46
Management of server features	58
Server software upgrade methods	61
Server software upgrade on Ubuntu	61
Upgrading the server software on Azure Kubernetes Service	63
Migration of user data	66
Migrating user data on Ubuntu from 10.1.2 or earlier	68
Migrating user data on Ubuntu from 10.1.3 or later	69
Backup and restoration of the server data	71
Backup and restoration of the server data on Ubuntu	
Backup and restoration of the server data on Azure Kubernetes Service	76
Uninstallation of the server software	
Uninstalling the server software from Ubuntu	
Uninstalling the server software from Azure Kubernetes Service	
Configuration of the server software	83
User administration	
Certificate authority: Importing and extending lists	
Copying third-party application Jars to Kubernetes	
Changing the password seed	103
Server extensions	
Team space administration	108
Team space overview	
Creating a team space	111

Tasks in a team space	113
Tasks in projects in a team space	117
HCL license portal	
Chapter 5. Test Author Guide	
Edit branch overview	129
Test authoring	130
Creating tests or virtual service resources	
Editing a test	
Editing virtual service resources	
Datasets overview	142
Creating a dataset	
Creating a dataset by using a CSV file	145
Creating a dataset by using data fabrication	147
Editing a dataset	150
Publishing a dataset	160
Viewing a dataset	161
Deleting a dataset	
Generation of test data	
Schema fabrication	
Schema design overview	
Test data generation from structured schemas	
Status of generated test data	
Chapter 6. Test Execution Specialist Guide	
System modeling	249
Task flows for working with a system model	252
Adding a repository to a team space	
Creating a system model	256
Creating components	257
Creating child components	
Creating linkages between components	
Deleting linkages between components	262
Modifying components	
Deleting components	
Publishing changes to the system model	
Associating resources with components	
Viewing resources associated with components	
Removing resources associated with components	
Publishing changes of associating resources with components	
Viewing the system model	
Deleting a system model	
Deleting a repository that is added to a team space	
Prerequisites to running tests	
Test run considerations for AFT Suites or Functional tests	
Test run considerations for API Suites or API tests	
Test run considerations for schedules	
Considerations for using Jaeger traces in reports	
Test run considerations for JMeter tests	

Test run considerations for JUnit tests	206
Test run considerations for Postman tests	
Management of agents	
Management of performance agents	
Management of Docker hosts	
Test run considerations for running tests on remote Docker hosts	
Setting up a remote Docker host	
Setting up a secure remote Docker host	
Copying third-party application Jars to a remote Docker host	
Registering a remote Docker host	
Viewing remote Docker hosts that are registered with HCL OneTest [™] Server	
Adding a remote Docker host	
Editing configurations	
Deleting a remote Docker	
Unregistering a remote Docker host from HCL OneTest [™] Server	
Management of remote Kubernetes clusters	
Considerations for using a remote Kubernetes cluster	
Registering a remote Kubernetes cluster	
Viewing remote Kubernetes clusters	
Adding a remote Kubernetes cluster to a project	
Editing configurations of a remote Kubernetes cluster	
Removing a remote Kubernetes cluster from a project	
Unregistering a remote Kubernetes cluster from a team space	
Test run configurations	
Configuring a Suite or test for a quick run	
Configuring an AFT Suite run	
Configuring an API Suite or an API test run	343
Configuring a run of a Compound Test that contains HTML tests	354
Configuring a run of a Compound Test that contains Web UI tests or a Functional Web UI test	363
Configuring a run of a Compound Test that contains mobile tests or a Functional Mobile test	374
Configuring a run of a Functional Windows test	387
Configuring a run of a Compound Test that contains performance tests or a Performance test	397
Configuring a run of a JMeter test	408
Configuring a run of a JUnit test	414
Configuring a run of a Postman test	421
Configuring a run of a Rate Schedule or VU Schedule	428
Running tests by using Data Fabrication	439
Configuration of test runs in a GitHub Actions Workflow	441
Prerequisites to run tests in a GitHub Actions Workflow	441
Configuring a test run in a GitHub Actions Workflow	442
Configuration of a scan of an application code	444
Considerations to scan an application code	445
Configuring a run to scan the application code	447
Management of running tests	453
Viewing the state of test assets	453
Viewing the progress of running test assets	457
Checking logs	460

Resetting the configuration settings for a test run	461
Stopping test runs	
Canceling scheduled test runs	
Management of virtualized services	
Prerequisites for running virtual services	468
Viewing intercepts that are registered with a team space on HCL OneTest [™] Server	474
Viewing virtual service resources	
Configuring a run of a virtual service	
Running HTTP virtual services without using proxies	491
Viewing running instances of virtual services	496
Viewing configurations of running instances of virtual services	501
Modifying configurations of running instances of virtual services	505
Viewing routing rules of the virtual services	
Viewing usage statistics of virtual services	
Stopping virtual services	512
Test results	
Test results and reports	514
Test results data in Grafana	
Viewing Surefire format reports	
Test logs	
Test log queries	
Resource monitoring	
Resource monitoring capabilities	548
Resource monitoring agents	567
Managing sources	
Collecting and viewing resource monitoring usage data	
Configuration of a change management system	
Configuration of Atlassian Jira as a change management system	593
Configuration of Azure DevOps as a change management system	603
Configuration of HCL® Compass as a change management system	
Integrations with other applications	620
Integration plugin compatibility matrix	
Integration with Azure DevOps	622
Integration with HCL® Launch	632
Integration with IBM Engineering Test Management	648
Integration with Jenkins	655
Integration with UrbanCode™ Deploy	670
Integration with other applications	
Managing access to the server	708
Working with HCL OneTest [™] Server REST services	710
Chapter 7. Test Manager Guide	711
Team space management	711
Viewing team spaces	711
Adding members to a team space	712
Modifying the configuration of a team space	715
Viewing the configuration of a team space	717
Becoming a team space member	719

Managing members and their roles in a team space	
Deleting a team space	723
Test assets and a server project	724
Working with projects in a team space	724
Repository considerations for a server project	725
Adding a project	
Adding repositories to a server project	
Secrets configuration	731
Adding users to a project	731
Viewing active projects	732
Changing the visibility configuration of a project	
Becoming a project member	733
Managing access to server projects	
Archiving or unarchiving server projects	736
Deleting server projects	737
Project overview	
Managing repositories	739
Adding repositories to a server project	740
Updating the authentication credentials of the repository	743
Deleting a repository	
Refreshing repositories manually	744
Selecting the global branch in a project	745
Creating webhooks	746
Protecting API test assets by using secrets	
Managing secrets collections	
Granting access to members or member roles	751
Creating a secret in a secrets collection	750
Managing secrets	
Managing an encrypted dataset	754
Creating a classification	
Editing or deleting a classification	755
Moving an encrypted dataset to another classification	757
Removing a dataset from the classification	
Granting classification access to members or members roles	758
Managing notifications	
Managing in-app notifications	761
Managing email notifications	
apter 8. Reference Guide	
Files	
Connections	
Project-level connections	
Connection testing	
Resource adapters	773
Schema design	
Introduction to schema design	
Type properties	
Item restrictions	843

Components	
Partitioning	
Type inheritance	
Schema analyzer	
Distinguishable objects	
Functions and expressions	
Chapter 9. Troubleshooting	
Troubleshooting issues	1136
Troubleshooting issues: Data fabrication	
Schema designing error or warning messages	
Compile-time error messages	
Configuring log files	1166
Audit log overview	
Commands used in HCL OneTest Data	
Troubleshooting installation issues	
Security Considerations	
Notices	mclxxiii
Index	

Chapter 1. Release notes for HCL OneTest[™] Server

This document includes information about What's new, installation and upgrade instructions, known issues, and contact information of HCL Customer Support.

Contents

- Product description on page 9
- What's new on page 9
- Deprecated capabilities on page 10
- Removed capabilities on page 11
- Installing and upgrading on page 11
- Known issues on page 11
- Contacting HCL support on page 11

Product description

You can find the description of HCL OneTest[™] Server.

HCL OneTest[™] Server is a server that includes capabilities such as project and role-based security, Docker-based distribution and installation, and running of test cases. For more information about the server, see HCL OneTest Server overview on page 19.

What's new

You can find information about the features introduced in this release of HCL OneTest[™] Server.

The following sections list the new features, enhancements or other changes made in this release.

Support to install Jaeger as part of HCL OneTest[™] Server is removed

The support to install Jaeger during the installation of HCL OneTest™ Server is removed.

Support for HCL® Compass as a change management system

You can now create HCL® Compass records for the tests that you run on HCL OneTest[™] Server, after you configure the HCL® Compass server as a change management system on HCL OneTest[™] Server.

Running tests on remote Kubernetes clusters

You can now run the supported test resources on remote Kubernetes clusters that you register with a team space on HCL OneTest[™] Server and add the Kubernetes cluster to your project in the team space.

You can select the remote cluster as a location to run the tests when you configure a run.

You can edit the configurations of a cluster, remove a cluster from a project, or unregister the cluster from a team space.

See Management of remote Kubernetes clusters on page 312.

· Support to run tests or resources as a GitHub Action

You can now run tests or resources that are contained in your project on HCL OneTest[™] Server as a GitHub Action from a Git repository.

See Configuration of test runs in a GitHub Actions Workflow on page 441.

· Creating an Edit branch to contain resources before committing to the repository branch

When you want to create or edit datasets, test assets, virtual service resources, or resources that are associated with components in a system model, you must now create an *Edit* branch, which is a temporary branch that will contain these until the time you commit or publish these to a branch in the project repository or the team space repository.

· Support to schedule recurring test runs

You can now schedule recurring test runs on HCL OneTest[™] Server.

· Panning icon removed from the System Model page

The Pan icon that existed previously to pan the view in the **System Model** page is now removed. You can now pan the view by clicking the area and moving the area in the direction you want with the left-mouse button pressed.

Enhancements to the HCL OneTest[™] Studio extension

When you run tests from Azure DevOps Pipeline by using the HCL OneTest[™] Studio extension, you can now store the JUnit report that is generated for the test in the XML format.

See Running HCL OneTest Server tests in an Azure DevOps Pipeline on page 624.

Enhancements to the Jenkin plugin

You can now view the test results by using the Test Results Analyzer feature in Jenkins if you have installed the Test Results Analyzer plugin in Jenkins. See Running tests from Jenkins on page 669.

Deprecated capabilities

You can find information about the capabilities that are deprecated in this release and are planned for a removal in a future release.



Note: You can contact the HCL Client Support team if you have any concerns.

The following feature or capability is deprecated:

• The test authoring capability of HCL OneTest[™] Server that utilizes a containerized version of the HCL OneTest[™] Studio desktop authoring products to author tests and virtual services.

Removed capabilities

No capabilities were removed in this release.

Installing and upgrading

You can find information about the installation and upgrade instructions for HCL OneTest[™] Server.

Installing HCL OneTest[™] Server

For instructions about installing the software, see Installation of the server software on page 36.

Upgrading of HCL OneTest[™] Server

For instructions about upgrading the software, see Server software upgrade methods on page 61.

Known issues

You can find information about the known issues identified in this release of HCL OneTest[™] Server.

Table 1. Release documents - Fix list and known

issues

Product	Download document	Knowledge Base
HCL Release document		Knowledge articles
OneTest⁺	и	
Server		

The knowledge base is continually updated as problems are discovered and resolved. By searching the knowledge base, you can quickly find workarounds or solutions to problems.

Contacting HCL support

You can find information about Contacting HCL support.

- For technical assistance, contact HCL Customer Support.
- Before you contact HCL support, you must gather the background information that you might need to describe your problem. When you describe a problem to the HCL support specialist, be as specific as possible and include all relevant background information so that the specialist can help you solve the problem efficiently. To save time, know the answers to these questions:

- What software versions were you running when the problem occurred?
- $\,\circ\,$ Do you have logs, traces, or messages that are related to the problem?
- Can you reproduce the problem? If so, what steps do you take to reproduce it?
- \circ Is there a workaround for the problem? If so, be prepared to describe the workaround.

Chapter 2. System Requirements

This document includes information about hardware and software requirements for HCL OneTest™ Server.

Contents

- Hardware on page 14
- Operating systems on page 14
- Host prerequisites on page 16
 - Licensing on page 16
 - Web browsers on page 16
- Supported software on page 16
 - Development tools on page 17
 - Integrations on page 17
 - Runtime environment on page 18
- Disclaimers on page 13

Disclaimers

This report is subject to the Terms of Use and the following disclaimers:

The information contained in this report is provided for informational purposes only. While efforts were made to verify the completeness and accuracy of the information contained in this publication, it is provided AS IS without warranty of any kind, express or implied, including but not limited to the implied warranties of merchantability, non-infringement, and fitness for a particular purpose. In addition, this information is based on HCL's current product plans and strategy, which are subject to change by HCL without notice. HCL shall not be responsible for any direct, indirect, incidental, consequential, special or other damages arising out of the use of, or otherwise related to, this report or any other materials. Nothing contained in this publication is intended to, nor shall have the effect of, creating any warranties or representations from HCL or its suppliers or licensors, or altering the terms and conditions of the applicable license agreement governing the use of HCL software.

References in this report to HCL products, programs, or services do not imply that they will be available in all countries in which HCL operates. Product release dates and/or capabilities referenced in this presentation may change at any time at HCL's sole discretion based on market opportunities or other factors, and are not intended to be a commitment to future product or feature availability in any way. Discrepancies found between reports and other HCL documentation sources may or may not be attributed to different publish and refresh cycles for this tool and other sources. Nothing contained in this report is intended to, nor shall have the effect of, stating or implying that any activities undertaken by you will result in any specific sales, revenue growth, savings or other results. You assume sole responsibility for any results you obtain or decisions you make as a result of this report.

Notwithstanding the Terms of Use users of this site are permitted to copy and save the reports generated from this tool for such users own internal business purpose. No other use shall be permitted.

Hardware

You can find information about the hardware requirements for HCL OneTest[™] Server.

Hardware	Requirement	Notes
Disk space	256 GB	Additional resources are required by the cluster for the execution of test assets.
		Disk space requirements can grow in line with quantity of test assets and results stored.
Memory	32 GB	Additional resources are required by the cluster for the execution of test assets.
		An additional 1 GB of memory is required by the cluster for each au- thoring or editing session.
Processor	8 CPUs	Additional resources are required by the cluster for the execution of test assets.
		Additional 3 CPUs are required by the cluster for each authoring or editing session.
Network	Gigabit (1000) Ether- net	
Other hardware		Operating system support is specified by the supported platform for Kubernetes. Refer to their associated documentation for a list of supported operating systems.

Related information

System Requirements on page 13

Operating systems

You can find details about the supported operating systems.

Contents

• Operating systems on page 15

Bit version support

Different parts of a product might run on the same operating system but support different application bitness.

For example, one part of the product might run only in 32-bit mode, whereas another might support 64-bit tolerate mode.

Bitness	Description
64-Tolerate	The product or part of the product runs as a 32-bit application in the 64-bit platforms listed as supported.
64-Exploit	The product or part of the product runs as a 64-bit application in the 64-bit platforms listed as supported.

Operating systems

Operating system	Hardware	Bitness	HCL OneTest™ Server	Notes
Ubuntu Server 18.04 LTS	x86-64	64-Exploit	~	Running K3s v1.24.3
Ubuntu Server 20.04 LTS	x86-64	64-Exploit	~	Running K3s v1.24.3

Cloud platforms

You can find details about the supported Cloud platforms.

Product	Cloud platform	Version
HCL OneTest™ Server	Azure Kubernetes Service	1.22.6
		1.23.8

Related information

System Requirements on page 13

Host prerequisites

You can find the prerequisites that support the operating capabilities for HCL OneTest[™] Server.

Contents

- Licensing on page 16
- Web browsers on page 16

Licensing

License Server	Version	HCL OneTest™ Server
FlexNet Operations LLS	2017.02	~
	2021.05	~

Web browsers

Browser	Version	HCL OneTest™ Server
Apple Safari	13 or later	~
Google Chrome	102 or later	~
Microsoft Edge	102 or later	~
Mozilla Firefox	101 or later	~
Mozilla Firefox (including ESR ver- sions)	91 or later	~

Related information

System Requirements on page 13

Supported software

You can find details about the additional software that are supported.

Contents

- Development tools on page 17
- Integrations on page 17
- Runtime environment on page 18

Development tools

Supported software	Version	HCL OneTest™ Server
Git	2.19.0	~
	2.21.0	~
	2.22.0	~
	3.1.0	~

Integrations

Supported software	Version	HCL OneTest™ Server
Azure Plugins	Cloud version, latest	×
HCL® Launch	7.1	~
	7.2.1	~
	7.2.3	~
IBM® Engineering Test	7.0.1	~
Management	7.0.2	~
Jenkins	2.x	~

Supported software	Version	HCL OneTest™ Server
Jira	8.x	~

Runtime environment

Supported software	Version	HCL OneTest™ Server	Notes
Helm CLI	3.8.0	~	Required locally for Helm.
	3.8.1	~	
	3.9.0	~	
	3.9.2	~	
Jaeger Operator		~	Can be optionally installed if you require trace information about test runs. The ver- sion depends on the target platform.

Related information

System Requirements on page 13

Chapter 3. Getting Started Guide

This guide provides an overview of HCL OneTest[™] Server. You can find the task flows to get you started with HCL OneTest[™] Server. This guide is intended for new users.

Before you can perform the various tasks described in the *Getting Started Guide* and the other guides, you must install HCL OneTest[™] Server. See Installation of the server software on page 36.

HCL OneTest[™] Server overview

HCL OneTest[™] Server brings together test data, test environments, and test runs and reports into a single, web-based browser for testers and non-testers.

HCL OneTest[™] Server provides the following capabilities:

Web-based continuous testing platform

HCL OneTest[™] Server is a web-based continuous testing platform built on modern, cloud native technologies that enables test teams to run a breadth of tests that includes API, functional, and performance tests and to benefit from a holistic view of test progress. HCL OneTest[™] Server is built on Docker for easy deployment. You can scale your testing on the cloud or remote on premise systems with native Docker, Kubernetes, and IBM® Red Hat OpenShift support.

Role-based access and security

Security is a key concern for HCL clients and therefore, HCL OneTest[™] Server brings a comprehensive, role-based access control scheme to the server with project owners assigning key permissions (by using roles) for specific members, for example managing test data or working with secrets such as passwords.

Running of tests from the server by using Docker containers

Server-based running of tests is the starting point for HCL OneTest[™] Server. For members of a project with the appropriate role, HCL OneTest[™] Server enables direct running of tests from the browser by using transient Docker containers.

Connected agents for existing performance agents

Agent owners can connect existing performance agents to the server and add them to a project for running schedules and Accelerated Functional Testing (AFT) Suites on the current infrastructure.

Project overview statistics

The **Overview** page for HCL OneTest[™] Server offers you a quick, simple view on the state of testing for your projects.

Project home page

The home page lists your projects and other projects, which makes it easy to manage different projects within an organization.

Reporting and the Resource Monitoring Service

HCL OneTest[™] Server provides the home for capabilities that previously were hosted on HCL® Quality Server. Reporting and the Resource Monitoring Service are in HCL OneTest[™] Server and provide a more direct relationship with their related projects. These capabilities also benefit from the project level, rolebased access controls. You can view unified test results to help you make informed business decisions.

Test data authoring

Beyond the concept of a project held in a Git repository for a simple location of tests and related assets, you can do full concurrent editing of test data sets directly from HCL OneTest[™] Server. This true multiuser capability enables team members to collaborate more easily as well as try out data changes without impacting the rest of the team. When satisfied with the results, team members can push their changes. You can also fabricate sample data to perform tests by using the data generator supported in HCL OneTest[™] Server.

Integration with DevOps tools

You can integrate HCL OneTest[™] Server with various popular DevOps tools like Jenkins, UrbanCode[™] Deploy, HCL® Launch, or Microsoft Azure DevOps to get more value from your DevOps pipelines. You can use UrbanCode[™] Deploy, or HCL® Launch to define a deployment process that automatically triggers test cases and have those test insights available directly within HCL® UrbanCode[™] Velocity. With the Microsoft Azure DevOps integration, you can also define a Azure DevOps pipeline that includes direct execution of tests by using the HCL OneTest[™] Server scalable infrastructure. HCL OneTest[™] Server also integrates with Jira for defect tracking and GitHub for software source management and version control.

Supported versions of assets and resources

You can find information about the versions of assets, resources, agents and Dockers that are supported in HCL OneTest[™] Server. You can also find information about the versions of the desktop clients that are supported.

The following table lists the versions of assets or resources created in the desktop clients along with the agents, Dockers, or proxies that are supported in HCL OneTest[™] Server:

Resource	Supported	Not supported
Assets or resources created in HCL OneTest™ UI	Assets or resources created in HCL OneTest [™] UI which are of versions earlier or the same as HCL OneTest [™] Server.	Assets or resources created in any later version of HCL OneTest [™] UI that is later than the version of HCL OneTest [™] Server.
Assets or resources created in HCL OneTest™ API	Assets or resources created in HCL OneTest [™] API which are of versions earlier or the same as HCL OneTest [™] Server	Assets or resources created in any later version of HCL OneTest [™] API that is later than the version of HCL OneTest [™] Server.

Resource	Supported	Not supported
Assets or resources created in HCL OneTest™ Performance	Assets or resources created in HCL OneTest [™] Performance which are of versions earlier or the same as HCL OneTest [™] Server	Assets or resources created in any later version of HCL OneTest [™] Per- formance that is later than the ver- sion of HCL OneTest [™] Server.
HCL OneTest™ Performance Agents	HCL OneTest™ PerformanceAgents which is the same version as HCL OneTest™ Server	Before you install the agents that are of the current version, see Manage- ment of agents on page 288.
Dockers on a remote host computer	Image of HCL OneTest [™] Server which is the same version as HCL OneTest [™] Server that you want to use to run tests, must be installed on the Docker on a remote host computer.	Before you set up Dockers remotely, see Management of Docker hosts on page 296.
HTTP proxies	Installation of the proxy component from HCL® Quality Server which is the same version as HCL OneTest™ Server.	Before you use HTTP proxies, see Setting up the HTTP proxy on page 472.

If there is a mismatch in the versions of the assets, resources, agents, or images used in Dockers with the version of HCL OneTest[™] Server that you are using, any of the following events can occur:

- Warnings or Errors are displayed when you add a repository to a project in your team space.
- Warnings or Errors are displayed when you open a project that you migrated from a previous version of HCL OneTest[™] Server.
- Warnings or Errors are displayed when you add or manually refresh a repository to which you added assets or resources that were created on a desktop client with a version previous to or later than the version of HCL OneTest[™] Server that you want to use.
- Test runs that you start or schedule on an agent or Docker fail to run.
- You cannot view the proxies that are registered with HCL OneTest[™] Server on the Agents and Intercepts page.

Suites and tests that are supported on HCL OneTest[™] Server

You can find information about the types of Test Suites and tests that you can configure for a run in a project on HCL OneTest[™] Server.

The following table lists the Test Suites and test types that are supported and those tests that are not supported to run on HCL OneTest[™] Server:

Supported Suites	Supported tests	Unsupported tests
 Accelerated Functional Testing (AFT) Suites Compound Tests that contain any of the following types of tests: Web UI tests HTML tests Mobile tests 	 Functional Web UI tests Functional Windows tests Functional Mobile tests 	 Traditional HTML tests Traditional non-HTML tests
 API Suites that include the following Test Suites: Test Suites that contain scenarios with references to local stubs. Test Suites that contain stubs that virtualize services run in any Kubernetes cluster or in the Kubernetes cluster or in the Kubernetes cluster that hosts HCL OneTest[™] Server. Stubs 	API tests	Suites or tests with subscribe actions that operate in the watch mode.
 Compound Tests that contain performance tests Rate Schedules VU Schedules 	Performance tests	 A single test script of any test extension. Tests that belong to 32- bit test extensions and SOA Quality included in VU Schedule, Rate Schedule, and Com- pound Test. Citrix, SAP, or Siebel as an individual test or as part of a Compound Test.
Postman resources		
JMeter tests		
JUnit tests		

Note: You must create compound tests for the same type of tests. For example, you can create a compound test that has different mobile tests that use different mobile testing platforms.

Restriction: You cannot merge folders that contain different test projects in the same project directory. For example, you cannot create a project directory that contains a Performance test project and an API Suite project. You must create separate project directories for each test type. For example, you must create the Performance test in the project directory as /MyPerfProject/ and the API Suite in the project directory as /MyAPIProject, before you commit the projects to the remote repository.

Related information

Test run configurations on page 327

HCL OneTest Data overview

HCL® OneTest[™] Data is an automated and customizable tool to generate the test data. HCL® OneTest[™] Data is one of the components of HCL OneTest[™] Server and can be accessed as Data Fabrication in the HCL OneTest[™] Server GUI.

You can generate the test data in various file formats such as Excel files, Native file, Comma-Separated Values (CSV), JavaScript Object Notation (JSON), and Extensible Markup Language (XML).

The test data is the core component of any application testing. Creating test data manually is very time-consuming. With HCL® OneTest[™] Data generator, you can generate huge volumes of intelligent data to perform application testing without the risk of data leaks or privacy issues. The generated test data can drive the testing of any application by using HCL OneTest suite.

HCL® OneTest[™] Data provides the following capabilities:

- Generates real-time data automatically.
- Provides powerful built-in API to match the data with the generated datatype.
- Supports flexibility to model the data.
- Supports both single and multi-tenancy.

HCL® OneTest[™] Data provides the following benefits:

- Protects data privacy.
- Improves the efficiency and accuracy of predefined data and real-time data generation.
- Avoids extraction of real and potentially sensitive information from production system.

You can find more information about the tasks that you must perform to generate the test data by using HCL® OneTest[™] Data.

Data design environment overview

The data design environment is a graphical interface to design all its components and data generation rules to generate test data on user demand. To design the components for data generation, you must log in to HCL OneTest[™] Server, and then create a project.

You use various components to structure data in HCL® OneTest[™] Data. The components of data design environment are:

- Files
- Connections
- Schemas

The definitions of data stored in the schemas are used to define a map. The map specifies the transformation logic in the form of rules. The map identifies the data definition of a schema, validates the type properties of data by using rules, and compiles the rules to generate the real-time test data.

You can refer to workspace management to manage workspace in HCL® OneTest™ Data.

Related information


Test assets and a server project on page 724

Task flows: HCL OneTest Data

You can use the task flow diagram to get started with HCL® OneTest[™] Data. After you select your project in HCL OneTest[™] Server and navigate to the **Data Fabrication** page, you can complete the tasks in sequence to generate the test data. You can click the links to get more information about the tasks.

Generating the test data by using HCL OneTest Data


You can use the task flow diagram to help you to generate the test data.



- 1. Generation of test data on page 23
- 2. Import JSON or XSD from the local file system on page 166
- 3. Generate a schema by using Connections on page 167
- 4. Import data from the local file system on page 169
- 5. Create a schema on page 168
- 6. Modify a schema on page 174
- 7. Design a schema on page 174
- 8. Define types on page 174
- 9. Set type properties on page 176
- 10. Use sample files on page 182
- 11. Add regular expressions on page 181

Generating schema by using Connections


You can use the task flow diagram to generate a schema by using **Connections** in the **Data Fabrication** page.



- 1. Create a sample schema on page 195
- 2. Establish a connection between HCL OneTest Data and external resource on page 167
- 3. Generate a schema in HCL OneTest Data on page 199
- 4. Generate the test data on page 200

Integrating HCL OneTest Data with other applications

You can use the task flow to integrate HCL® OneTest[™] Data with other applications such as Jenkins and UrbanCode[™] Deploy.



- 1. Integration with other applications on page 686
- 2. Generating the test data by using Jenkins on page 686
- 3. Generating the test data by using HCL OneTest Data on page 693
- 4. Generating the test data by using Jenkins on page 686
- 5. Generating the test data by using Jenkins on page 686
- 6. Generating the test data by using HCL OneTest Data on page 693
- 7. Generating the test data by using HCL OneTest Data on page 693

Project management

You can create a project to manage the data design environment that is used to generate the test data. If the data design environment that you created is no longer required, then you can archive or delete the project. If you do want to use an archived project, you can unarchive it.

While you manage your project, the following components of HCL® OneTest[™] Data are impacted:

- Projects
- Schemas
- Jobs
- Data files
- API history
- Map files
- Files
- Connections
- Actions

If you want to modify the name of your HCL® OneTest[™] Data project, then you can rename the project in HCL OneTest[™] Server.

Note: When you delete any archived project, then that project is deleted based on the configured job settings.

Related information Configuring job settings on page 246

Workspace management

You can view and manage all the data design components such as files, connections, or schema of your project on the **Workspace** page.

Quick Links is a list of links that enables you to access the frequently used features of HCL® OneTest[™] Data. You can export or import the project by using the list of links in **Quick Links**. You can also export or import a selective list of components.

Importing a project or components

When you have a project or any component of a project into your local file system and you want to reuse it for another project, you can import those artifacts from the local file system.

Before you begin

- You must have a project or any component of a project in your local file system.
- The project or component that you want to import must be in a zip format.

1. From the list of links in Quick Links, click Import into workspace.

Result

The Import dialog appears.

2. Select a file you want to import into your workspace and click Import.

Results

The selected file is imported successfully into the workspace.



Exporting a project or components

When you want to reuse your existing project for another project, you can export either the selected components or an entire project to your local file system.

Before you begin

You must have a project.

1. To export the entire project, click Export current workspace from the list of links in Quick Links.

Result

The project with all its artifacts is exported to your local file system.

2. To export the selective components from a project, click Selective export of current workspace.

Result

The Selective Export dialog appears.

- 3. Select schemas, files, or connections from the drop-down list. You can select multiple components to export.
- 4. Click OK to export.


Results

The selected file is exported successfully from the workspace.

Task flow: Test runs and results in HCL OneTest[™] Server

You can use the task flow diagram to get started with HCL OneTest[™] Server. After you install the software, you can complete the tasks in sequence to run test assets in HCL OneTest[™] Server and view and analyze the test results.

You can click the links to get more information about the tasks. The diagram also provides the tasks to be performed by personas. HCL OneTest[™] Server supports user roles.




- 1. Default user administration on page 85
- 2. Test assets and a server project on page 724
- 3. Adding a project on page 727

32

- 4. Adding repositories to a server project on page 728
- 5. Protecting API test assets by using secrets on page 747
- 6. Managing an encrypted dataset on page 754
- 7. Adding users to a project on page 731
 - 8. Adding a performance agent to a project on page 291
- 9 Test run configurations on page 327

Task flow: HCL OneTest[™] Server access from desktop clients

You can use the task flow diagram to help you access the server from the different desktop clients to retrieve secrets, publish reports, or enable resource monitoring agents. You can perform these tasks after you install and set up the server.



- 1. Managing access to HCL OneTest Server on page 708
- 2. Managing access to HCL OneTest Server on page 708
- 3. Test results and reports on page 514
- 4. Test results and reports on page 514
- 5. Test results and reports on page 514
- 6. Retrieving secrets
- 7. Managing access to HCL OneTest Server on page 708
- 8. Configuring HCL OneTest Performance Agent
- 9. Enablement of Resource Monitoring services for a schedule

Related information

Managing access to server projects on page 734

Accessibility features

Accessibility features help users who have physical disabilities, such as visual and, hearing impairment, or limited mobility, to use the software products successfully.

Accessibility compliance

The product documentation is published by using Oxygen XML WebHelp Responsive. To understand the accessibility compliance status for Oxygen XML WebHelp Responsive, refer to WebHelp Responsive VPAT Accessibility Conformance Report.

Accessing UI elements

HCL OneTest[™] Server supports navigation in the UI by using different methods such as a mouse, keyboard, or touchpad.

You can use the keyboard keys such as **Tab**, arrow keys such as **UP**, **DOWN**, **LEFT**, and **RIGHT** to navigate to the different pages in the **Navigation** pane or to the different action labels in the right pane on the UI.

Chapter 4. Administrator Guide

This guide describes how to install the HCL OneTest[™] Server software.

After you install the software, you can perform administration tasks such as license configuration, user management, security, memory and disk usage management, back up and restore user data, and other tasks that a server administrator can perform. This guide is intended for administrators.

As a Server Administrator, you can assign the role of a Server Administrator to any user. For information about how to change the role, see Default user administration on page 85.



Remember: When your role is changed from a user to a *Server Administrator*, you must log out and log in again so that HCL OneTest[™] Server can apply the change in your role.

Installation of the server software

To get started working with HCL OneTest[™] Server, you must first install the server software.

You can install HCL OneTest[™] Server on the following platforms:

- Ubuntu Server (by using k3s)
- Azure Kubernetes Service (AKS)

Installation task flows

Ubuntu Server

You must perform the following tasks to install HCL OneTest[™] Server:

- 1. Set up Ubuntu Server.
- 2. Install the OpenSSH server and the Helm software.
- 3. Set up the Kubernetes environment (k3s) by using the provided script.
- 4. Install HCL OneTest[™] Server.

Azure Kubernetes Service

You must perform the following tasks to install HCL OneTest[™] Server:

- 1. Create an Azure subscription and set up the AKS cluster.
- 2. Install the Helm software.
- 3. Install the kubectl and Azure command-line interface (Azure CLI) software.

- 4. Install Emissary-ingress.
- 5. Install HCL OneTest[™] Server.

To learn more about the installation of the server software on platforms such as Ubuntu and AKS, refer to the following topics:

Installation of the server software on Ubuntu

You can find information about the tasks that you can perform to install HCL OneTest[™] Server software on the Ubuntu platform.

Prerequisites to install the server software on Ubuntu

You must complete certain tasks before you install HCL OneTest[™] Server on the Ubuntu platform.

The following sections describe prerequisites in detail:

- Internet access on page 37
- Ubuntu Server on page 37
- Backup of user data on page 38
- Mandatory software on page 38
- k3s environment on page 38
- Optional software on page 38
- Collection of usage metrics on page 39


Internet access

You must have access to the internet to install HCL OneTest[™] Server.

Ubuntu Server

You must install the supported version of Ubuntu Server and have a working Domain Name Server (DNS) that resolves the hostname into a machine-readable IP address.

For more information about specific versions of software requirements, see System Requirements on page 13.



organization requires user data to be stored in a separate partition, then you can create a mount point at / var/lib/rancher/k3s/storage/ with at least 128 GB capacity.

Backup of user data

If you want to upgrade HCL OneTest[™] Server from a previous version, then you must perform one of the following tasks based on the existing version of the server software:

- Back up the data from V10.0.2, Fix Pack 1 or earlier. See Backing up the user data from a previous release.
- Back up the data from V10.1.0 or later. See Backing up the server data on Ubuntu on page 72.

Note: You must select the existing version of HCL OneTest[™] Server from the drop-down list to view the procedure to back up and restore the user data for your version because the instructions differ for different versions.

Mandatory software

You must install the following mandatory software:

• Helm. For more information, refer to the Helm documentation. For more information about specific versions of software requirements, see System Requirements on page 13.



Note: The Helm command must be in one of the directories in your PATH environment variable.

• OpenSSH Server. For more information, refer to the Installation section in the OpenSSH Server documentation.



Note: If you use ssh to log in to the computer, then you can skip this step because OpenSSH is already installed on your computer.

k3s environment

You must set up the Kubernetes environment (k3s) along with other configurations such as firewall, Jaeger, and Prometheus server. See Setting up a Kubernetes environment (k3s) on Ubuntu on page 39.

Optional software

You can install the Jaeger operator to trace test logs and Jaeger-based reports when you run tests. For more information, refer to the Jaeger documentation.

You can then configure HCL OneTest[™] Server to use Jaeger traces by passing the following parameters during the installation of the server software:

```
--set global.jaegerDashboard.externalURL={my-jaeger-dashboard-url} \
--set global.jaegerAgent.internalHostName=localhost
```

Where {my-jaeger-dashboard-url} is the URL of the Jaeger server.

If you use the default values during the installation of Jaeger as suggested in the Jaeger documentation, then you must pass the following parameters during the installation of the server software:

```
--set global.jaegerDashboard.externalURL=https://$INGRESS_DOMAIN/jaeger \
--set global.jaegerAgent.internalHostName=jaeger-agent.observability
```

Where \$INGRESS_DOMAIN is the IP address of Jaeger.

Note: You can run the following command to get the value of \$INGRESS_DOMAIN:

kubectl get ingress

Collection of usage metrics

If you want HCL OneTest[™] Server to display the usage statistics of the virtual service instances, you must install the Prometheus server at the time of server installation.

Setting up a Kubernetes environment (k3s) on Ubuntu

You must set up a Kubernetes environment (k3s) so that you can install the server software on the Ubuntu Server. You can use the script that is provided with HCL OneTest[™] Server to set up a Kubernetes environment (k3s).

Before you begin

You must have completed the following tasks:

- · Installed the following software:
 - OpenSSH server
 - Helm
- Ensured that your computer has a Domain Name Server (DNS) resolvable host name to resolve the host name into a machine-readable IP address.

About this task

As part of the Kubernetes environment (k3s) set up, you can enable the Prometheus server to monitor your system resources by using metrics data.

- 1. Log in to the Ubuntu server using an SSH session.
- 2. Add the software registry to Helm by running the following command:

helm repo add hclsoftware https://hclcr.io/chartrepo/ot

3. Run the following command to get the latest updates from the repository:

helm repo update

4. Run the following commands to fetch the scripts that are used to install Kubernetes:

```
helm pull --untar hclsoftware/hcl-onetest-base --version 9.1050.0
chmod +x hcl-onetest-base/*.sh
```

5. Perform one of the steps described in the following table to install the k3s Kubernetes environment based on your requirement:

Step description	Step no
To install the Kubernetes environment (k3s)	Perform 5.a on page 40
To install the Kubernetes environment (k3s) by overriding the default name	Perform 5.b on page 40

a. Run the following commands to install the Kubernetes with a default domain name that is either based on IP address or fully qualified hostname:

Ubuntu version	Commands to be run	
18.04	\$ cd hcl-onetest-base \$ sudo ./ubuntu-init.sh	
20.04	\$ cd hcl-onetest-base \$ sudo HOME=\$HOME ./ubuntu-init.sh	

b. Run the following commands to install the Kubernetes environment (k3s) by overriding the default name:

Ubuntu version	Commands to be run	
18.04	\$ cd hcl-onetest-base	
	\$ sudo INGRESS_DOMAIN={onetest.}myorg.com ./ubuntu-init.sh	
20.04	\$ cd hcl-onetest-base \$ sudo INGRESS_DOMAIN={onetest.}myorg.com HOME=\$HOME ./ubun- tu-init.sh	

Where:

• {onetest.} is a sub-domain name that you specified for the server. For example, testenv.

Note: The sub-domain must consist of lowercase alphanumeric characters, "-"(hyphen) or ". "(period). Also, the value must start and end with an alphanumeric character.

• myorg.com is the domain name of your organization. For example, hcl.com

You can access the product through a web browser by using any of the following methods:

- Fully Qualified Hostname: When the server is configured, you can use hostname -f command to get the fully qualified host name defined in the DNS to access HCL OneTest[™] Server. For example, onetest.myorg.com
- IP address: You can use the IP address to access HCL OneTest[™] Server when you cannot create a specific DNS record for the server. For example, ip-address.nip.io.

Result

On completion of the ubuntu-init.sh script, a namespace with the name test-system is created to install the server software and the output displays the following information on the command-line interface:

- The INGRESS_DOMAIN that is in use. This is the URL from where you can access HCL OneTest[™] Server. You must use this value for the global.hclOneTestIngressDomain parameter in step 2 on page 44 in the server installation topic.
- The DNS information that the Kubernetes cluster uses to resolve names.
- Certificate Authority (CA) that you must import into the browser to prevent certificate errors.

You can run the following command to get the certificate from the system:

kubectl get secret ingress -n test-system -o jsonpath={.data.ca\\.crt} | base64 -d

• Instructions to confirm whether the Kubernetes environment has started.

You can refer to the **What to do next** section for more details on how to verify that the Kubernetes environment has started.

6. Perform one of the following options to configure a firewall:

Choose from:

• Run the following script to configure the firewall that allows traffic on cni0 and port 443:

Ubuntu version	Command to be run	
18.04	\$ sudo ./ubuntu-firewall.sh	

Ubuntu version	Command to be run	
20.04	\$ sudo HOME=\$HOME ./ubuntu-firewall.sh	

Note: You must consult your network administrator before you run this script, and confirm whether the firewall is compatible with your corporate policy.

- Update the firewall that allows traffic on *cni0* and port *443*, if your Ubuntu server is already configured with the firewall.
- 7. **Optional:** Run the following command to enable the Prometheus server to monitor your system resources by using metrics data:

./service.sh expose prometheus

Important: The Prometheus metrics are not protected, thus, any information logged into the Prometheus server might be accessible by anyone who has or discovers the *server-url>/prometheus* URL.

Results

You have set up the Kubernetes environment on Ubuntu.

What to do next

You can perform the following tasks:

• Log in to the server host system again after the installation process is completed so that changes to the group membership are applied.



Note: You can run the kubectl get pods -A command to verify that the Kubernetes environment is working. After a while, the status of the pods display a Running Or Complete state.

• Install the server software. See Installing the server software on Ubuntu by using k3s on page 42.

Related information

Prometheus server

Troubleshooting on page 1136

Installing the server software on Ubuntu by using k3s

You can install HCL OneTest[™] Server on the Ubuntu server that has a Kubernetes environment to run functional, integration, and performance tests. HCL OneTest[™] Server combines test data, test environments, and test runs and reports into a single, web-based browser for testers and non-testers.

Before you begin

- You must have read and been familiar with additional Helm parameters. See Additional Helm parameters on page 58.
- You must have performed the following tasks:
 - Completed the tasks provided in the Prerequisites section. See Prerequisites to install the server software on Ubuntu on page 37.
 - Set up the Kubernetes environment (k3s). See Setting up a Kubernetes environment (k3s) on Ubuntu on page 39.
 - Logged in to the server host system again after you completed the k3s environment setup.
 - Copied the INGRESS_DOMAIN value that is displayed on completion of the ubuntu-init.sh script.

About this task


The following table lists the variables that you must replace with the actual value in the command.

Variables	Description		
{my-ots}	The release name of your choice.		
	Note: The release name must consist of alphanumeric characters that are in lower- case or "-" (hyphen). The release name must also start with an alphabetic character and end with an alphanumeric character. For example, <i>my-org</i> or <i>abc-123</i> .		
{my-ingress-dns- name}	The INGRESS_DOMAIN value that is displayed on completion of the ubuntu-init.sh script.		
{password-seed}	A value of your choice for the password.		
	Important: This password seed is used to create several default passwords for the server. You must store the password seed securely. When you install the server software by using the backup of the user data, you can reuse the password seed. You can use this seed to restore the backed-up files either on the current or later versions of the server software.		
{cloud-license-serv- er-id}	The ID of the License Server for the initial team space, if you want to set the license for the first time.		

Variables	Description
	Important: When you want to upgrade the product from the previous version, you must configure the value of License Server ID from the Team Space License Configuration page when the installation of the server is complete.

The test-system is the name of the namespace that is created during the setting up of the k3s environment.

HCL OneTest[™] Server provides you with the test authoring capability, which utilizes a containerized version of the HCL OneTest[™] Studio desktop authoring tools.



You must not install the test authoring feature in the following scenarios:

- If you administer a network policy for your server installation.
- If you do not intend to use the test authoring feature.
- 1. Log in to the Ubuntu server using an SSH session.
- 2. Perform the following steps to install the server software:
 - a. Run the following command to get the latest updates from the repository:

helm repo update


b. Run the following command to retrieve the charts required to install the server software:

helm pull --untar hclsoftware/hcl-onetest-server --version 9.1050.0

c. Run the following command to provide the execution permission for the scripts that are available in the files directory:

```
chmod +x hcl-onetest-server/files/*.sh
```

d. Run the following command to install the server software:



If you want to enable the **Sign up** link on the **Login** page, then you must add the --set keycloak.signup.enabled=true parameter in the following helm install command.

```
helm install {my-ots} ./hcl-onetest-server -n test-system \
-f hcl-onetest-server/values-k3s.yaml \
--set global.hclOneTestIngressDomain={my-ingress-dns-name} \
--set global.hclFlexnetURL=https://hclsoftware.compliance.flexnetoperations.com \
--set global.hclFlexnetID={cloud-license-server-id} \
--set global.hclOneTestPasswordAutoGenSeed={password-seed}
```

3. **Optional:** Run the following command to remove a job that is used to initialize the PostgresQL database during the installation of the server software:

kubectl delete job {my-ots}-postgresql-init -n test-system

4. Run the following script from the hcl-onetest-server/files directory to verify and test the installed server software:

hcl-onetest-server/files/helm-test-diag.sh {my-ots} -n test-system

Results

On completion of the installation of server software, the output displays the following information on the commandline interface:

Instructions to access Keycloak to manage and authenticate users.

The user name can be keycloak and the password can be retrieved by running the following command:

```
kubectl get secret -n test-system onetest-keycloak-postgresql -o jsonpath="{.data.password}" |
base64 --decode; echo
```

Where, onetest is a sub-domain name that you selected for the server.

• The URL to access the HCL OneTest[™] Server UI.

What to do next

You can perform the following tasks:

- Configure licenses for team spaces. See Configuring licenses for team spaces on page 121.
- Configure the server software. See Configuration of the server software on page 83.

You can migrate the user data if you upgraded the server software from the earlier version to a new version.

The migration procedure is different based on the existing version of the server software. For more information about migration process, go to the following topics:

- Migrating user data on Ubuntu from 10.1.2 or earlier on page 68.
- Migrating user data on Ubuntu from 10.1.3 or later on page 69.

Related information

Helm documentation

Troubleshooting on page 1136

Installation of the server software on Azure Kubernetes Service

You can find information about the tasks that you can perform to install HCL OneTest[™] Server on the Azure Kubernetes Service (AKS) platform.

Prerequisites for installing the server software on Azure Kubernetes Service

You must complete certain tasks before you install HCL OneTest[™] Server on the Azure Kubernetes Service (AKS) platform.

The following sections describe each prerequisite in detail:

- Internet access on page 46
- Azure subscription on page 46
- Azure Kubernetes Service on page 47
- Mandatory software on page 47
- Azure resource provider on page 48

Internet access

You must have access to the internet to install HCL OneTest[™] Server.

Azure subscription

You must have an active Azure subscription along with the following Azure built-in and Azure Active Directory roles:

Categories	Roles	Go to	
Azure built-in	Owner Or	Azure built-in roles in Azure Kubernetes Service documentation.	
	Contributor and User Access Administrator		
Azure Active Directo- ry	Application Administrator	Azure AD built-in roles in Azure Kubernetes Service documentation.	

Note: You can create a subscription from Microsoft Azure if you do not have a valid subscription.

Azure Kubernetes Service

You must ensure that you select the size of the virtual machine as *Standard_D8ds_v4* while setting up the AKS cluster, if you plan to disable the test authoring feature.

The default status of the test authoring feature is enabled when you install HCL OneTest[™] Server on AKS. If you plan to use the test authoring feature, then you must set up the AKS cluster with Kubernetes and ensure that you confirm the maximum number of nodes that are available in your quota of Azure subscription to configure the size of the node pool while setting up the AKS cluster.

For more information about specific versions of software requirements, see System Requirements on page 13.

For more information about Azure Kubernetes Service and deployment options, refer to Azure Kubernetes Service documentation.

Mandatory software

You must install the following mandatory software:

- Git Bash 2.31.1. For more information, refer to the Git documentation.
- Helm. For more information, refer to the Helm documentation. For more information about specific versions of software requirements, see System Requirements on page 13.



Note: The Helm command must be in one of the directories in your PATH environment variable.

• Azure command-line interface (Azure CLI) 2.34.1. For more information, refer to the Azure CLI documentation.



Note: You can run the az version command to find the version and dependent libraries that are installed.

- kubectl tool 1.21. For more information, refer to the Kubernetes documentation.
- Emissary-ingress. See Installing Emissary-ingress on page 50.

• Optional: Jaeger operator. For more information, refer to Jaeger documentation.

Note: You must install Jaeger if you want to trace test logs and Jaeger-based reports after the test run is complete.

Azure resource provider

You must register an Azure resource provider so that the AKS cluster can provision to use Persistent Volumes with Azure Files for the ReadWriteOnceMany (RWX) storage class. You can run the following command to enable the storage for the RWX storage class:

az provider register -n Microsoft.Storage

For more information about Azure resource providers and types, refer to Azure Kubernetes Service documentation.

Related information Emissary-ingress

Cluster autoscaler on Azure Kubernetes Service

You can enable the cluster autoscaler feature on Azure Kubernetes Service (AKS) to manage the cost of the cluster effectively.

You can use the cluster autoscaler with multiple node pools that are enabled. Depending on your AKS setup, when the nodes are not in use, the nodes of the AKS cluster are automatically shut down to minimize the runtime costs of the AKS cluster without risking the performance of HCL OneTest[™] Server.

When you create an AKS cluster, that contains a single node pool as the default node pool. You can use the az aks node pool command to add a node pool to your existing AKS cluster. You can then use the az aks update command to enable and configure the cluster autoscaler on the node pool for the existing AKS cluster.

You can use the following commands to add a node pool and enable the cluster autoscaler on the node pool for the existing AKS cluster:

```
az aks nodepool add -g <resource_group> -n wrk0 \
    --cluster-name <aks_cluster_name> \
    --kubernetes-version <k8s_version> \
    --node-vm-size Standard_D2ds_v4 \
    --enable-cluster-autoscaler \
    --node-count 1 --min-count 1 --max-count 2 \
    --labels execution=allow editor=allow \
    --node-taints reserved=reserved:NoSchedule
az aks update \
    -g <resource_group> -n <aks_cluster_name> \
    --cluster-autoscaler-profile scale-down-unneeded-time=1m scale-down-delay-after-add=1m
```

Note: You must replace <resource_group>, <k8s_version>, and <aks_cluster_name> with the name of the resource group, the version number of Kubernetes, and the name of the AKS cluster in the command.

The preceding commands has one node that runs all the time to reduce the launch time of test editors. You can minimize the compute costs by changing -node-count to 0. The maximum size of the node pool is set to 2. Therefore, due to the resources that are requested by the test editor, you can run only two test editors concurrently.

Ż

Note: You must confirm the maximum number of nodes that are available in your quota of Azure subscription to configure the size of the node pool.

After you run the commands, you have completed the following actions:

- Added a user node pool called wrk0
- · Enabled the cluster autoscaler feature
- Updated the default values of **scale-down-unneeded-time** and **scale-down-delay-after-add** in the cluster-wide autoscaler profile to *1m*

You can add the following command in Installing the server software on Azure Kubernetes Service on page 53 when you install the server software to run test assets and to open the test editor on the created node pool:

-f hcl-onetest-server/values-dedicated-nodes.yaml

After you install the server software by enabling the cluster autoscaler feature on your AKS cluster, a new container is used only to run test assets and to open the test editor. You can run the kubectl get pods command to view the status of the pod, which is displayed as Pending.

You can describe the pod by running the kubectl describe pod <pod_name> -n <namespace> command to view a scale event when you run test assets from HCL OneTest[™] Server.

You can describe the pod by running the kubectl describe pod <pod_name> -n <namespace> command to view a scale event in the following circumstances:

- When you run test assets from HCL OneTest[™] Server.
- When you open the test editor from HCL OneTest[™] Server.

When the test asset run or editing of test assets is complete, the pod shuts down automatically. Thus, you can reduce the cost of the cluster when the node is not in use. You can then run the kubectl get nodes command to verify the number of nodes that are currently in the Ready state.

Related information

Automatically scale a cluster to meet application demands on Azure Kubernetes Service (AKS) Create and manage multiple node pools for a cluster in Azure Kubernetes Service (AKS)

Installing Emissary-ingress

You must install Emissary-ingress to terminate Transport Layer Security (TLS) and route traffic to HCL OneTest[™] Server. You can install Emissary-ingress by pulling the images from Azure Container Registry (ACR) when you do not want to pull the images from the public registries.

Before you begin

You must have completed the following tasks:

- Set up the Azure Kubernetes Service (AKS) cluster with Kubernetes. For more information, refer to Azure Kubernetes Service documentation.
- · Installed the following software:
 - Git Bash 2.31.1. For more information, refer to the Git documentation.
 - Helm. For more information, refer to the Helm documentation. For more information about specific versions of software requirements, see System Requirements on page 13.
 - Note: The Helm command must be in one of the directories in your PATH environment variable.
 - kubectl tool 1.21. For more information, refer to the Kubernetes documentation.
 - Azure command-line interface (Azure CLI) 2.34.1. For more information, refer to the Azure CLI documentation.
 - Note: You can run the az version command to find the version and dependent libraries that are installed.
- · Logged in to the AKS cluster.



Note: You can run the az login command to log in to AKS interactively.

· Subscribed to active Azure subscription.



Note: You can run the az account set --subscription {subscription_name} command to set your active subscription.

· Configured the location of your AKS cluster.

Note: You can run the az configure --defaults location={location_name} command to set the location of your AKS cluster.

Tip: You can run the following command to get the list of all the available locations: az account list-locations --query "[].{DisplayName:displayName, Name:name}" -o table

About this task

1

The following table lists the variables that you must replace with the actual value in the command.

Variables	Description
{resource_group}	The name of the resource group that you created during the creation of the AKS cluster.
{azure_cluster}	The name of the Azure cluster that you created during the creation of the AKS cluster.
{azure_container_registry}	The name of the ACR that you created during the AKS setup.
{ip_address}	The internal IP address to use with the Emissary-ingress. Note: You must ensure that the IP address is not in use within your virtual network.

1. Run the following command to configure kubectl to connect to the AKS cluster:

az aks get-credentials -g {resource_group} -n {azure_cluster}



Note: You can verify the connection to the AKS cluster by running the kubectl get nodes command that displays a list of the cluster nodes.

2. Add the Emissary-ingress repository to Helm by running the following command:

helm repo add datawire https://app.getambassador.io --force-update

3. Run the following command to know the latest version of the Emissary-ingress chart that matches the keyword *emissary-ingress*:

helm search repo emissary-ingress

4. Run the following command to list the images and move into ACR:

```
for image in $(helm template emissary-ingress --namespace emissary datawire/emissary-ingress \
--set adminService.create=false \
--set agent.enabled=false \
--set replicaCount=1 \
--set test.enabled=false \
--set image.repository=gcr.io/datawire/emissary \
--version "8.1.0" \
| sed -r -n 's/ *image: *([^"]*)/\1/p' | uniq)
do
    echo "az acr import -n {azure_container_registry} \\"
    echo " --source ${image/:*?@/@} \\"
    tag=${image/@*/}
    echo " --image ${tag#*/}"
done
```

Remember: emissary-ingress is the name of the namespace. If you created a namespace by using a different value, then you must use that value in place of the emissary-ingress in all the instances in this procedure.

Result

The terminal displays a block of commands.

- 5. Run the commands that are displayed on the terminal after you perform Step 4 on page 51 to import an image to ACR.
- 6. Run the following commands to install the Emissary-ingress by referencing the images from ACR:

```
curl -s https://app.getambassador.io/yaml/emissary/3.1.0/emissary-crds.yaml \
    sed -r -e "s/replicas: 3/replicas: 1/" \
    | sed -r -e "s#docker.io/emissaryingress#{azure_container_registry}.azurecr.io/datawire#" \
    | kubectl apply -f -
helm install emissary-ingress datawire/emissary-ingress \
    -n emissarv \
    --create-namespace \
    --set adminService.create=false \
    --set agent.enabled=false \
    --set replicaCount=1 \
    --set test.enabled=false \
    --set image.repository="{azure_container_registry}.azurecr.io/datawire/emissary" \
    --set service.annotations."service\.beta\.kubernetes\.io/azure-load-balancer-internal"=true \
    --set service.loadBalancerIP={ip_address} \
    --version "8.1.0" && \
  kubectl rollout status -n emissary deployment/emissary-ingress -w
```

7. Run the following command to verify that external-IP is assigned to Emissary-ingress:

kubectl get svc -n emissary -w emissary-ingress

Note: The status of EXTERNAL-IP is displayed as Pending for a few minutes. If the status does not change to {ip_address}, then that indicates you have a permission issue.

You can run the following command to investigate the issue:

kubectl describe svc -n emissary emissary-ingres

Results

You have installed Emissary-ingress.

What to do next

You can install the server software. See Installing the server software on Azure Kubernetes Service on page 53.

Related information

Create an ingress controller to an internal virtual network in Azure Kubernetes Service (AKS) Create an ingress controller to an internal virtual network in Azure Kubernetes Service (AKS) Emissary-ingress documentation

Installing the server software on Azure Kubernetes Service

You can install HCL OneTest[™] Server on Azure Kubernetes Service (AKS) that has a Kubernetes environment to run functional, integration, and performance tests. HCL OneTest[™] Server combines all the capabilities into a single webbased browser for testers and non-testers. The capabilities include test runs, test data, test environment, or test reports.

Before you begin

- You must have read and been familiar with additional Helm parameters. See Additional Helm parameters on page 58.
- · You must have performed the following tasks:
 - Completed the tasks provided in the Prerequisites section. See Prerequisites for installing the server software on Azure Kubernetes Service on page 46.
 - Optional: Enabled the autoscaler feature if you want a new container to be used only to run test assets and to open the test editor. See Cluster autoscaler on Azure Kubernetes Service on page 48.
 - Logged in to the AKS cluster.

Note: You can run the az login command to log in to AKS interactively.

• Subscribed to active Azure subscription.

Note: You can run the az account set --subscription {subscription_name} command to set your active subscription.

• Configured the location of your AKS cluster.



Note: You can run the az configure --defaults location={location_name} command to set the location of your AKS cluster.



Tip: You can run the following command to get the list of all the available locations:
 az account list-locations --query "[].{DisplayName:displayName, Name:name}" -o
 table

About this task

The following table lists the variables that you must replace with the actual value in the command.

Variables	Description	
{resource_group}	The name of the resource group that you created during the creation of the AKS cluster.	
{azure_cluster}	The name of the Azure cluster that you created during the creation of the AKS cluster.	
{azure_container_reg- istry}	The name of the ACR that you created during the AKS setup.	
{my-ingress-dns- name}	The Ingress name and DNS zone value that you provided during the setting up of the AKS cluster.	
	For example, if the Ingress name and DNS zone value that you provided are <code>onetest, my-org.nonprod</code> , then {my-ingress-dns-name} value must be <code>onetest.myorg.nonprod</code> .	
{my-ots}	The release name of your choice.	
	Note: The release name must consist of alphanumeric characters that are in lower- case or "-" (hyphen). The release name must also start with an alphabetic character and end with an alphanumeric character. For example, <i>my-org</i> or <i>abc-123</i> .	
{cloud-license-serv- er-id}	The ID of the License Server for the initial team space, if you want to set the license for the first time.	

Variables	Description		
	Important: When you want to upgrade the product from the previous version, you must configure the value of License Server ID from the Team Space License Con- figuration page when the installation of the server is complete.		
{password-seed}	A value of your choice for the password.		
	Important: This password seed is used to create several default passwords for the server. You must store the password seed securely. When you install the server software by using the backup of the user data, you can reuse the password seed. You can use this seed to restore the backed-up files either on the current or later versions of the server software.		
{ip_address}.nip.io	The IP address that is assigned to Emissary-ingress.		
	You can run the following command to obtain the IP address of Emissary-ingress:		
	kubectl get ingress -A		

Remember: The test-system is the name of the namespace. If you created a namespace by using a different value, then you must use that value in place of test-system in all the instances in this procedure.

HCL OneTest[™] Server provides you with the test authoring capability, which utilizes a containerized version of the HCL OneTest[™] Studio desktop authoring tools.

Note: By design, the test authoring feature provides you with the capability to author tests that include writing code, executing code, and accessing the shell. The container in Kubernetes that is used by the test authoring or editing feature does not run as root and the container is not privileged. Hence, it results in providing some protection to the host and other workloads that run on the same node.

You must not install the test authoring feature in the following scenarios:

- If you administer a network policy for your server installation.
- If you do not intend to use the test authoring feature.
- 1. Add the software registry to Helm by running the following command:

helm repo add hclsoftware https://hclcr.io/chartrepo/ot

2. Run the following command to get the latest updates from the repository:

helm repo update

3. Run the following commands to fetch the scripts that are used to install HCL OneTest[™] Server:

```
helm pull --untar hclsoftware/hcl-onetest-server --version 9.1050.0
chmod +x hcl-onetest-server/files/*.sh
```

4. Run the following command to configure kubectl to connect to the AKS cluster:


```
az aks get-credentials -g {resource_group} -n {azure_cluster}
```



Note: You can verify the connection to the AKS cluster by running the kubectl get nodes command that displays a list of the cluster nodes.

5. Run the following script from the hcl-onetest-server/files directory to pull the images of HCL OneTest[™] Server from the Harbor repository to ACR:

bash hcl-onetest-server/files/move-images.sh {azure_container_registry}.azurecr.io/hcl-onetest hclcr.io/ot/hcl-onetest



```
az acr repository list -n {azure_container_registry} -otsv
az acr repository show-manifests -n {azure_container_registry} --repository \
$(az acr repository list -n {azure_container_registry} -otsv --query [0])
```

6. Create a namespace in which you want to install the server software by running the following command:

kubectl create namespace test-system

- 7. Perform one of the following steps to enable Certificate Authority (CA) as trusted certificates and to create an ingress Secret:
 - a. Run the following script from the hcl-onetest-server/files directory if your endpoints can resolve Azure private DNS zones:

hcl-onetest-server/files/certificate.sh -n test-system -s ingress {my-ingress-dns-name}

b. Run the following script from the hcl-onetest-server/files directory if your endpoints cannot resolve Azure private DNS zones:

hcl-onetest-server/files/certificate.sh -n test-system -s ingress {ip_address}.nip.io

8. Run the following command to install the server software:

The following command installs the server software by referencing the images from ACR. Thereby, HCL OneTest[™] Server can provide better performance.



- · If you enabled the autoscaler feature to use a new container only to run test assets and to open the test editor, then you must add -f hcl-onetest-server/values-dedicated-nodes.yaml in any of the following helm install commands.
- To provide enhanced security to HCL OneTest[™] Server, the Sign up link on the Login page of HCL OneTest[™] Server is not visible when you install the server software.

If you want to enable the Sign up link on the Login page, then you must add the --set keycloak.signup.enabled=true parameter in the following helm install command.

```
helm install {my-ots} ./hcl-onetest-server -n test-system \
-f hcl-onetest-server/values-k8s.yaml \
--set global.persistence.rwxStorageClass=azurefile \
--set global.hclOneTestIngressDomain={my-ingress-dns-name} \
--set global.hclFlexnetURL=https://hclsoftware.compliance.flexnetoperations.com \
--set global.hclFlexnetID={cloud-license-server-id} \
--set global.hclOneTestRegistry=<azure_container_registry>.azurecr.io/hcl-onetest \
--set global.hclOneTestPasswordAutoGenSeed={password-seed}
```

9. Run the following script from the hcl-onetest-server/files directory to verify and test the installed server software:

hcl-onetest-server/files/helm-test-diag.sh {my-ots} -n test-system

Results

You have installed the server software. The terminal displays the following information:

• The URL to access Keycloak to manage and authenticate users.

The user name can be keycloak and the password can be retrieved by running the following command:

```
kubectl get secret -n test-system {my-ots}-keycloak-postgresql -o jsonpath="{.data.password}" |
base64 --decode; echo
```

Where:

- {my-ots} is the name of the release that was provided during the installation of the server software.
- test-system is the name of the namespace that you created during the installation of the server software.
- The URL to access the HCL OneTest[™] Server UI.

What to do next

You can perform the following tasks:

- Configure licenses for team spaces. See Configuring licenses for team spaces on page 121.
- Configure the server software. See Configuration of the server software on page 83.

Related information

Helm documentation Azure Kubernetes Service documentation

Management of server features

After you install the server software, you can manage certain features based on your requirements.

You can author or edit test assets in HCL OneTest[™] Server by using the test authoring feature. Depending on the platform that you used to install the server software, the default status of the test authoring feature is enabled or disabled.

During the installation of the server software, if you did not use any Helm parameters, you can still use those parameters even after installation is complete.

You can use the helm upgrade command to enable or disable server features after the installation of HCL OneTest[™] Server is complete.

The default status of the test authoring feature is disabled when you install the server software on Ubuntu (by using k3s). However, the default status of the test authoring feature is enabled when you install the server software on Azure Kubernetes Service (AKS).

For example, if you want to enable only the test authoring feature by retaining the values of other parameters that you used during the installation, you can run the following command after the installation is complete:

```
helm upgrade {my-ots} -n {namespace} ./hcl-onetest-server \
--reuse-values \
--set global.hclOneTestAuthorEnabled=true
```

Note: You must substitute {my-ots} and {namespace} with the name of the release and namespace that you provided during the installation of the server software.

Similarly, you can use the other additional Helm parameters to enable or disable features based on your requirements. See Additional Helm parameters on page 58.

Additional Helm parameters

You can find the information about Helm parameters that you can use during the installation of HCL OneTest[™] Server.

As a system administrator when you install or upgrade HCL OneTest[™] Server, you can pass values for some of the individual parameters by using --set. The following table lists such parameters that you can use while running the helm install or helm upgrade command to enable or disable certain features in HCL OneTest[™] Server.

Parameters	Values	Description
keycloak.signup- .enabled	true false	Use this parameter to show or hide the Sign-Up link on the HCL OneTest™ Server Login page.
		The default value of the keycloak.signup.enabled parameter is set to false to enhance the security of HCL OneTest [™] Server.
		Note: You can use this parameter only during the installation of the server software.
		If you have administrator access to Keycloak, then you can also enable the self-registration by using the Keycloak UI after the installation of HCL OneTest [™] Server is complete. For more information, refer to the Keycloak documentation.
global. hclOneTestAu-	true false	Use this parameter to enable or disable the test authoring feature in HCL OneTest™ Server.
thorEnabled		The default status of the test authoring feature is disabled when you install HCL OneTest [™] Server on Ubuntu (by using k3s). Therefore, the value of the global.hclOneTestAuthorEnabled parameter is set to false.
		The default status of the test authoring feature is enabled when you install HCL OneTest [™] Server on Azure Kubernetes Service. Therefore, the value of the global.hclOneTestAuthorEnabled parameter is set to true.
		For example,
		set global.hclOneTestAuthorEnabled=true
		set global.hclOneTestAuthorEnabled=false
Origin	IP address or do- main name of other servers.	Use this parameter to integrate call requests from other web servers to HCL OneTest [™] Server.
	other servers.	The default configuration of HCL OneTest [™] Server rejects all Cross-origin re- source sharing (CORS). Therefore, you must use the gateway.allowedOrigin parameter to restrict CORS to a specific whitelist.
		For example,
		set gateway.allowedOrigin=http://http.example.com:*,https:// https.mydomain.net:*

Parameters	Values	Description
		Where, http.example.com and https.mydomain.net are the domains that you want to provide access to HCL OneTest [™] Server.
		You can also provide the value of gateway.allowedOrigin as the IP address when you cannot resolve a specific Domain Name Server (DNS). If your do- main can be accessible through IP address on a specific port, then you can provide the value of gateway.allowedOrigin as follows:
		<pre>set gateway.allowedOrigin=*://ip-address:*,*://ip-address:port_number</pre>
		For example,
		set gateway.allowed0rigin="*://192.0.2.0:*"
		set gateway.allowedOrigin="*://192.0.2.1:3000"
		Note: You can provide multiple domain names or IP addresses separated by a comma (,).
networkPoli- cy.egress.en- abled	true	Set this parameter value to true to restrict traffic from HCL OneTest [™] Server to private IP addresses.
		The default configuration of HCL OneTest [™] Server does not create any Egress policy to restrict the other endpoints that can connect with HCL OneTest [™] Server. Therefore, you must use the networkPolicy.egress.enabled parameter to enable the Egress policy that can restrict traffic to private IP addresses.
		For example,
		set networkPolicy.egress.enabled=true
		You can inspect the deployed policy by running the following command:
		<pre>kubectl get networkpolicy -n {namespace} {my-ots}-allow-egress -oyaml</pre>
		Note: You must substitute {namespace} with the name of the name- space and {my-ots} with the release name that you used during the installation of the server software.
execution.tem- plate.	<size_of_memo- ry>Gi</size_of_memo- 	Use this parameter to run VU schedules that contain multiple Web UI tests or a large number of virtual users or a combination of Web UI, performance,

Parameters	Values	Description
resources.limits- .memory		The default value of the execution.template.resources.limits.memory para- meter is set to 3Gi.
		For example, set execution.template.resources.limits.memory=5Gi

Related information

Installing the server software on Ubuntu by using k3s on page 42 Installing the server software on Azure Kubernetes Service on page 53 Management of server features on page 58

Server software upgrade methods

When you want to use the enhanced functionalities of HCL OneTest[™] Server, you must upgrade HCL OneTest[™] Server to the latest version.

You can upgrade the server software by using following methods:

- **In-place upgrade:** In this method, you can upgrade the server software in the same location that contained 10.1.3 or later version of the server software by using the helm upgrade command.
- Upgrade (by new install): In this method, you can upgrade the server software by uninstalling the existing version of HCL OneTest[™] Server, and then by installing the latest version of the server software.
- Important: On the Ubuntu platform, the In-place upgrade method is not available. You must use the Upgrade (by new install) method to upgrade the server software.

The upgrade procedures are different based on the existing version of the software. To learn more about server software upgrade methods on platforms such as Ubuntu and Azure Kubernetes Service (AKS), refer to the following topics:

Server software upgrade on Ubuntu

When you want to use the latest version of the server software on Ubuntu, you must upgrade HCL OneTest[™] Server from the previous version of the software.

Before you upgrade the server software, you must ensure that you have completed the following tasks:

- Installed Helm. For more information, refer to the Helm documentation.
- Completed all test executions that are running on the existing version of HCL OneTest[™] Server.

- Stopped all stub executions that are running on the existing version of HCL OneTest[™] Server.
- Canceled any scheduled test runs that have a future date or time.
- Informed users that HCL OneTest[™] Server is offline temporarily during the upgrade process.

For more information about specific versions of software requirements, see System Requirements on page 13.

In upgrade (by new install) method, depending on the existing version of the software, you can upgrade the server software by using any of the following options.

To upgrade HCL OneTest[™] Server (10.1.0 or later) to latest version, you must perform these tasks in sequence as listed in the following table:

Tasks	Task description	More information
1	Back up the user data from the previous version of HCL OneTest [™] Server.	 For 10.1.0 or 10.1.1, refer to Backing up user data. For 10.1.2 or later, refer to Back- ing up user data.
2	Uninstall the previous version of HCL OneTest™ Server in- cluding entire Kubernetes environment.	Uninstalling the server software from Ubuntu on page 81
3	Set up the Kubernetes environment (k3s) by using the provid- ed script.	Setting up a Kubernetes environment (k3s) on Ubuntu on page 39
4	Install the latest version of the server software.	Installing the server software on Ubuntu by using k3s on page 42
5	Migrate the user data after the installation is complete.	Migrating user data on Ubuntu from 10.1.2 or earlier on page 68
		Or Migrating user data on Ubuntu from 10.1.3 or later on page 69

If your existing version of server software is 10.0.2, Fix Pack 1, or earlier, then you cannot directly upgrade to the latest version of the server software due to the steps involved in the migration process. Therefore, you must perform the tasks in sequence as listed in the following table:

Tasks	Task description	More information
1	Upgrade HCL OneTest™ Server 10.1.2.	Installation of the server software on
		Ubuntu

62

Tasks	Task description	More information
2	Back up the user data from HCL OneTest [™] Server 10.1.2.	Backing up user data - 10.1.2
3	Uninstall HCL OneTest [™] Server 10.1.2 including entire Kuber- netes environment.	Uninstalling the server software
4	Install the latest version of the server software.	Installing the server software on Ubuntu by using k3s on page 42
5	Migrate the user data after the installation is complete.	Migrating user data on Ubuntu from 10.1.2 or earlier on page 68

Upgrading the server software on Azure Kubernetes Service

When you want to use the latest version of the server software on Azure Kubernetes Service (AKS), you must upgrade HCL OneTest[™] Server from the previous version of the software.

Before you begin

- You must have read and been familiar with additional Helm parameters. See Additional Helm parameters on page 58.
- You must have completed the following tasks:
 - Completed the tasks provided in the Prerequisites section. See Prerequisites for installing the server software on Azure Kubernetes Service on page 46.
 - Uninstalled NGINX Ingress controller. For more information refer to the NGINX Ingress Controller documentation.
 - Note: To install HCL OneTest[™] Server 10.2.2 or earlier on AKS, you installed the NGINX as Ingress controller. From 10.2.3 the Ingress controller has been changed to Emissary-ingress. Therefore, you must uninstall the NGINX Ingress controller.
 - Installed Emissary-ingress. See Installing Emissary-ingress on page 50.
 - ∘ Informed users that HCL OneTest[™] Server is offline temporarily during the upgrade process.
 - ∘ Completed all test executions that are running on the existing version of HCL OneTest[™] Server.
 - ∘ Stopped all stub executions that are running on the existing version of HCL OneTest[™] Server.
 - Canceled any scheduled test runs that have a future date or time.
 - $\,{}^{\circ}$ Logged in to the AKS cluster.

Note: You can run the az login command to log in to AKS interactively.

• Subscribed to active Azure subscription.



Note: You can run the az account set --subscription {subscription_name} command to set your active subscription.

Optional. You can back up the user data from the earlier version of the product. If the upgrade fails, then you can use that backup file to restore it to the latest version of the server software. See Backing up the server data on Azure Kubernetes Service on page 79.

Note: For more information about specific versions of software requirements, see System Requirements on page 13.

About this task

When you want to install the latest version of the server software in the same location that contained the 10.2.0 or later, then you can upgrade HCL OneTest[™] Server by using the helm upgrade command.

Variables	Description	
{resource_group}	The name of the resource group that you created during the creation of the AKS cluster.	
{azure_cluster}	The name of the Azure cluster that you created during the creation of the AKS cluster.	
{azure_container_reg- istry}	The name of the ACR that you created during the AKS setup.	
{my-ingress-dns- name}	The Ingress name and DNS zone value that you provided during the setting up of the AKS cluster. For example, if the Ingress name and DNS zone value that you provided are onetest, my- org.nonprod, then {my-ingress-dns-name} value must be onetest.myorg.nonprod.	
{my-ots}	The release name that you provided during the installation of the server software.	

The following table lists the variables that you must replace with the actual value in the command.

Remember: The test-system is the name of the namespace that you created during the installation of the server software. If you created a namespace by using a different value, then you must use that value in place of test-system in all the instances in this procedure.

Tip: You can run the following command to know the value of the variables that you used during the installation of the previous version of the server software:

helm get values {release_name} -n {namespace}

For example, if your name of the release is my-ots and the name of the namespace is testsystem, then you must run the command as follows:

helm get values my-ots -n testsystem

1. Add the software registry to Helm by running the following command:

helm repo add hclsoftware https://hclcr.io/chartrepo/ot

Run the following command to get the latest updates from the repository:

helm repo update

3. Run the following commands to fetch the scripts that are used to install HCL OneTest[™] Server:

```
helm pull --untar hclsoftware/hcl-onetest-server --version 9.1050.0
chmod +x hcl-onetest-server/files/*.sh
```

4. Run the following command to configure kubectl to connect to the AKS cluster:

az aks get-credentials -g {resource_group} -n {azure_cluster}



Note: You can verify the connection to the AKS cluster by running the kubectl get nodes command that displays a list of the cluster nodes.

5. Run the following script from the hcl-onetest-server/files directory to pull the images of HCL OneTest[™] Server from the Harbor repository to ACR:

bash hcl-onetest-server/files/move-images.sh {azure_container_registry}.azurecr.io/hcl-onetest hclcr.io/ot/hcl-onetest



Tip: You can verify that multiple manifests are associated with the image in the ACR by running the following commands:

```
az acr repository list -n {azure_container_registry} -otsv
az acr repository show-manifests -n {azure_container_registry} --repository \
$(az acr repository list -n {azure_container_registry} -otsv --query [0])
```

6. Run the helm list -A command to list all releases that are deployed across all namespaces.

7. Run the following command to upgrade the server software:

```
helm upgrade {my-ots} ./hcl-onetest-server -n test-system \
-f hcl-onetest-server/values-k8s.yaml \
--set global.persistence.rwxStorageClass=azurefile \
--set global.hclOneTestIngressDomain={my-ingress-dns-name} \
--set global.hclOneTestRegistry={azure_container_registry}.azurecr.io/hcl-onetest \
--set global.hclOneTestPasswordAutoGenSeed={password-seed}
```



Note: The following command upgrades the server software by referencing the images from ACR. Therefore, HCL OneTest[™] Server can provide better performance.

8. Run the following script from the hcl-onetest-server/files directory to verify and test the installed server software:

hcl-onetest-server/files/helm-test-diag.sh {my-ots} -n test-system

Results

On the successful upgrade of HCL OneTest[™] Server, the output displays the following information:

- Keycloak URL to manage and authenticate users.
- A URL to access the HCL OneTest[™] Server UI.

What to do next

- Configure licenses for team spaces. See Configuring licenses for team spaces on page 121.
- Configure the server software. See Configuration of the server software on page 83.

Migration of user data

You can find information about the migration limitations and methods when you want to migrate data such as projects, test resources, configuration details of integrated applications, and so on. You can migrate data that is generated in an earlier version of HCL OneTest[™] Server after you upgrade to or install the latest version, and then use that data in the latest version.

Limitations for user data migration

Before you can decide on the migration method for the version of HCL OneTest[™] Server, you must review the limitations that apply to the migrated data.

Migrat- ing from	Migrating to	Limitation	The workaround, if available	
10.2.3	10.5.0	If you configured IBM® Engineering Test Management on HCL OneTest™	You must reconfigure IBM® Engineer- ing Test Management as a quality man-	

Table 2. Migration limitations

Migrat- ing from	Migrating to	Limitation	The workaround, if available
		Server 10.2.3, the information about En- gineering Test Management is not vis- ible after you migrate HCL OneTest [™] Server from 10.2.3 to 10.5.0 or later.	agement solution in the latest version of HCL OneTest™ Server.
10.2.3	10.5.0	If you configured Jira on HCL OneTest [™] Server 10.2.3, the information about Ji- ra is not visible after you migrate HCL OneTest [™] Server from 10.2.3 to 10.5.0 or later.	You must reconfigure Jira as a change management system in the latest ver- sion of HCL OneTest [™] Server.
10.2.3 or earli- er	10.5.0	You cannot migrate edited test assets that were created in HCL OneTest [™] Server 10.2.3 or earlier, to HCL OneTest [™] Server 10.5.0 or later.	You might have to open and edit the test assets in the latest version of HCL OneTest [™] Server.
10.2.0	10.2.1 or later	If you edited test assets in your project on HCL OneTest [™] Server 10.2.0 and mi- grated them, then the values displayed in the Last Changed By field might be in- correct for the edited test assets.	

Table 2. Migration limitations (continued)

Migration methods

The data that is generated in HCL OneTest[™] Server can be migrated and used in a later version of HCL OneTest[™] Server with except for the limitations detailed in Table 2: Migration limitations on page 66.

You can refer to the following table to know the details of the migration when you want to upgrade to the latest HCL OneTest[™] Server version:

OS / Plat-	Server	Upgrade	Migration method
form	version	method	
Ubuntu	10.1.3 or lat- er	Upgrade by new install	When you upgrade the server software by uninstalling the existing ver- sion, and installing the required version of HCL OneTest [™] Server, then you must perform the migration task after the installation of the server software is complete.

Table 3. Migration method used during an upgrade

OS / Plat- form	Server version	Upgrade method	Migration method
	10.1.2 or earlier		For more information about the migration process, see Migrating user data on Ubuntu from 10.1.3 or later on page 69 or Migrating user da- ta on Ubuntu from 10.1.2 or earlier on page 68.
Azure Kuber- netes Ser- vice	10.2.3 or lat- er	In-place up- grade	When you upgrade the software by using the helm upgrade command, the migration of user data takes place during the upgrade process.

Table 3. Migration method used during an upgrade (continued)

Migrating user data on Ubuntu from 10.1.2 or earlier

When you want to use the data, which was in your earlier version, in a new version of HCL OneTest[™] Server, you can migrate those user data.

Before you begin

You must have upgraded HCL OneTest[™] Server to a new version.

About this task

The following table lists the variables that you must replace with the actual value in the command.

Variables	Description
{my-ots}	The name of the release that you provided during the installation of the server software.
{backup-release}	The Helm release name of the server where you store the backup data.
{target-release}	The Helm release name of the server where you want to restore the data.

Remember: The test-system is the name of the namespace that you created during the installation of the server software. If you created a namespace by using a different value, then you must use that value in place of test-system in all the instances in this procedure.

1. Run the following script from the hcl-onetest-server/files directory to create a directory that contains metadata related to the Persistent Volume Claims and their Persistent Volumes:

migrate.sh create-pvcs -n test-system {my-ots}

2. Run the following script from the hcl-onetest-base directory to back up the data:

sudo backup.sh create-pvc-links -v ~/migration-pvc-links

3. Run the following command to stop the cluster and HCL OneTest[™] Server:

k3s-killall.sh

4. Run the following script from the hcl-onetest-base directory to restore the backed-up data:

sudo backup.sh restore -v ~/migration-pvc-links --release {backup-release}:{target-release}
{backup-file-name}

5. Run the following command to restart Kubernetes and to start HCL OneTest[™] Server:

sudo systemctl start k3s

6. Run the following script from the hcl-onetest-server/files directory to merge the data into the server:

migrate.sh merge-dbs -n test-system {my-ots}

7. Run the following command to remove the resources that were created during the migration process:

migrate.sh delete-temp-resources -n test-system {my-ots}

8. Run the following script from the hcl-onetest-server/files directory to verify and test the installed server software:

hcl-onetest-server/files/helm-test-diag.sh {my-ots} -n test-system

Results

You have migrated the user data from the earlier version to the new version.

What to do next

You can perform the following tasks:

- Configure licenses for team spaces. See Configuring licenses for team spaces on page 121.
- Configure the server software. See Configuration of the server software on page 83.

Migrating user data on Ubuntu from 10.1.3 or later

When you want to use the data, which was in your earlier version, in a new version of HCL OneTest[™] Server, you can migrate those user data..

Before you begin

You must have upgraded HCL OneTest[™] Server to a new version.

About this task

The following table lists the variables that you must replace with the actual value in the command.

Variables	Description
{my-ots}	The name of the release that you provided during the installation of the server software.

Variables	Description
{backup-release}	The Helm release name of the server where you store the backup data.
{target-release}	The Helm release name of the server where you want to restore the data.

The test-system is the name of the namespace that is created during the setting up of the k3s environment.

1. Run the following script from the hcl-onetest-base directory to create a directory that contains metadata related to the Persistent Volume Claims and their Persistent Volumes:

sudo backup.sh create-pvc-links

- 2. Stop the Kubernetes cluster by running the k3s-killall.sh command.
- 3. Restore the backed-up user data by running the following commands:

sudo ./backup.sh restore [options] {backup-file-name}

You can use the following parameters along with the restore command:

-namespace or -n: Use this parameter to restore a specific namespace from the backup file. If you do
not mention the namespace, then volumes from all the namespaces in the backup file are restored.
 You can map one namespace to another namespace by using a colon (:). The syntax is:

--namespace <name of the namespace> [:<target-namespace>]

 -release or -r: Use this parameter if the Helm release name of the server to which the backup is being restored is different than the Helm release name of the server where the backup was taken. The syntax is:

--release <backup-release>:<target-release>

• -volumes or -v: Use this parameter to specify the directory path of the volumes. The syntax is:

--volumes <path-of-the-directory>

- -k or --confirm: Use this parameter to skip the confirmation step.
- 4. Restart the Kubernetes cluster by running the systemctl start k3s command to start HCL OneTest[™] Server.
- 5. Run the following script from the hcl-onetest-server/files directory to create all the missing databases:

migrate.sh create-missing-dbs {my-ots}

- **Note:** You can expect the output of the command to contain several errors on objects that already exist. They do not indicate a problem with the execution of the script.
- 6. Run the following script from the hcl-onetest-server/files directory to verify and test the installed server software:

hcl-onetest-server/files/helm-test-diag.sh {my-ots} -n test-system

Results

You have migrated the user data from the earlier version to the new version.

What to do next

You can perform the following tasks:

- Configure licenses for team spaces. See Configuring licenses for team spaces on page 121.
- Configure the server software. See Configuration of the server software on page 83.

Backup and restoration of the server data

You must back up all your server data before you uninstall the current version of the server software or upgrade to the latest version of the server software. You must back up the server data to avoid data loss or inaccessibility of data.

A backup is the process of creating a copy of the data on your system and storing it elsewhere, generally on secondary storage. You can then use that copy to recover if your original data is lost or becomes inaccessible.

A restore is a process of copying the backed-up data from the secondary storage and restoring it to the original location. You can restore the backed-up data when your original data is lost or becomes inaccessible.

You must back up and restore the data when you perform the following tasks:

- · Move the existing environment to a new system.
- Change the name of the release or namespace that you used during the installation of the server software.
- Minimize the downtime of HCL OneTest[™] Server during disaster recovery.
- Upgrade to the latest version of the server software.

To learn more about backup and restoration of the server data on platforms such as Ubuntu and Azure Kubernetes Service (AKS), refer to the following topics:

- Backup and restoration of the server data on Ubuntu on page 72
- Backup and restoration of the server data on Azure Kubernetes Service on page 76

Backup and restoration of the server data on Ubuntu

To secure the data of HCL OneTest[™] Server that is installed on the Ubuntu server, you can back up the data. At any point in time, after you install HCL OneTest[™] Server, you can restore the backed-up data.

Backing up the server data on Ubuntu

When you want to upgrade to a new version of the server software or to move your existing environments to new systems, you must back up the server data.

Before you begin

You must have completed the following tasks:

- · Been assigned the same role that was required to install and uninstall the server software.
- Been granted with the sudo access.
- Installed the server software and all of the HCL OneTest[™] Server pods are in Running state.
- Communicated to the users that HCL OneTest[™] Server might be unavailable for some time until the process is complete.
- 1. Log in to the Ubuntu server and open a terminal.
- 2. Add the software registry to Helm by running the following command:

helm repo add hclsoftware https://hclcr.io/chartrepo/ot

3. Run the following command to extract the base:

helm pull --untar hclsoftware/hcl-onetest-base --version 9.1050.0

4. Change to the hcl-onetest-base directory.

This directory contains the backup.sh script which is required to complete the backup operation.

5. Create a directory that contains metadata related to the Persistent Volume Claims and their Persistent Volumes by running the following command:

sudo ./backup.sh create-pvc-links

You can use the following optional parameter along with the create-pvc-links command:

--volumes or -v: Use this parameter to specify the directory path of the Volumes.

For example, backup.sh create-pvc-links -v hcl-onetest-base/my-pvc-links creates a directory called mypvc-links that stores the metadata required for backup.



4

- If you did not provide the volume parameter, by default, the command creates a sub-directory in the same directory where you have the backup script.
- You must ensure that the directory you create must be empty or not exist to avoid script failure.
- If you specify a directory by using the -v parameter, then you must use the same parameter value when you restore the data.
- 6. Run the following command to stop the cluster and HCL OneTest[™] Server:

k3s-killall.sh

7. Run the following command to create a backup of the existing user data:

sudo ./backup.sh create [options] <backup-file-name>

After you run this command, a backup of the local Persistent Volumes is created. The backup is created as tar archives that is compressed by using gzip (.tar.gz). The **create** command archives the Persistent Volumes into the *<backup-file-name>*.

You can use the following parameters along with the create command:

-namespace or -n: Use this parameter to back up the Persistent Volumes in the specified namespace.
 If you do not mention the namespace, then all the Volumes from all the namespaces are included in the backup. The syntax is:

-namespace <name of the namespace>

• -volumes or -v: Use this parameter to specify the directory path of the Volumes. The syntax is:

-volumes <path-of-the-directory>

Remember:

- If you did not provide the volume parameter, by default, the command creates a subdirectory in the same directory where you have the backup script.
- If you specify a directory by using the -v parameter, then you must use the same parameter value when you restore the data.

For example,

sudo ./backup.sh create --namespace test-system my-backup.tar.gz

This command creates a backup file named *my-backup.tar.gz* that contains all of the Persistent Volumes associated with pods available in the *test-system* namespace.

8. Run the following command to restart the cluster and HCL OneTest[™] Server:

sudo systemctl start k3s

Results

You have backed up the data of HCL OneTest[™] Server.

Restoring the server data on Ubuntu

You can restore the data that is backed up in HCL OneTest[™] Server at any point in time after you install latest version of server software.

Before you begin

You must have completed the following tasks:

- Been assigned the same role that was required to install and uninstall the server software.
- Been granted with the sudo access.
- Communicated to the users that HCL OneTest[™] Server might be unavailable for some time until the process is complete.
- Backed up the data from HCL OneTest[™] Server.

About this task

The following procedure is for the restoration of the server data from the current release. If you are upgrading the server software, then you can restore the server data from the earlier version to the latest version during the installation of the server software. For more information, see the **Related information** section.

- 1. Log in to the Ubuntu server and open a terminal.
- 2. Add the software registry to Helm by running the following command:

helm repo add hclsoftware https://hclcr.io/chartrepo/ot

3. Run the following command to extract the base:

helm pull --untar hclsoftware/hcl-onetest-base --version 9.1050.0

4. Change to the hcl-onetest-base directory.

This directory contains the backup.sh script which is required to complete the restore operation.

5. Create a directory that contains metadata related to the Persistent Volume Claims and their Persistent Volumes by running the following command if you have not done before:

sudo ./backup.sh create-pvc-links

You can use the following optional parameter along with the create-pvc-links command:

--volumes or -v: Use this parameter to specify the directory path of the Volumes.

For example, backup.sh create-pvc-links -v hcl-onetest-base/my-pvc-links creates a directory called mypvc-links that stores the metadata required to restore your user data.

Remember:

- If you did not provide the volume parameter, by default, the command creates a sub-directory in the same directory where you have the backup script.
- You must ensure that the directory you create must be empty or not exist to avoid script failure.
- 6. Run the following command to stop the cluster and HCL OneTest[™] Server:

k3s-killall.sh

7. Run the following command to restore the backed-up user data:

sudo ./backup.sh restore [options] <backup-file-name>

The restore command overwrites the existing Persistent Volumes with data from the <backup-file-name>.

You can use the following parameters along with the restore command:

-namespace or -n: Use this parameter to restore a specific namespace from the backup file. If you do
not mention the namespace, then volumes from all the namespaces in the backup file are restored.
 You can map one namespace to another namespace by using a colon (:). The syntax is:

--namespace <name of the namespace> [:<target-namespace>]

 -release or -r: Use this parameter if the Helm release name of the server to which the backup is being restored is different than the Helm release name of the server where the backup was taken. The syntax is:

--release <backup-release>:<target-release>

• -volumes or -v: Use this parameter to specify the directory path of the volumes. The syntax is:

--volumes <path-of-the-directory>

• -k or --confirm: Use this parameter to skip the confirmation step.

For example,

```
sudo ./backup.sh restore --namespace test-system:new-test-system -r rel-1:rel-2 -k
my-backup.tar.gz
```

This command restores the volumes that are backed up from the *rel-1* release in the *test-system* namespace to the *rel-2* release in the *new-test-system* namespace and skips the confirmation step.

8. Run the following command to restart the cluster and HCL OneTest[™] Server:

sudo systemctl start k3s





- The cluster and HCL OneTest[™] Server might take some time to restart and until that time, you cannot access the HCL OneTest[™] Server URL.
- You can run the *kubectl get pods* -A command to verify that the Kubernetes environment is working. After a while, the status of the pods must be *Running* state.

Results

You have restored the data of HCL OneTest[™] Server.

Related information

Server software upgrade on Ubuntu on page 61

Backup and restoration of the server data on Azure Kubernetes Service

To secure the data in HCL OneTest[™] Server that is installed on Azure Kubernetes Service (AKS), you can back up the data. At any point in time, after you install HCL OneTest[™] Server, you can restore the backed-up data.



Attention: The instructions provided are an example of how an AKS cluster can be configured to use Velero for backing up and restoring the HCL OneTest[™] Server data. The procedures to backup and restore the server data might be not valid in all the scenarios.

You must refer to the Velero and Azure Kubernetes Service documentation to identify how you can configure Velero in your AKS cluster based on your existing AKS setup to backup and restore the HCL OneTest[™] Server data.

- Velero Documentation
- AKS Documentation

Preparing the Azure Kubernetes Service cluster to back up the server data

When you want to back up the server data, you must prepare your Azure Kubernetes Service (AKS) cluster to store the backed-up data.

Before you begin

You must have completed the following tasks:

 Created an Azure subscription along with an Owner or Contributor and User-Access Administrator role on the Azure subscription.

You can create a subscription from Microsoft Azure if you do not have a valid subscription.

• Downloaded the Velero 1.5.3 plugin for Microsoft Azure from the Velero repository.

CAUTION: The instructions provided in this procedure are an example of how an AKS cluster can be configured to use Velero 1.5.3 Microsoft Azure plugin for backing up and restoring the HCL OneTest[™] Server data. The procedures to backup and restore the server data might be not valid in all the scenarios.

- Copied the Velero executable file into one of the directories in the PATH environment variable.
- Installed Azure Command-Line Interface (CLI). For more information, refer to the Azure CLI documentation.

About this task

Velero is one of the tools that is available to back up and restore the server data. You must prepare your AKS cluster where you installed HCL OneTest[™] Server before you back up the data by using Velero.

1. Run the following command to log in to AKS interactively:

az login

Result

The command-line interface opens a browser and displays the Log-in page of AKS.

- 2. Sign in with your AKS account credentials.
- 3. Run the following command to set your active subscription:

az account set --subscription <subscription_name>

You must replace subscription_name> with the name of your active Azure subscription.

4. Run the following command to set the location of your AKS cluster:

```
az configure --defaults location=<location_name>
```

For example, az configure --defaults location=eastus2



Tip: You can run the following command to get the list of all the available locations:

az account list-locations --query "[].{DisplayName:displayName, Name:name}" -o table

Run the following commands to create a storage account within the AKS cluster for the Velero to store the backup files:

```
AZURE_BACKUP_SUBSCRIPTION_NAME=<subscription_name>
AZURE_BACKUP_SUBSCRIPTION_ID=$(az account list
        --query="[?name=='$AZURE_BACKUP_SUBSCRIPTION_NAME'].id | [0]" -o tsv)
AZURE_BACKUP_RESOURCE_GROUP=Velero_Backups
az group create -n $AZURE_BACKUP_RESOURCE_GROUP --location <location_name>
AZURE_STORAGE_ACCOUNT_ID="velero$(date -u +%s)"
az storage account create \
```

```
--name $AZURE_STORAGE_ACCOUNT_ID \
--resource-group $AZURE_BACKUP_RESOURCE_GROUP \
--sku Standard_GRS \
--encryption-services blob \
--https-only true \
--kind BlobStorage \
--access-tier Hot
```



Note: You must replace subscription_name> and <location_name> with the name of your active Azure
subscription and location of the AKS cluster.

6. Run the following command to create a container within the storage account to store the backup files:

```
AZURE_BLOB_CONTAINER=velero
az storage container create -n $AZURE_BLOB_CONTAINER --public-access off --account-name
$AZURE_STORAGE_ACCOUNT_ID
```

7. Run the following commands to obtain a key of Azure storage account and to create a file that contains all the relevant environment variables:

```
AZURE_STORAGE_ACCOUNT_ACCESS_KEY=$(az storage account keys list \
--account-name $AZURE_STORAGE_ACCOUNT_ID \
--query "[?keyName == 'key1'].value" -o tsv)
cat << EOF > ./credentials-velero
AZURE_STORAGE_ACCOUNT_ACCESS_KEY=${AZURE_STORAGE_ACCOUNT_ACCESS_KEY}
AZURE_CLOUD_NAME=AzurePublicCloud
EOF
```



Note: There are several ways Velero can authenticate to Azure. This procedure is based on using a storage account access key. The available values for Azure_CLOUD_NAME in the Storage account access key method are AzurePublicCloud, AzureUSGovernmentCloud, AzureChinaCloud, and AzureGermanCloud.

8. Run the following command to install Velero with the restic option by using the Azure storage account key:

```
velero install \
--provider azure \
--plugins velero/velero-plugin-for-microsoft-azure:v1.1.0 \
--bucket $AZURE_BLOB_CONTAINER \
--secret-file ./credentials-velero \
--backup-location-config
resourceGroup=$AZURE_BACKUP_RESOURCE_GROUP,storageAccount=$AZURE_STORAGE_ACCOUNT_ID,storageAccou
ntKeyEnvVar=AZURE_STORAGE_ACCOUNT_ACCESS_KEY,subscriptionId=$AZURE_BACKUP_SUBSCRIPTION_ID \
--use-volume-snapshots=false \
--use-restic
```

Results

You have prepared your cluster to back up the server data.

What to do next

You can back up the server data. See Backing up the server data on Azure Kubernetes Service on page 79

Related information

Velero Documentation Velero plugin for Microsoft Azure documentation AKS Documentation

Backing up the server data on Azure Kubernetes Service

You might want to back up the server data to protect against data corruption or malicious attacks. You might also want to back up the server data when you want to upgrade to a new version of the server software.

Before you begin

You must have completed the following tasks:

- · Been assigned the same role that was required to install and uninstall the server software.
- Installed the server software and all of the HCL OneTest[™] Server pods are in Running state.
- Communicated to the users that HCL OneTest[™] Server might be unavailable for some time until the process is complete.
- Prepared your cluster to store the backed-up data by using Velero. See Preparing the Azure Kubernetes Service cluster to back up the server data on page 76.

About this task

If you plan to back up the data immediately after you prepared your Azure Kubernetes Service (AKS) cluster, then you must go to Step 3 on page 79 to start the backup process.

1. Run the following command to log in to AKS interactively:

az login

Result

The command-line interface opens a browser and displays the Log-in page of AKS.

- 2. Sign in with your AKS account credentials.
- 3. Run the following command to start the backup process of the HCL OneTest[™] Server data:

```
velero backup create {backup_file_name} --include-namespaces=test-system
    --default-volumes-to-restic
```



Note: You must replace $\{ backup_file_name \}$ with the name that you want to provide for the backup file.



Tip: You can run the velero backup describe {backup_file_name} --details command to verify the progress of the backup operation.

Results

You have backed up the data of HCL OneTest[™] Server on AKS.

What to do next

You can restore the server data. See Restoring the server data on Azure Kubernetes Service on page 80.

Related information

Velero Documentation

Restoring the server data on Azure Kubernetes Service

You can restore the server data that is backed up in HCL OneTest[™] Server when required.

Before you begin

You must have completed the following tasks:

- Been assigned the same role that was required to install and uninstall the server software.
- Communicated to the users that HCL OneTest[™] Server might be unavailable for some time until the process is complete.
- Backed up the data from HCL OneTest[™] Server.

About this task

If you plan to restore the server data immediately after you backed up the data from HCL OneTest[™] Server that you installed on Azure Kubernetes Service (AKS), then you must go to Step 3 on page 80 to start the restoration process.

1. Run the following command to log in to AKS interactively:

az login

Result

The command-line interface opens a browser and displays the Log-in page of AKS.

- 2. Sign in with your AKS account credentials.
- 3. Run the following command to start the restore process of the HCL OneTest[™] Server data:

velero restore create --from-backup={backup_file_name} --restore-volumes



Tip: You can run the velero restore describe {backup_file_name} --details command to verify the progress of the restore operation.



Note: You must replace {backup_file_name} with the name that you provided during the backing up of the server data.

Results

You have restored the data of HCL OneTest[™] Server on AKS.

Related information

Velero Documentation

Uninstallation of the server software

When you no longer require HCL OneTest[™] Server, you can uninstall the server software. You can uninstall the server software depending on the platform on which you installed the server software.

Uninstalling the server software from Ubuntu

When you want to install a new version of server software or you want to reinstall the server software when an ongoing installation fails, you can uninstall the server software and its components from the Ubuntu platform.

Before you begin

You must have completed the following tasks:

- Installed HCL OneTest[™] Server software.
- Closed HCL OneTest[™] Server, any open web browsers, and all other applications that are enabled by HCL OneTest[™] Server.
- Optional: Backed-up data from the previous version of the product.

About this task

You must replace {my-rtas}{my-ots} with the name of the release that you provided during the installation of the server software in all the instances in this procedure.

The test-system is the name of the namespace that is created during the setting up of the k3s environment.

- 1. Log in to the Ubuntu server using an SSH session.
- 2. Run the following command to stop the workload that is running:

kubectl delete all,cm,secret -lexecution-marker -n test-system

3. Run the following command to uninstall the server software:

helm uninstall {my-ots} -n test-system

The PersistentVolumeClaims and PersistentVolumes that were created during the installation are not deleted automatically. If you reinstall the server software, the user data is reused unless you specifically delete those volumes.

4. Run the following commands to delete the entire Kubernetes environment, including all user data:

Ubuntu version	Commands to be run	
18.04	cd hcl-onetest-base sudo ./ubuntu-wipe.shconfirm	
20.04	cd hcl-onetest-base sudo HOME=\$HOME ./ubuntu-wipe.shconfirm	

After you run this command, the system returns to the same state as if ubuntu-init.sh was never run.

Important: If you want to migrate data from a previous version to the latest version of the product, then you must ensure to back up the data before you run this command.

Results

You have uninstalled the server software from the Ubuntu platform.

Uninstalling the server software from Azure Kubernetes Service

When you want to install a new version of server software or you want to reinstall the server software when an ongoing installation fails, you can uninstall the server software and its components from the Azure Kubernetes Service (AKS) cluster.

Before you begin

You must have completed the following tasks:

- Installed HCL OneTest[™] Server software.
- Closed HCL OneTest[™] Server, any open web browsers, and all other applications that are enabled by HCL OneTest[™] Server.
- Optional: Backed-up data from the previous version of the product.
- 1. Run the following command to log in to AKS interactively:

az login

Result

The command-line interface opens a browser and displays the Log-in page of AKS.

- 2. Sign in with your AKS account credentials.
- 3. Run the following command to uninstall the server software:

helm uninstall {my-ots} -n test-system

The PersistentVolumeClaims and PersistentVolumes that were created during the installation are not deleted automatically. If you reinstall the server software, the user data is reused unless you specifically delete those volumes.

4. Run the following command to delete the resource group from the AKS cluster:

az group delete -g <resource_group>

You must replace <resource_group> with the name of the resource group that you created during the creation of the AKS cluster.

Results

You have uninstalled the server software from the AKS cluster.

Configuration of the server software

You can find information about the tasks that you must perform after you installed the server software to configure HCL OneTest[™] Server.

The following table describes the tasks that you can perform as an administrator after you installed the server software:

Require- ment	Tasks	More information
Required	Review the default user management to know how the server software manages the users and their authentication.	User administration on page 84
Required	Import Certificate Authority (CA) into a browser to prevent certificate errors when you access the HCL OneTest™ Server UI.	Certificate authority: Importing and extending lists on page 97
Optional	Copy the third-party application Jars to Kuber- netes to run API Suites that uses a transport.	Copying third-party application Jars to Kubernetes on page 100

Require- ment	Tasks	More information
Optional	Change the password seed to provide enhanced security to HCL OneTest [™] Server.	Changing the password seed on page 103
Optional	Disable the server extensions that are enabled during the installation of the server software if you do not want the server extensions to run on the cluster to save server resources.	Disabling server extensions on page 106

User administration

After you install HCL OneTest[™] Server, you must consider how the software manages users and authentication.

You can review the default user management provided by the server and decide what additional controls you might want to add. If you manage users and authentication through an existing LDAP/AD server, you can review how to use that server to manage HCL OneTest[™] Server users.

Enabling the Sign up link on the Login page of server

You can enable the **Sign up** link when it is not visible on the **Login** page of HCL OneTest[™] Server by using the Keycloak UI.

Before you begin

You must have completed the following tasks:

- Installed HCL OneTest[™] Server.
- Assigned the role of a Keycloak Administrator.
- Copied the URL of the Keycloak UI, username, and password on completion of the installation of server software.

About this task

The **Sign up** link on the **Login** page of HCL OneTest[™] Server is not visible when you install the server software by using the default values. The **Sign up** link is hidden to provide the enhanced security to HCL OneTest[™] Server. You can enable the **Sign up** link on the **Login** page when you want to provide self-registration of users in HCL OneTest[™] Server.

You can enable the **Sign up** link on the **Login** page in two ways:

• You can use the keycloak.signup.enabled parameter during the installation of the server software.

For more information about installing the server software by using the keycloak.signup.enabled parameter, see the **Related information** section.

• You can use the Keycloak UI after the installation is complete.

For more information on Keycloak UI, see the **Related information** section.

The following procedure describes steps to be performed to enable the Sign up link by using Keycloak UI.

- 1. Log in to the Keycloak Admin Console.
- 2. Click **Realm Settings** from the left navigation pane.
- 3. Click the **Login** tab.
- 4. Set User Registration to ON.
- 5. Click Save to apply the changes.

Results

You have enabled the **Sign up** link on the **Login** page of HCL OneTest[™] Server. The **Sign up** link is now visible on the **Login** page of HCL OneTest[™] Server.

What to do next

You can click the Sign up link to create an account in HCL OneTest[™] Server.

Related information Installing the server software on Azure Kubernetes Service on page 53 Installing the server software on Ubuntu by using k3s on page 42 Keycloak

Default user administration

You installed HCL OneTest[™] Server and you want to know about how the software manages user access.

HCL OneTest[™] Server uses Keycloak (https://www.keycloak.org/) to manage and authenticate users.

If you manage and authenticate users by using an LDAP and Active Directory server, you can configure Keycloak to connect to that server. For more information, see LDAP user administration on page 87.


Keycloak uses the concept of a realm to manage and authenticate users. When you install the server software, a realm called testserver is created for you in Keycloak. All server users belong to this realm and when they log in to the server, they log into that realm.

As an administrator, it is important to consider the following points about the server administration:

• By default, there is no administrator for HCL OneTest[™] Server.

Such an administrator is required for accessing additional functions, which includes claiming ownership of server projects and unarchiving them. But you can assign administrative privileges to any user. You must do this by adding the admin role to the user in Keycloak.

• You must sign up a user that you want to be the administrator. You must go to the Login page at https://stully-qualified-dns-name: 443 and sign up.



• After you sign up the user that you want to be the administrator for HCL OneTest[™] Server, you must log in to the Keycloak Admin Console at :443/auth/admin/">https://stully-qualified-dns-name>:443/auth/admin/ to make that user the server administrator.

The default user name for the Keycloak administrator is keycloak. The password is randomly generated when the software is installed. You can see the password by using the following kubectl command:



Note: You must substitute {my-ots} with the release name that you used during the installation of the server software.

After you log in to the Keycloak Admin Console, from the Users page, you can search and select the user that you want to make an administrator. From the **Groups** tab, you can join the user to the **Admins** group.

For more information about assigning user roles, see Groups in the Keycloak documentation.

Now that you are the server administrator, it is important to consider the following points about the default user management and authentication:

- · Minimum password length defaults to 8 characters
- · Email verification of new users is turned off
- The Forgot Password feature is turned on by default but no instructions are sent to the user to reset their password
- Forgotten user passwords are changed by you if you do not enable Keycloak to send instructions to reset a password

You can review the following sections about changing the default authentication controls.

Email settings

By default, the testserver realm sets the Forgot Password switch on. However, as an administrator, you must enable Keycloak to send an email to the user with instructions to reset their password. If you want to verify an email, you must also enable Keycloak to send an email to the user to verify their email address.

You must provide SMTP server settings for Keycloak to send an email. After you log in to the Keycloak Admin Console, see Email Settings in the Keycloak documentation.

Then, to set up the email verification, see Forgot Password in the Keycloak documentation.

Password policy

By default, the testserver realm has a password policy where the minimum length of a password is 8. As an administrator, you can update password policies in Keycloak.

After you log in to the Keycloak Admin Console, see Password Policies in the Keycloak documentation.

User password

If you did not enable Keycloak to send instructions to a user about how to reset a password, you must use the Keycloak Admin Console to change their password for them.

After you log in to the Keycloak Admin Console, see User Credentials in the Keycloak documentation.

User deletion

When a user is inactive or no longer needs to access the server, you can delete that user.

After you log in to the Keycloak Admin Console, see Deleting Users in the Keycloak documentation.

LDAP user administration

After you installed HCL OneTest[™] Server, you can use a Lightweight Directory Access Protocol and Active Directory HTTP server to manage users and authentication. Some of the following best practices, can help you to use an LDAP/ AD server to manage user access to HCL OneTest[™] Server.

HCL OneTest[™] Server uses Keycloak (https://www.keycloak.org/) to manage and authenticate users.

Existing user databases hold user credentials. Keycloak federates these existing external user databases through the concept of storage providers. By default, Keycloak supports an LDAP and Active Directory storage provider. By adding a storage provider, you can map LDAP user attributes into Keycloak. You can also configure more mappings.

Before you configure Keycloak to use an existing LDAP/AD provider, you might consider the following best practices:

- Set up your LDAP/AD provider as a read-only repository so that HCL OneTest[™] Server cannot change it.
- Add and remove users in LDAP/AD and not the Keycloak local user database.
- Import and synchronize your LDAP/AD users to your Keycloak local database.

• Map a login style name, for example, userl@server.com, by using the UserPrincipalName attribute in LDAP/ AD to a username in Keycloak. If you want the full name of the user as your login style, use the cn attribute in LDAP/AD.



Note: The LDAP/AD user name attribute must match the LDAP/AD provider user name attribute (**Username LDAP attribute**) in Keycloak for the LDAP/AD provider to connect with Keycloak.

The following sections use these best practices to guide you to set up Keycloak to connect to your LDAP/AD HTTP server.

LDAP provider selection in Keycloak


You can use the Keycloak Admin Console to add an LDAP/AD provider.

You can log in to the Keycloak Admin Console at https://<fully-qualified-dns-nam>/auth/admin. The default user name for the Keycloak administrator is keycloak. The password is randomly generated when you installed the HCL OneTest[™] Server software. You can see the password by using the following kubectl command:

kubectl get secret -n test-system {my-ots}-keycloak-postgresql -o jsonpath="{.data.password}" | base64
 --decode; echo

Note: You must substitute {my-ots} with the release name that you used during the installation of the server software.

After you log in, you can go to the User Federation page to add your provider.



You want to select the provider named **Idap** from the list. From the Add user federation provider page, you can use a form to complete your LDAP/AD connection parameters.

Required settings for a successful connection to your LDAP/AD provider

The form includes many fields and several fields include default values. Tables describe the important fields that you must complete to ensure a successful HTTP connection to your LDAP/AD provider.

Required Settings

Enabled 😡	ON	
Console Display Name 🕢	Test Server LDAP/AD Provider	
Priority 🕑	0	
Import Users 🕑	ON	
Edit Mode 🚱	READ_ONLY	~
Sync Registrations 🚱	OFF	
* Vendor 🔞	Active Directory	~

Field	Description
Console Display Name	You want to make your console name recognizable, for example, Test Server LDAP/AD Provider. This name is shown in the Keycloak Admin Console.
Priority	The priority must be set to 0 so that when a user logs in to HCL OneTest [™] Server, Key- cloak looks up the user first in the list of users managed in the LDAP/AD user database. If the user is not found in your LDAP/AD user database, Keycloak then looks up the user in the local Keycloak user database.
Import Users	You want to leave import users ON so that users in your LDAP/AD user database are syn- chronized (imported) automatically into the Keycloak local user database. The import us- es the settings that you are defining now. After the initial import, when you add a user to your LDAP/AD user database and that user logs in to HCL OneTest [™] Server, the LDAP/AD provider imports the LDAP/AD user
	into the Keycloak user database and authenticates the user against the LDAP/AD pass- word. Similarly, after the initial import, when you remove a user from your LDAP/AD user data- base that user cannot log in to HCL OneTest [™] Server.

Field	Description		
	Note: For consistent user management, continue to manage users in your LDAP/ AD user database.		
Edit Mode	Make sure that edit mode is set to READ_ONLY .		
	This setting means that your LDAP/AD user database is read-only. No user data defined through the mapping of attributes in Keycloak such as the username is written back from the Keycloak user database to your LDAP/AD user database. This read-only setting also means that a new user cannot sign up from HCL OneTest [™]		
	Server as no user data can be written to your LDAP/AD user database.		
Vendor	You want to select Active Directory from the list of vendors. Many fields complete with default values based on this selection.		

* Username	userPrincipalName		
LDAP attribute 🚱			
* RDN LDAP	cn		
attribute 🚱			
* UUID LDAP	objectGUID		
attribute 🚱			
* User Object	User		
Classes 🚱			
* Connection URL	ldap://1012		Test connection
0			
* Users DN 😡	cn=Users,dc=OneTest,dc=COM		
Custom User	(memberOf=cn=Testers,dc=OneTest,dc=COM)		
LDAP Filter 🚱) <u>-</u>		
Search Scope 😡	One Level	~	
* Bind Type 🚱	simple	~	
* Bind DN 😡	ServerAdmin		
* Bind Credential		۲	Test authentication
0			

Field	Description
Username LDAP attribute	You can use the default value on for the username, which is a first name, last name, or you can use userPrincipalName, which is username@domain.
	You might want a login that matches your company style. For example, you might prefer joetester@mycompany.com instead of Joe Tester.
	If you do make this change the username that you specify now must match the username in the Mapper. Keycloak makes this change for you.
User Object Classes	Because LDAP user records are found based on a user object class, you must set the User Object Classes to User.
Connection URL	So that Keycloak can connect to your LDAP/AD user database, you must enter your LDAP/AD URL, for example, <pre>ldap://<hostname>.<domain></domain></hostname></pre>
	Make sure that you test the connection and confirm that the connection is successful.
Users DN	You must provide the directory where the LDAP users are listed, for example, cn=User- s,dc=OneTest,dc=COM.
Custom User LDAP Filter	You can filter your LDAP/AD users to import a subset of all your LDAP users.
	For example, you can set up a RTAS user group for your LDAP/AD user database such that only those users are imported to Keycloak.
Bind DN	(memberOf=cn=Testers,dc=OneTest,dc=COM)
Bind DN Bind Credential	You must also provide the LDAP/AD user database administrator user ID for BIND DN and password for the BIND Credential . These credentials are used by Keycloak to ac- cess the LDAP/AD user database.
	Make sure that you test the authentication and confirm that the authentication is suc- cessful.

You can save the settings, which create your LDAP/AD provider.

Mappers

Keycloak uses mappers to map the user attributes defined in the Keycloak user model such as **username** and **email** to the corresponding user attributes in the LDAP/AD user database. By default, when you saved your settings and created your LDAP/AD provider, the following mappers were created.

Test Server LDAP/AD Provider 🍵

Settings

Mappers

Search	Q	Create	
Name		Туре	
email		user-attribute-ldap-mapper	
creation date		user-attribute-ldap-mapper	
MSAD account cont	ols	msad-user-account-control-mapper	
username		user-attribute-ldap-mapper	
last name		user-attribute-ldap-mapper	
modify date		user-attribute-ldap-mapper	
full name full-name-Idap-mapper		full-name-Idap-mapper	

The username attribute that you specified in the **Username LDAP attribute** must match the **username** t attribute defined in the Keycloak mapper for the LDAP/AD user database to connect with Keycloak.

Because you changed the **Username LDAP attribute** from the default value <u>cn</u> to <u>userPrincipalName</u>, Keycloak made the same change in the mapper called **username** to match.

Username 👕

ID

e5c30485-086e-44ae-81dc-eb12383d2de3

Name * 🚱

username

Mapper Type 😡

user-attribute-ldap-mapper

User Model Attribute 😡

username

LDAP Attribute @

userPrincipalName

Read Only @

ON

Always Read Value From LDAP @

s	Mandatory	In	LDAP	6
_				-



Is Binary Attribute 🚱

	OFF		
	1000	-	

User synchronization

Save Cancel

You must import all users from your LDAP/AD user database by using the option to **Synchronize all users**. Users are imported based on your saved settings when you set up your LDAP/AD provider.

Save	Cancel	Synchronize changed users	Synchronize all users	Remove imported
Unlink	users			

A successful import is followed by a success message with the number of users imported.

You can view all the LDAP/AD database users that were imported and authenticated from the Users page in the Keycloak Admin Console.

								🛓 Keycloak 🗸
Testserver 🗸	Users							
Configure	Lookup	Permiss	ions 🛛					
Realm Settings	Search	Q		View all users	Unlock us		Inlock users	Add user
🗊 Clients				Last	First			· · · · · · · · · · · · · · · · · · ·
🚓 Client Scopes	ID	Username	Email	Name	Name	Actions		
📰 Roles	2cfff9	build.ver	build	verific	build	Edit	Impersona	te Delete
and a second	36c7d	rituser1		User1	RITUs	Edit	Impersona	te Delete
💳 Identity Providers	94f62	rituser4		LastN	RITUs	Edit	Impersona	te Delete
User Federation								
Authentication								
Manage								
k Groups								
💄 Users								

Users are listed with ID, Username, Email, Last Name, and First Name. The ID is generated by Keycloak. The value of the other attributes is fetched from the LDAP/AD user database by using mappers.

Important: If you get a message of a failed import for an LDAP/AD user, then the failed import might be due to any one of the following reasons:

- The User logon name field under the Account tab of that LDAP/AD user is blank.
- The value of the **Custom User LDAP Filter** field to import only a subset of all LDAP users does not match with the LDAP set of users.

You can check the log file of the Keycloak pod to understand the reason for the failed import.

You can perform the following steps to view the log file of the Keycloak pod:

1. Run the following command to view the list of all pods:

kubectl get pods -n test-system

- 2. Identify the Keycloak pod ssocloak-0.
- 3. Run the following command to view the log of the Keycloak pod:

!

kubectl logs {my-ots}-ssocloak-0 -n test-system



Note: Where, {my-ots} is the name of the release that is provided during the installation of the server software.

The log file of the Keycloak pod is displayed.

A sample of a log file is as follows:

```
12:49:00,535 ERROR [org.keycloak.storage.ldap.LDAPStorageProviderFactory] (default task-40)
Failed during import user from LDAP: org.keycloak.models.ModelException: User returned from LDAP
has null username!
Check configuration of your LDAP mappings.
Mapped username LDAP attribute: userPrincipalName, user DN:
    CN=DefaultAccount,CN=Users,DC=ONETEST,DC=COM,
attributes from LDAP: {whenChanged=[20190527143130.0Z], whenCreated=[20190527143130.0Z],
    cn=[DefaultAccount],
    userAccountControl=[66082], pwdLastSet=[0]}
```

Managing account settings

You might want to change your password or other settings for your account.

About this task

As an account owner, you can view your account settings, which include your user name, email, and first and last name. You can also change all of these settings except the user name. Changing your password is also possible from your account settings.



Note: Account settings cannot be changed if HCL OneTest[™] Server was configured to use an LDAP/AD provider. For more information about server security, see the related links.

- Edit your account details by following these steps:
 - 1. Click the **User** icon (2) from the menu bar, and select **Account Settings**.

The Edit account page is displayed.

- 2. Edit your user details and save the changes. You can also reset your changes. If you cancel your changes, you return to the Home page.
- Change your password by following these steps:
 - 1. Click the **User** icon ⁽²⁾ from the menu bar, and select **Account Settings**.

The Edit account page is displayed.

2. Click Change password.

The Change password page is displayed.

- 3. Type your current password followed by your new password
- 4. Confirm the new password by typing it again and save the changes. You can also reset your changes. If you cancel your changes, you return to the Home page.

Related information

Default user administration on page 85

Certificate authority: Importing and extending lists

When you want browsers and other applications to access HCL OneTest[™] Server, you must enable browsers to trust the certificate authority (CA) of HCL OneTest[™] Server. For some applications that integrate with HCL OneTest[™] Server, you must also extend the CA lists that are trusted by the applications.

You can find the following tasks to import the certificate authority in the browser that you want to use:

- Importing Certificate Authority into the Google Chrome browser on page 97
- Importing Certificate Authority into the Microsoft Edge browser on page 98
- Importing Certificate Authority into the Mozilla Firefox browser on page 99

You can find the following tasks when you want to extend the CA lists:

- Extending the trusted CA list on Linux on page 99
- Extending the trusted CA list on Windows systems on page 100

Importing Certificate Authority into the Google Chrome browser

You must import certificate authority into the Google Chrome browser to prevent certificate errors when accessing the HCL OneTest[™] Server UI.

Before you begin

You must have completed the following tasks:

• Saved a certificate authority (CA) during the installation of HCL OneTest[™] Server.

You can run the following command to get the certificate from the system:

```
kubectl get secret ingress -n test-system -o jsonpath={.data.ca\\.crt} | base64 -d
```

- **Remember:** test-system is the name of the namespace. If you created a namespace by using a different value, then you must use that value in place of the *test-system*.
- Installed the browser that you want to use to access HCL OneTest[™] Server.
- 1. Open a Google Chrome browser.
- 2. Navigate to Customize and control Google Chrome > Settings.
- 3. Click Security from the Privacy and security pane.
- 4. Click Manage certificates, and then Import.
- 5. Click Next in the Certificate Import Wizard window.
- 6. Click Browse and select the CA that you want to import, and then click Next.
- 7. Select the Place all certificates in the following store option to store the CA securely.
- 8. Click Browse, and then select Trust Root Certification Authorities as certificate store.
- 9. Click OK, and then Finish.

Results

You have imported the CA into the Google Chrome browser.

Importing Certificate Authority into the Microsoft Edge browser

You must import Certificate Authority (CA) into the Microsoft Edge browser to prevent certificate errors when accessing the HCL OneTest[™] Server UI.

Before you begin

You must have completed the following tasks:

• Saved a certificate authority (CA) during the installation of HCL OneTest[™] Server.

You can run the following command to get the certificate from the system:

kubectl get secret ingress -n test-system -o jsonpath={.data.ca $\$ | base64 -d

4

Remember: *test-system* is the name of the namespace. If you created a namespace by using a different value, then you must use that value in place of the *test-system*.

- Installed the browser that you want to use to access HCL OneTest[™] Server.
- 1. Type certmgr.msc in the Start menu Search filed, and then press Enter.
- 2. Expand Trusted Root Certification Authorities, and then select Certificate.
- 3. Right-click on the empty space, and then select All tasks > Import.
- 4. Click Next in the Certificate Import Wizard window.
- 5. Click **Browse** and select the CA that you want to import, and then click **Next**.
- 6. Select the Place all certificates in the following store option to store the CA securely.

- 7. Click Browse, and then select Trust Root Certification Authorities as certificate store.
- 8. Click Next, and then Finish to import the certificate.

Results

You have imported the CA into the Microsoft Edge browser.

Importing Certificate Authority into the Mozilla Firefox browser

You must import Certificate Authority (CA) into the Mozilla Firefox browser to prevent certificate errors when accessing the HCL OneTest[™] Server UI.

Before you begin

You must have completed the following tasks:

• Saved a certificate authority (CA) during the installation of HCL OneTest[™] Server.

You can run the following command to get the certificate from the system:

kubectl get secret ingress -n test-system -o jsonpath={.data.ca\\.crt} | base64 -d

Remember: *test-system* is the name of the namespace. If you created a namespace by using a different value, then you must use that value in place of the *test-system*.

• Installed the browser that you want to use to access HCL OneTest[™] Server.

- 1. Open a Mozilla Firefox browser.
- 2. Enter "about:preferences#privacy" in the address bar, and then press Enter.
- 3. Locate and click the **View Certificates** option.
- 4. Select Authorities tab, and then click Import.
- 5. Select the CA that you want to import, and then click **Open**.
- 6. Select Trust this CA to identify websites in the Downloading Certificate window.
- 7. Click **OK** to import the CA into the browser, and then close the window.
- 8. Restart Firefox.

Results

You have imported the CA into the Mozilla Firefox browser.

Extending the trusted CA list on Linux

HCL OneTest[™] Server trusts the certificates signed by a recognized Certified Authority (CA). When you have any additional CAs, you must extend the trusted certificates list by using an environment variable on Linux.

Before you begin

You must have saved the CA assigned to HCL OneTest[™] Server.

Note: You can contact the administrator of HCL OneTest™ Server if you do not have a copy of the CA.

- 1. Open the terminal.
- 2. Run the following command to create an environment variable on the Linux operating system:

export NODE_EXTRA_CA_CERTS= {path of the downloaded CA with the file extension}

For example,

export NODE_EXTRA_CA_CERTS=/opt/mycert/ca-master.crt

Results

You have extended the trusted CA certificates list on Linux.

Extending the trusted CA list on Windows systems

HCL OneTest[™] Server trusts the certificates signed by a recognized Certified Authority (CA). When you have any additional CAs, you must extend the trusted certificates list by using an environment variable on Windows systems.

Before you begin

You must have saved the CA assigned to HCL OneTest[™] Server.

Note: You can contact the administrator of HCL OneTest™ Server if you do not have a copy of the CA.

- 1. Right-click the Windows icon 🖽 from the Windows taskbar, and then click **System**.
- 2. Click Advanced system settings from the Related setting section.
- 3. Click the Advanced tab, and then click Environment Variables.
- 4. Click New from the System variables section.
- 5. Enter NODE_EXTRA_CA_CERTS in the Variable name field.
- 6. Enter the path of the downloaded CA with the file extension in the Variable value field.

For example, if you stored the ca-master.crt CA in the C:\Users\Desktop\cert location, then enter the Variable value field as C:\Users\Desktop\cert\ca-master.crt

7. Click OK.

Results

You have extended the trusted CA certificates list on Windows systems.

Copying third-party application Jars to Kubernetes

You can run API Suites in a project on HCL OneTest[™] Server. If the API Suite uses a transport and the transport requires third-party application Jar files for a successful run, you must ensure that the third-party application Jar files are available at the test run time. To achieve this, you must copy the third-party application Jar files to the computer where HCL OneTest[™] Server is installed on Kubernetes.

Before you begin

If you want to copy the third-party application Jar files to the remote Docker host, see Copying third-party application Jars to a remote Docker host on page 301.

You must have server administrator or cluster administrator privileges.

You must have completed the following tasks:

- Identified the third-party application Jar files that are required and copied the files. See Test run considerations for API Suites or API tests on page 279.
- Copied the third-party application Jar files from HCL OneTest[™] API to the directory or folder in Kubernetes from where you can run the kubectl commands.

About this task

You can copy the third-party application Jar files to the folder that is specific for the application under the /data/ <application_name> folder. You need not extract the files.

You can perform this task any time after you have installed HCL OneTest[™] Server and you plan to run an API Suite that meets any of the following conditions:

- The API Suite uses transports and the transports require third-party application Jar files to be available at the test run time.
- The API Suite in the project has a results database configured.

You can copy the JDK version Jar files that you have used to create the JUnit tests.

You can get help on the kubectl commands by running the command: kubectl cp --help from the /kube directory. For more information, refer to the kubectl documentation.

1. Use the following table to find the name of the folder that corresponds to the specific third-party application for the transport used in the API Suite.

Application	Name of the folder to use
Camel	Camel
CentraSite	CentraSite
CICS	CICS
Coherence	Coherence
Database	JDBC
IMS	IMS

Application	Name of the folder to use
Integra	Integra
JMS	JMS
SAP RFC	SAP
Software AG Universal Messaging	SoftwareAGUM
TIBCO EMS	ТІВСО
TIBCO Rendezvous	
TIBCO SmartSockets	
WebSphere Application Server Service Integration Bus (SiBus)	WAS
WebLogic	WebLogicJMX
Software AG webMethods	webMethods

2. Open the command prompt from the /kube directory and copy the Jar files to the folder that corresponds to the application by using the following command:

kubectl cp <compressed_files> test-system/{my-ots}-userlibs-0:/data/<application_name>/

For example, if you are copying the Database Jar files, then the name of the folder is *JDBC* and the command to use is:

kubectl cp mysql-connector-java.jar test-system/{my-ots}-userlibs-0:/data/JDBC/



Note: You must substitute $\{my-ots\}$ with the release name that you used during the installation of the server software.

3. Verify whether the Jar files are copied by running the following command:

kubectl exec $_{\tt my-ots}\mbox{-userlibs-0}$ -n test-system -- ls /data/<folder_created>

For example, if you copied the Database Jar files, mysql-connector-java.jar to the folder JDBC, then the command to verify is:

kubectl exec {my-ots}-userlibs-0 -n test-system -- ls /data/JDBC

The following information is displayed for the JDBC folder:

mysql-connector-java.jar



Note: You must substitute $\{m_{y-ots}\}$ with the release name that you used during the installation of the server software.

Results

You have successfully copied the third-party application Jar files to the folder in Kubernetes.

What to do next

You can configure the API Suite run. See Configuring an API Suite or an API test run on page 343.

Changing the password seed

As an administrator, you can change the password seed that is used when you install the server software to provide enhanced security to HCL OneTest[™] Server.

Before you begin

You must have completed the following tasks:

- Installed HCL OneTest[™] Server. See Installation of the server software on page 36.
- Installed the JSON command-line tool, jq, and ensured that the jq is in your environment PATH. For information about jq, refer to jq documentation.
- Installed the Curl command line tool. For more information refer to curl documentation.

About this task

When you install HCL OneTest[™] Server, you supply a password seed when you run the helm install command. This password seed is used to generate several Kubernetes secrets. Kubernetes Secrets can contain the following information:

- The authentication credentials for micro-services.
- An encryption key for the user-created secrets collection or other secrets.

When you change the password seed for HCL OneTest™ Server, you must consider the following scenarios:

- HCL OneTest[™] Server cannot communicate until you reconcile the passwords which are in Kubernetes Secrets by using the old and a new password seed.
- Users cannot read secret collections or other secrets that they have created in HCL OneTest[™] Server until you re-encrypt them using a new password seed.



Important: You must provide an offline token and old password seed that you used during the installation of server software to re-encrypt user secrets.

1. Run the following command to change the password seed for HCL OneTest[™] Server:

```
helm upgrade {my-ots} ./hcl-onetest-server -n test-system \
--reuse-values \
--set global.hclOneTestPasswordAutoGenSeed= {my-new-super-secret}
```



Notes: You must substitute the value of the following variables with the actual value in the command:

- {my-ots} with the release name that you used during the installation of the server software.
- {my-new-super-secret} with a new value of your choice as the password seed.
- You must run the following helm upgrade command from the same directory where the helm install command was run during the installation of the server software. Because the upgrade is dependent on the helm charts and .yaml file values used during the run time of the helm install command.
- Run the following script to generate new server secrets from the updated password seed and to save them to the persistent storage:

./hcl-onetest-server/files/reconcile-secrets.sh -n test-system {my-ots}

Run the following command to restart all the pods:

```
kubectl delete pods -n test-system \
    -lapp.kubernetes.io/instance={my-ots} \
    -lapp.kubernetes.io/managed-by=Helm
```

4. Run the following commands to re-encrypt the user-created secrets collection or other secrets by providing the old password seed:

```
export ACCESS_TOKEN=$(curl -k -X POST {SERVER_URL}/rest/tokens/ \
-H "Content-Type: application/x-www-form-urlencoded" \
-H "accept: application/json" \
-d "refresh_token={OFFLINE_TOKEN}" | jq -r '.access_token')
curl -k -X POST {SERVER_URL}/rest/secrets/re-encrypt/ \
-H "Authorization: Bearer $ACCESS_TOKEN" \
-H "Content-Type: application/json" \
-d "{\"type\":\"helm\",\"password_auto_gen_seed\":\"{OLD_SEED}\"}"
```

Note: You must substitute the value of the following variables with the actual value in the following commands:

- {SERVER_URL} with the URL of your HCL OneTest[™] Server UI.
- {OFFLINE_TOKEN} with the offline token that belongs to a user with the administrator role.
- {OLD_SEED} with the previous password seed that you used during the installation of the server software.
- 5. Run the following command to display the log file of the gateway pod:

kubectl logs {my-ots}-gateway-abcdefghij-abcde -n test-system



Note: You must substitute the value of the following variables with the actual value in the command:

- {my-ots} with the release name that you used during the installation of the server software.
- abcdefghij-abcde with an identifier that is assigned to the name of the gateway pod.

You can run the kubectl get pods -n test-system command to obtain the identifier that is assigned to the gateway pod.

Result

The following message is displayed when re-encryption is completed:

reEncrypt complete. StringyReEncryptor [total=100, fixed=100, broken=0, noop=0]

Results

You have successfully changed the password seed for HCL OneTest[™] Server.

Server extensions

You can run specific tests in HCL OneTest[™] Server by enabling the server extensions.

The server extensions are enabled at the time of installation of the server software. When the server extensions are enabled, you can perform the following tasks on HCL OneTest[™] Server:

- Add repositories that contain the test assets for the HCL AppScan CodeSweep tests, JMeter tests, JUnit tests or Postman collections.
- Configure a test run for the following test types:
 - HCL AppScan CodeSweep
 - JMeter

- JUnit
- Postman

To learn more about enabling and disabling the server extensions, refer to the following topics:

Disabling server extensions

When you do not want the server extensions to run on the cluster to save server resources, you can disable server extensions.

Before you begin

You must have ensured that the server extension that you want to disable is enabled and running.

Tip: You can verify the status of the extension by running the kubectl get pods -n {name_of_the_namespace} command. The status of an enabled server extension is displayed as Running.

About this task

You must substitute $\{m_{Y-ots}\}\$ with the release name that you provided during the installation of the server software in the following procedure.

The test-system is the name of the namespace. If you created a namespace by using a different value, then you must use that value in place of test-system in all the instances in this procedure.

1. Log in to the platform that you used to install the server software.

For example, you can log in to the Ubuntu server using an SSH session if you installed the server software on Ubuntu.

2. Run the following command to disable all the extensions:

```
helm upgrade {my-ots} -n test-system ./hcl-onetest-server \
--reuse-values \
--set global.hclOneTestPostmanEnabled=false \
--set global.hclOneTestJUnitEnabled=false \
--set global.hclOneTestCodesweepEnabled=false
```


If you want to disable any specific extension, then you can set the respective helm parameter value to false.

For example, to disable the JMeter extension alone, then you can run the following command:

```
helm upgrade {my-ots} -n test-system ./hcl-onetest-server \
--reuse-values \
--set global.hclOneTestJMeterEnabled=false
```

3. Run the following command to verify the status of the extensions:

kubectl get pods -n test-system



Note: The pod for each server extension that you disabled no longer displays.

Results

You have disabled the required server extensions on HCL OneTest[™] Server.

Enabling server extensions

If you find that the server extension is disabled and you want to run the tests supported by the server extension, then you must enable them.

Before you begin

You must have ensured that the server extension that you want to enable is disabled.

About this task

You must substitute {my-ots} with the release name that you provided during the installation of the server software in the following procedure.

The test-system is the name of the namespace. If you created a namespace by using a different value, then you must use that value in place of test-system in all the instances in this procedure.

1. Log in to the platform that you used to install the server software.

For example, you can log in to the Ubuntu server using an SSH session if you installed the server software on Ubuntu.

2. Run the following command to enable all the extensions:

```
helm upgrade {my-ots} -n test-system ./hcl-onetest-server \
--reuse-values \
--set global.hclOneTestPostmanEnabled=true \
--set global.hclOneTestJMeterEnabled=true \
--set global.hclOneTestJUnitEnabled=true \
--set global.hclOneTestCodesweepEnabled=true
```

If you want to enable any specific extension, then you can set the respective helm parameter value to true.

For example, to enable the Postman extension alone, then you can run the following command:

```
helm upgrade {my-ots} -n test-system ./hcl-onetest-server \
--reuse-values \
--set global.hclOneTestPostmanEnabled=true
```

3. Run the following command to verify that specific or all the extensions are enabled:

kubectl get pods -n test-system

Result

The status of the specific extension or all the extensions in the pod is displayed as Running.

Results

You have enabled the required server extensions on HCL OneTest[™] Server.

Related information

Test authoring on page 130 Configuring a run of a JMeter test on page 408 Configuring a run of a JUnit test on page 414 Configuring a run of a Postman test on page 421 Configuration of a scan of an application code on page 444

Team space administration

You can find information about team spaces including the initial team space on HCL OneTest[™] Server along with the tasks that you can perform to administer a team space.

You can find the following information about team spaces:

- Team space overview on page 108
- Creating a team space on page 111
- Tasks in a team space on page 113
- Tasks in projects in a team space on page 117
- Management of licenses in HCL OneTest Server on page 119
- · Configuring an SMTP server to manage email notifications on page 771

Team space overview

Team spaces are logical partitions of HCL OneTest[™] Server. Team space is an exclusive, separate, and secure space on HCL OneTest[™] Server that enables you to share a single installation among multiple teams.

You can find the following information about team spaces:

- Initial team space on page 108
- Team spaces on page 109
- Migration from earlier releases of HCL OneTest Server on page 110

Initial team space

After you install HCL OneTest[™] Server and log in for the first time, you enter the **Initial team Space**.

The initial team space is the default logical partition that is created on an instance of HCL OneTest[™] Server.

As a server administrator, you must consider the following points:

- After you install HCL OneTest[™] Server and log in for the first time, the **Projects** page of the initial team space is displayed.
- You must configure the license server for the initial team space.
- Add or remove users in the team space and assign them different roles in a team space.
- You can assign the role of a *Team Space Owner* to any other member in the initial team space.
- Change the type of the initial team space from the default type of permissive.

The following table describes the type that you can assign to a team space:

Туре	Description
Permissive	Specifies that any licensed user of HCL OneTest [™] Server can access a team space and get assigned the default roles of a <i>Project Owner</i> and <i>Member</i> in the team space.
Restrictive	Specifies that all licensed users of HCL OneTest [™] Server must request for access to a team space and must be provided access and assigned roles by the <i>Team Space</i> <i>Owner</i> . The Restrictive type of team space can be either Public or Private . A Public team space is visible in the team spaces dashboard, while a Private team space is not visible in the team spaces dashboard.

• You can evaluate the requirement and create team spaces other than the initial team space.

As a licensed user, you must consider the following points:

- When you log in for the first time immediately after the installation of HCL OneTest[™] Server, the **Projects** page of the initial team space is displayed.
- After you log in to the initial team space, you are assigned the default roles of *Project Creator* and *Member* of the initial team space.
- On subsequent logins, the **My Projects** page in the initial team space is displayed as the default page.

Team spaces

You can either work with the initial team space or you can create multiple team spaces on HCL OneTest[™] Server. The team space facilitates users of the same team space to work together.

Apart from being a container for projects, a team space facilitates the registration of remote Docker hosts and Resource Monitoring agents, designing the system model, and viewing the registered agents, Dockers, or intercepts.

After you create a team space as a server administrator, you must consider the following actions:

Note: You are assigned the default role of a *Team Space Owner* for team spaces that you create.

- Add users in the team space and assign them different roles in a team space.
- Assign the role of a *Team Space Owner* to other team space members, if you want other members to own the team space.



Note: As a *Team Space Owner*, you can remove any member of your team space from the assigned role. The member who is removed from a team space, can send a request and become a member of that team space after the request is accepted.

- If the *Team Space Owner* is no longer a member of a team space, then you as the server administrator can access that team space with the default role of a *Team Space Owner*. You can then assign the role of a *Team Space Owner* to any other member.
- Delete the initial team space or any other team space that you created, if required.



Note: If you delete the initial team space, the users of the initial team space are redirected to the **Team Space Dashboard** page.

You as a server administrator or the *Team Space Owner* must perform the following tasks in a team space before other members can start using the team space:

- Configure the license server.
- Configure the team space type as either Restrictive or Permissive.
- Configure the SMTP server and add members who can receive notifications about the operations performed in the team space.

As a member of a team space, you must consider the following points:

- When you log in for the first time immediately after the installation of HCL OneTest[™] Server, the **Projects** page of the team space is displayed.
- After you log in to the team space, you are assigned the default roles of a *Project Creator*, and *Member* of the team space.
- You can request to become a member of any other team space. After your request is approved, you are assigned the default role of a *Member* of that team space.
- You can become a member of either a Permissive or Restrictive type of team space.
- On subsequent logins, the Team Space Dashboard page is displayed as the default page.

Migration from earlier releases of HCL OneTest[™] Server

The initial team space is the only logical partition in HCL OneTest[™] Server 10.1.3. If you migrate from an earlier release of HCL OneTest[™] Server to 10.2 or later, then all the assets and resources that you created and associated with the initial team space are migrated to associate with the initial team space in HCL OneTest[™] Server 10.2 or later.



The results of migration are as follows:

- All projects are contained in the initial team space.
- If you created a repository in a team space, then you can find the repository in the initial team space in 10.2.
- All Dockers, agents, and intercepts that you registered with the server are then registered with the initial team space and you can view from the **Agents and Intercepts** page of the initial team space.
- If you configured a resource monitoring agent in any project, then the details of the configured agent are available in the project.
- You can find the details of SMTP configuration on the server. Only you as a server administrator can view the details of SMTP configuration.
- The license server that is configured for the server for earlier release of HCL OneTest[™] Server is then configured for the initial team space.
- All users are assigned the role of a Project Creator and Architect of the initial team space.
- All users with server administrator roles are assigned the default role of a *Team Space Owner* of the initial team space.



- All users of earlier releases are migrated to HCL OneTest[™] Server 10.2 or later. You can view the list of all migrated users in the application only when they log into the application at least once.
- After you migrate the server data from a previous version to a newer version, the Project
 Owner must log in to HCL OneTest[™] Server so that other members of the project can access the test assets in that project.

Related information

Team space administration on page 108

Default user administration on page 85

Creating a team space

To manage projects in the logical containers of HCL OneTest[™] Server, you must create team spaces.

Before you begin

You must have been assigned the role of a server administrator of HCL OneTest[™] Server.

About this task

As a server administrator, you can create multiple team spaces on HCL OneTest™ Server.

1. Log in to HCL OneTest[™] Server.

Result

The Projects page of the initial team space is displayed.

2. Click the **Settings** icon from the left navigation pane, and then click **Create team space**.

Result

The New Team Space dialog is displayed.

3. Provide a name to the team space.

Result

The URL alias field is automatically filled.



Note: If you modify the name of a team space, the URL alias is also modified automatically.

4. Optional: Modify the URL alias for the team space, if required.



Note: You must enter the URL alias that starts with a letter.

- Select an option to set the permissions to access the team space. You can select any one of the following options:
 - Permissive When a team space is set as Permissive, the new user gets the permissions automatically on sending the request to become a member of that team space.
 - Restrictive When a team space is set as Restrictive, the Team Space Owner provides permission to the new user who becomes a member of that team space.

You can set the visibility mode of the Restrictive type team space as Public or Private.

- The Public team space is visible to all users in the Team Space Dashboard.
- The **Private** team space is visible only to the members of that team space in the **Team Space Dashboard**.

Note: If you select the Restrictive type team space, then the default setting of the team space becomes Public.

- 6. Provide a brief description of the team space.
- 7. Select the owner of the team space from the list of users who accessed the application.

The selected user is assigned the role of a Team Space Owner.



Note: You can assign the Team Space Owner role to only one user when you create a team space.

8. Click Create.

Result

The dashboard of the team space is displayed.

Results

You have created a team space.

If you are assigned the role of a *Team Space Owner*, then you can view the name of the team space that you created in the navigation pane.

If you assigned any other licensed user with the role of a *Team Space Owner*, then you can view the team space under the **Other Team Spaces** panel.

What to do next

You must configure the license for your team space. See Configuring licenses for team spaces on page 121.

Tasks in a team space

You can find information about the tasks that you can perform as a *Member*, *Project Owner*, *Architect*, or *Team Space Owner* in a team space on HCL OneTest[™] Server.

2	Initial team space		Any team space	
Persona	Role	Notes	Role	Notes
Server ad- ministrator	Team Space Own- er	Default role assigned	Team Space Own- er	Default role assigned
Licensed user	Team Space Own- er	Role assigned by Server ad- ministrator	Team Space Own- er	Role assigned by Server ad- ministrator
	Architect	Role assigned by Team Space Owner	Architect	Role assigned by Team Space Owner
	Project Creator	Default role assigned	Project Creator	 Default role assigned in a <i>Permissive</i> team space. Role assigned by <i>Team Space Owner</i> in a <i>Restrictive</i> team space.
	Member	Default role assigned	Member	Default role assigned in ei- ther a <i>Permissive</i> or <i>Restric-</i> <i>tive</i> team space.

The roles assigned in a team space for users are as follows:

The following table shows the tasks that can be performed by licensed users with their assigned roles in a team space:

Tasks	Team Space Owner	Architect	Project Creator	Member
Configuring licenses	~			
Configuring a Simple Mail Transfer Protocol (SMTP) server to send email notifications.	~			
Changing the license server configuration	~			
Adding members in a team space	~			
Assigning different roles to other team space members	~			
Modifying configuration details of a team space	~			
Deleting a team space	~			
Renaming a team space	~			
Adding or removing the team space repository from a team space	~	~		
Designing a system model	~	>		
Creating projects in a team space	~		~	
Adding, removing, or modifying remote Docker hosts	~	~	~	~
Adding agents	~	×	~	~
Adding, modifying, or removing resource moni- toring sources	~			
Connecting resource monitoring agents	~			
Adding resource monitoring labels	~			
Working with projects in a team space	~	~	~	~

The following table provides the links to the information about the tasks that can be performed by users with different roles in a team space:

Tasks	Roles	More information
Configuring a team space license server	Team Space Owner	Configuring licenses for team spaces on page 121
Configuring the Named Users	Team Space Owner	Adding users to the Named Users list on page 124

Tasks	Roles	More information
Modifying the configuration of a team space	Team Space Owner	Modifying the configuration of a team space on page 715
Viewing the configuration of a team space	All members of a team space	Viewing the configuration of a team space on page 717
Reassigning the role of team space members	Team Space Owner	Managing members and their roles in a team space on page 720
Becoming a team space member	 Team Space Owner All users can send a request 	Becoming a team space member on page 719
Viewing team spaces	All members of a team space	Viewing team spaces on page 711
	Notes:	
	• The Permissive and	
	public Restrictive	
	team spaces are visi-	
	ble to all the users.	
	The private Restric -	
	tive team spaces are only visible to its	
	members.	
Deleting a team space	Team Space Owner	Deleting a team space on page 723
Adding a project in a team space	Project Creator	Adding a project on page 727
Viewing existing projects	All members of a team space	Viewing active projects on page 732
Viewing details about the users or li- cense server	All members of a team space	Viewing license details of the team space on page 126
Installing remote agents and con- figuring them to register with HCL OneTest™ Server	All members of a team space	Management of agents on page 288
Registering a remote Docker host with HCL OneTest™ Server	All members of a team space	Registering a remote Docker host on page 303
Editing configurations of a remote Docker host	All members of a team space	Editing configurations of a remote Docker host on page 307

Tasks	Roles	More information
Unregistering a remote Docker host	All members of a team space	Unregistering a remote Docker host from HCL OneTest Server on page 311
Viewing remote agents, remote Dockers, or intercepts that are registered with HCL OneTest™ Server in the initial team space	All members of a team space	 Viewing remote Docker hosts that are registered with HCL OneTest Server on page 305 Viewing performance agents that are registered with HCL OneTest Server on page 290 Viewing intercepts that are registered with a team space on HCL OneTest Server on page 474
Adding resource monitoring sources and agents	Team Space Owner	Resource monitoring on page 547
Adding resource monitoring labels to the sources	Team Space Owner	Controlling resource monitoring sources in a schedule on page 581
Viewing the performance metrics	All members of a team space	Viewing resource monitoring usage data on page 588
Creating a model of the system un- der test	Architect	Creating a system model on page 256
Adding a repository to a team space	• Team Space Owner • Architect	Adding a repository to a team space on page 253
Viewing an existing system model	All members of a team space	Viewing the system model on page 275

Related information

Team space administration on page 108

Tasks in projects in a team space

You can find information about the roles that you can assign in a project for members of a team space and the tasks that you can perform in projects in a team space.

Members of a team space with the role of a *Project Creator* can create projects in the team space and become the *Owner* of a project. The owners of projects can add *Members* of the team space to a project and assign them the following roles:

- Owner
- Tester
- Viewer

For the list of actions that members assigned any of the roles can perform, see Managing access to server projects on page 734.

All projects are created in a team space. When you open a project, the options that are displayed in the navigation pane are specific to the projects within a team space.

When you are working on a project in a team space and you want to return to the options available to work in the team space, you can click the **Home** icon **a** in the navigation pane.



Note: You must be assigned the role of an Owner, a Tester, or a Viewer of a project.

The following table lists the tasks that members of a team space can perform while working with projects in a team space:

Tasks	More information
Viewing projects in a team space.	Viewing active projects on page 732
Adding a project.	Adding a project on page 727
Adding a repository that contains test assets and re- sources that you want to run on the server.	Adding repositories to a server project on page 728
Adding secrets to a secrets collection.	Secrets configuration on page 731
Encrypting the data set resources.	Data security
Configuring a change management system.	Configuration of a change management system on page 592
Adding members to a project and configuring their roles.	Adding users to a project on page 731
Selecting the global branch in a project to view the test assets and resources.	Selecting the global branch in a project on page 745

Tasks	More information
Adding agents to your project, if you are using remote agents as a location to run certain tests.	Adding a performance agent to a project on page 291
Adding remote Dockers, if you are using a remote Docker host as a location to run tests.	Adding a remote Docker host to the project for running tests on page 306
Reading the considerations that you must take into ac- count before you configure a test run.	Prerequisites to running tests on page 277
Reading the considerations that you must take into ac- count before you configure a run or start a virtual ser- vice.	Prerequisites for running virtual services on page 468
Configuring a run of the test assets.	Test run configurations on page 327
Configuring a run of the virtual service resource.	Configuring a run of a virtual service on page 478
Viewing the progress of a test run.	Viewing the progress of running test assets on page 457
Managing a running test.	Management of running tests on page 453
Viewing the results of a test run after the run is complet- ed.	Test results on page 513
Reviewing the test results and creating defects for test runs from the Results page.	Creating Jira issues for tests that ran on page 598

HCL license portal

Licensing for HCL OneTest[™] Server is administered through HCL Software License & Download portal. This portal is a FlexNet-based web application that helps to manage software entitlements and licenses.

When a software order is placed and acknowledged, a software entitlement is created. You must then follow the instructions in the Software Order Acknowledgment document that you receive to activate your entitlement, create devices, and download the software from the portal.

The license portal provides both software distribution and management of your software entitlements that are purchased from HCL Software. The portal provides control and flexibility on how to consume your licenses. An organization identifies one of its resources as a License Manager (also called Tech or Portal Admin) who is familiar with the language of licenses.

For more information about the HCL Software License & Download portal, you can refer to the following knowledge articles:

- What is the HCL Software License & Download portal (FlexNet portal)?
- How to find HCL Product Releases in HCL Software License & Download portal
- Managing Users on the HCL Software License & Download portal

Management of licenses in HCL OneTest[™] Server

As a *Team space Owner* or *Server Administrator*, you can configure and manage licenses for your team spaces in HCL OneTest[™] Server. As a member of any team space, you can only view the number of licenses that are configured for the team space. If you are not a member of any team space, you cannot view or perform any operations in any of the team spaces on HCL OneTest[™] Server.

You can get all the information of configured license server for different team spaces from various *Team Space Owners*. You can navigate to the HCL OneTest[™] Server Swagger UI by accessing the following URL:

https://myorg.com/#/Initial/admin/docs

Where myorg.com is the hostname of HCL OneTest[™] Server.

You can then open the **Licensing management** tab, and then click the **GET /rest/licensing/inventory** option. To generate the report that contains all the information of license server, you can click the **Try it out** option, and then click **Execute**.

The license inventory report contains information such as details about the configuration of team space licensing, a list of *Team Space Owners* and their email addresses, information about licenses that are mapped to the license server, and the current connectivity status of the license server.

Privileges	Tasks	More information
Team space Owner	Read about licensing on HCL OneTest™ Server.	Server software licensing information on page 120
OR Server Administrator	Configure licenses.	Configuring licenses for team spaces on page 121
	Configure named users.	Adding users to the Named Users list on page 124
	Remove or replace named users.	Removing or replacing named users on page 124
Licensed user	Perform tasks or operations in a team space.	Tasks in a team space on page 113
	Viewing details about licenses.	Viewing license details of the team space on page 126

Depending on your privileges, you can perform the following tasks in HCL OneTest™ Server:

Server software licensing information

You can find information about the licensing on HCL OneTest[™] Server.

To use the features offered by HCL OneTest[™] Server, you must purchase the following licenses:

- Named user
- Concurrent Virtual Service

Named user licenses

As a *Team space Owner*, you can configure the License Server and add users to the **Named Users** list for the team spaces.

The **Named user** licenses are automatically self-acquired on a first-come-first-serve basis. The licenses are always available for the users who are added to the **Named Users** list. Also, those users can perform the project tasks in their team space even though the **Disable automatic self-acquisition of named user licenses** checkbox is cleared in the **License Configuration** page. However, the other users receive an error notification about the unavailability of the license when they try to perform the project tasks.



Remember: A single **Named user** license is used from the total number of **Named user** licenses when you perform most of the operations in HCL OneTest[™] Server.

Important: You can perform only the following operations in team space without using a license:

- Configure the License Server
- Modify the user roles in a team space
- · Delete the team space

Remember: The Named user license is returned to the license pool only under any of the following conditions:

- When the Named user is no longer a member of any team space.
 - When the Named user is removed as a user of HCL OneTest[™] Server.

Important: The Named user license can take a few minutes to return to the license pool.

Concurrent Virtual Service licenses

HCL OneTest[™] Server requires an additional license to use the service virtualization feature. You must have sufficient **Concurrent Virtual Service** licenses to run instances of virtual services that are contained in API Suites on HCL OneTest[™] Server.

A single **Concurrent Virtual Service** is used from the total number of **Concurrent Virtual Service** licenses when any of the following events occur:

- An instance of a virtual service is started by running a virtual service resource. A license is consumed for every running instance of the virtual service.
- · An API suite is run that has a scenario that references a local virtual service and the scenario begins

The Concurrent Virtual Service license is returned to the license pool when the virtual service instance stops.

For example, consider you decided to have three team spaces including the initial team space, then you must configure the licenses required for each team space on the License Server based on your requirement. You must then use the URL and ID of those License Servers to configure the licenses for the team spaces.

Related information

Configuring licenses for team spaces on page 121

Configuring licenses for team spaces

As a *Team space Owner*, you can configure the License Server for the team spaces on the **License Configuration** page so that members of the team space can perform various operations such as creating a project, running tests, and so on.

Before you begin

You must have completed the following tasks:

- Configured the licenses that you purchased on the Licensing Server.
- Been assigned the role of a Team space Owner of the team space.

- Installed the product and signed up as a user on HCL OneTest[™] Server.
- Optional: Created a team space. See Creating a team space on page 111.

About this task

You must have a valid license to work with the team spaces that you create on HCL OneTest[™] Server. You must provide a separate URL and ID of the License Server for the team spaces when you configure the License Server. If you provided the URL and ID of the License Server that is already configured for any other team space, then the configuration of the license for the team space fails with an error message. If you delete the team space, then the URL and ID of the License Server used for that team space is released. You can then use that for another team space.

Note: When you upgrade the server software from the previous version to the latest version, then the license configuration of the previous release applies to the initial team space. You can verify the information from the License Configuration page of the initial team space.

- 1. Log in to HCL OneTest[™] Server.
- 2. Click the **Settings** icon ⁽²⁾ from the left navigation pane.
- 3. Open the team space for which you want to configure the license from the Switch to option.

Note: The **Switch to** option is displayed only if you have two or more team spaces.

4. Click the Settings icon (2014), and then License.

Result

The License Configuration page is displayed.

5. Enter the values in the License Server URL and License Server ID fields to configure the licenses for the team space.

Result

You can view the following messages based on the value that you enter in the License Server URL and License Server ID fields:

Values	Messages
No value	Add the missing license details or enter the License Server URL.
Incorrect format of the License Server URL or License Server ID	This is not a valid format of the License Server URL or License Server ID.
Correct value	License Server is already in use by another team space owner

6. Perform the following actions to view or hide the details of the License Server:

Note: The default status of the License Server URL and License Server ID fields are hidden.

Fields	Icons	Ac- tion	Results
 License Server URL 	0	Click	HCL OneTest [™] Server shows the URL and ID of the License Server that you have configured.
∘ License Server ID	Ø	Click	HCL OneTest [™] Server hides the URL and ID of the License Server that you have configured.

7. **Optional:** Click **Check connection** to verify the current status of License Server.

Based on the availability of License Server, you can view the following messages:

• License Server is available

- License Server is unreachable
- Select the Disable automatic self-acquisition of named user licenses option if you do not want to self-acquire Named users license on a first-come-first-serve basis for your team space.

The following table describes the functionality of the **Disable automatic self-acquisition of named user licenses** option:

Option	When	Description
Disable automat- ic self-acquisi-	Cleared	Any member of a team space can get a license when there are sufficient licens- es are available for the team space.
tion of named user licenses	Select- ed ⊠	Only such users who are added to the Named Users list get a license to per- form the tasks in their team space. If other users try to perform any project op- erations in any of the team spaces, they cannot get a license even if sufficient licenses are available.

9. Click **Configure** to apply the license configuration.

Results

You have configured the license for the team space.

The License usage section displays the number of **Named user** licenses that are currently in use. However, the License usage section does not display the number of **Concurrent Virtual Service** licenses that are currently in use.

The License configuration section displays the number of Named user, Concurrent Virtual Service, and Studio licenses that are configured on the License Server.

What to do next

You can perform any of the following tasks:

- Add users to the Named Users list. See Adding users to the Named Users list on page 124.
- Add members to your team space. See Adding members to a team space on page 712.

Adding users to the Named Users list

As a *Team space Owner*, you can add users to the **Named Users** list so that the licenses are always available for those users.

Before you begin

You must have completed the following tasks:

- Been assigned the role of a Team space Owner of the team space.
- Optional: Created a team space. See Creating a team space on page 111.
- Configured the license for the team space. See Configuring licenses for team spaces on page 121
- 1. Log in to HCL OneTest[™] Server.
- 2. Click the **Settings** icon ^{III} from the left navigation pane.
- 3. Open the team space for which you want to add users from the Switch to option.
- 4. Click the Settings icon 2, and then License.

Result

The License Configuration page is displayed.

5. Enter the name or the email ID of the user in the **Add named users** field, and then select the name from the list that displays to add members to the **Named Users** list.



Note: You can press ${\tt ctrl}$ to select multiple users simultaneously.

6. Click Add to make selected users as Named users.

Results

You have added users to the Named Users list.



Remember: The **License usage** section does not display the number of **Concurrent Virtual Service** licenses that are currently in use.

Removing or replacing named users

When you want to remove a user from the list of named users or you want to replace an existing user with another named user, you as a *Team space Owner* can perform these changes from the **License Configuration** page.

Before you begin

You must have completed the following tasks:

- Been assigned the role of a *Team space Owner* for the team space that you want to modify the users from the **Named Users** list.
- Added users to the list of named users for the team space on HCL OneTest[™] Server.
- 1. Log in to HCL OneTest[™] Server.
- 2. Click the **Settings** icon ³ from the left navigation pane.
- 3. Open the team space for which you want to remove or replace the users from the **Named users** list from the **Switch to** option.
- 4. Click the **Settings** icon and then **License**.

Result

The License Configuration page is displayed.

5. Perform the actions described in the following table to remove or replace users from the Named Users list:

Tasks	Actions
Remove a user	Perform the following steps:
from the list of named users.	a. Locate the user that you want to remove from the Named Users list.
	b. Click the Menu icon next to the name of the user, and then click Remove .
	c. Click Remove on the Remove named user dialog to complete the action.
	Remember:
	 When the Disable automatic self-acquisition of named user licens- es option is cleared, and if the user who is removed from the Named Users list tries to perform any project operation, then the name of the user is added back to the list. The name of the user is added only if sufficient licenses are available.
	 When the Disable automatic self-acquisition of named user licenses option is selected and you remove the user from the Named Users list, then the following operations are impacted by the user who is removed from the list:

Tasks	Actions
	 The test runs scheduled by the user might fail to run. The test results which are in progress by the user might fail to record complete details. The user cannot perform any of the project operations that include the generation of offline tokens that are used for long-run tests. Note: If the user is currently on HCL OneTest[™] Server, then the license can be used while the current session remains active.
Replace a user in the list of named users.	 Perform the following steps: a. Locate the user from the Named Users list that you want to replace with another user. b. Click the Menu icon next to the name of the user, and then click Replace. c. Enter the email ID or name of another user that you want to add to the Named Users list.
	d. Click Replace to complete the action.

Results

You have removed or replaced a user from the Named Users list.

Viewing license details of the team space

You can view license details of the team space to know information such as number of licenses that are configured, licensed users or details of the License Server on the **License Configuration** page.

Before you begin

The Team space Owner must have configured the licenses for the team spaces on HCL OneTest™ Server.

About this task

You as a licensed user can view only the number of licenses configured, details of the licensed users on the **License Configuration** page. However, if you are a *Team space Owner* or *Server Administrator*, you can also view the URL and ID of the License Server that is configured for the team space.

- 1. Log in to HCL OneTest[™] Server.
- 2. Perform one of the following actions described in the following table to view the license details of the team space:

Roles	Action
Team space Owner	Perform Steps 3 on page 127 to 6 on page 127.
or	
Server Administrator	
Any other users	Perform Steps 3 on page 127 to 5 on page 127.

- 3. Click the **Settings** icon ²⁶ from the left navigation pane.
- 4. Open the team space for which you want to view the license details from the **Switch to** option.

Note: The Switch to option is displayed only if you have multiple team spaces.

5. Click the Settings icon ⁽²⁾, and then License. Result

The License Configuration page is displayed with the following license information:

- \circ The number of Named user licenses that are currently in use.
- \circ The number of Named user licenses that are configured on the License Server.
- The number of **Concurrent Virtual Service** licenses that are configured on the License Server.
- \circ The number of $\ensuremath{\textit{Studio}}$ licenses that are configured on the License Server.
- The status of License Server.
- Whether the self-acquisition of named user licenses feature is enabled or disabled.
- The name and email ID of the users that are configured as named users by the Team space Owner.
- **Remember:** The License usage section does not display the number of Concurrent Virtual Service licenses that are currently in use.
- 6. Perform the following actions to view or hide the details of the License Server:

Fields	Icons	Ac- tion	Results
 License Server URL 	0	Click	HCL OneTest [™] Server shows the URL and ID of the License Server that you have configured.
∘ License Server ID	Ø	Click	HCL OneTest [™] Server hides the URL and ID of the License Server that you have configured.

Results

You have viewed the details about the licenses for the team space.

Chapter 5. Test Author Guide

This guide describes how to create test assets in HCL OneTest[™] Server and publish test assets to the Git repository that you have configured. You can also edit existing test assets that are in the repository added to your project. This guide is intended for testers and test managers.

Edit branch overview

When you want to create or modify any test assets in HCL OneTest[™] Server, you must use an Edit branch.

You must be a *Team Space Owner*, *Project Owner*, or *Member* with a Tester role to create or edit test assets. You can create the Edit branch during the creation or modification of any test assets. You can create or select the Edit branch from HCL OneTest[™] Server as shown in the following table:

HCL	Actions				
OneTest™ Server UI	Test assets creation	Test assets modification	Edit branch creation	Edit branch selection	
Author > Datasets	Yes	Yes	Yes	Yes	
Author > Changes	No	Yes	No	Yes	
Author > Tests	Yes	Yes	Yes	Yes	
Execute > Execution	No	Yes	Yes	Yes	

While you provide a name for the Edit branch, you must adhere to the rules of Git branch naming conventions. For more information, refer to the Git documentation. When you create the Edit branch, any member of the project can use your Edit branch while the branch is available. You can also view all the Edit branches from the **Branch** drop-down list when other members of the project create Edit branches.

To differentiate the remote branch and Edit branch from the **Branch** drop-down list, an edit icon 2° and the initials of the member who created the Edit branch are shown for the Edit branch. After you create the Edit branch, you can also view the Edit branch by accessing the remote Git repository from a browser.

After you create or edit the test assets, you can either publish the test assets to a remote Git repository or discard the changes made to the test assets. All created or modified test assets reside in the Edit branch until you publish or discard the changes made to the test assets.

The Edit branch automatically disappears from the **Branch** drop-down list and remote Git repository when you perform any of the following actions:

- · Publish changes to the remote Git repository
- · Discard the changes made in all test assets



Note: After the Edit branch disappears, the Branch field is set to the previously selected branch name.

Test authoring

You can use HCL OneTest[™] Server to author tests instead of creating the tests by using the desktop products.

HCL OneTest[™] Server provides you with the test authoring capability, which utilizes a containerized version of the HCL OneTest[™] Studio desktop authoring tools.

Refer to the following table to know about the default status of the test authoring feature during server installation:

Server installation	Test authoring feature
Ubuntu Server (using k3s)	Disabled
Azure Kubernetes Service	Enabled

lmportant:

By design, the test authoring feature provides you with the capability to author and edit tests that include writing code, executing code, and accessing the shell. The container in Kubernetes that is used by the test authoring or editing feature does not run as root and the container is not privileged. Hence, it results in providing some protection to the host and other workloads that run on the same node.

You must not install the test authoring feature in the following scenarios:

- If you administer a network policy for your server installation.
- If you do not intend to use the test authoring feature.

Note: If you are installing the server on the Azure Kubernetes Service platform and you do not want to use the test authoring feature, you must run a helm command to turn off the installing of the test authoring feature.

Prerequisites for authoring tests

You must be familiar with the methods for authoring or creating tests in any of the following desktop products before you can use the test authoring capabilities in HCL OneTest[™] Server:

- HCL OneTest[™] API
- HCL OneTest[™] Performance
- HCL OneTest[™] UI

You must ensure that you have not disabled the test authoring feature at the time of installation of HCL OneTest[™] Server or any time after installation.

You must be a Team Space Owner, Project Owner or Member with Tester role to create or edit tests.

Working with the test authoring feature

You must create a project in your team space on HCL OneTest[™] Server and add a repository to your project.

You must enable the browser that you use to start an instance of HCL OneTest[™] Server to trust the self-signed certificate so that the containerized product can be displayed in another tab of the same browser. See Certificate authority: Importing and extending lists on page 97.

A containerized version of the HCL OneTest[™] Studio desktop authoring tools is launched on a new browser tab different from the tab that displays the HCL OneTest[™] Server instance when you initiate any of the following tasks on HCL OneTest[™] Server:

- Create a test in a branch of the project repository.
- Edit a test in a branch of the project repository.

You must select the type of test that you want to create. After you select the type of test, the corresponding containerized product is displayed in a new browser tab. Refer to the following table for the types of tests that you can create in the containerized product:

Test type selected	Containerized product displayed	Supported tests that you can create
API test	HCL OneTest™ API	The following test types are support- ed:
		 API Test Suite API tests Virtual services Postman resources
Functional test	HCL OneTest™ UI	The following test types are support-
Performance test		ed :

Test type selected	Containerized product displayed	Supported tests that you can create
	Note: This is a shell-shared version with HCL OneTest [™] Performance with which you can create both functional tests and performance tests.	 AFT Suite Compound tests that contain any of the following types of tests: HTML tests Performance tests Web UI tests JMeter tests JUnit tests Functional Web UI tests Performance tests Rate Schedules VU Schedules

The containerized product displays the product GUI similar to the desktop product. You must use the options similar to the desktop product to create the tests in the containerized products. Refer to the following table for the supported technologies and features in the containerized products in comparison with the desktop products:

Container- ized product	Supported features	Suț	oported tech	nologies	
HCL OneTest™ API	excluding the following features:	All technologies as following technolog tests: Transport			-
	 Rules Cache in the Architectural School perspective. Monitoring logging of tests in the Test Factory view. Results Gallery. Results Publishing and Quality Management in the Project Settings UI. Test Cycles, General Tool Configuration, Project Security, and Ant task. 	FIX Mongo TCP Server UDP Server CICS Region IMS Connect Software AG IS Database z/OS DB2	Yes Yes No Yes Yes Yes No No	No No No No No No No	No No No No No No No

Container- ized product	Supported features	Supported technologies
HCL OneTest™ UI	All features as in the desktop prod-	All technologies as in the desktop products.
shell-shared with	ucts.	
HCL OneTest™		
Performance		

You can refer to the product documentation of the desktop products to find information about the specific tasks that you want to perform in the containerized product. Use the following links to the product documentation:

- HCL OneTest[™] Performance documentation
- HCL OneTest[™] UI documentation
- HCL OneTest[™] API documentation

After you create the test in the containerized product, you must save the test assets or resources to the branch in the repository of your project. You accomplish committing the assets or resources by publishing them.

You can pause your test creation activities in the containerized product and resume the task in the following conditions:

- When you do not delete the ongoing session in the browser tab with the containerized product.
- When you resume the test authoring session within 8 hours of pausing the task.



Important: You might not be able to continue with the test creation activities if you close the browser and delete the session with the containerized product.

After the created test assets are published to the project repository, you can run the test assets from the **Execution** page or the virtual services from the **Resources** page.

When you want to edit the created tests or other tests that are in the project repository, you can open the test in the containerized product and use the containerized product to edit the test. After you edit the test, you must publish the test assets to the repository so that the edited test asset is available for a run.

Limitations when using the test authoring feature

You can initiate only one session to either create or edit a test in the containerized product.

When you open a test for editing, the browser displays a message whether you want to view copied text and images on the clipboard. You must choose **Allow** so that the test is opened for editing.

Note: If you select Block, the test is not opened for editing.

When you create a Performance test or Functional test for the first time in the containerized product, after the product is loaded in a new browser, the **New Test From Recording** window is displayed. You can ignore this message by clicking **Cancel** and continue with test creation in the containerized product.

When you work in the containerized HCL OneTest[™] UI on Performance or Functional tests, you can do any of the following actions to display the context menu:

- Press Shift+F10
- · Keep the right mouse key pressed for a few seconds

When you work in the containerized HCL OneTest[™] API to create or edit API tests or resources and if you want to copy and paste API tests or resources, then you must use the Context menu by selecting **Edit > Copy** and then click **Edit > Paste**.



Note: The shortcut keys Ctrl+C and Crtl+V do not work to copy and paste API test resources.

The window size control options do not work in the HCL OneTest™ API containerized product.

Creating tests or virtual service resources

You can create tests or virtual service resources by using the test authoring capabilities of HCL OneTest[™] Server. After you create and publish the test assets or resources to a branch in your project repository, you can run the tests or virtual service resources on HCL OneTest[™] Server.

Before you begin

You must have completed the following tasks:

- Read the information presented in Prerequisites for authoring tests on page 130 and Working with the test authoring feature on page 131.
- Created a project in HCL OneTest[™] Server. See Adding a project on page 727.
- Added a Git repository to your project. See Adding repositories to a server project on page 728.
- 1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

2. Open the project, and then click Author > Tests.

The existing test assets in the branch of the project repository are displayed if they exist.

The details such as test design considerations, the load test profile, or other details that you entered as properties of the test asset in the desktop products are displayed in the **Description** column.

3. Click Create test, and then select the type of test assets that you want to create.

You can select any of the following types of tests:

- API test
- Functional test
- Performance test

After you select the type of test, the corresponding containerized product is displayed in a new browser tab. Refer to the following table for the types of tests or virtual services that you can create in the containerized product:

Test type selected	Containerized product displayed	Supported tests that you can create
API test	HCL OneTest™ API	The following test types are sup- ported: • API Test Suite • API tests • Virtual services • Postman resources
Functional test	HCL OneTest™ UI	The following test types are sup-
Performance test	Note: This is a shell- shared version with HCL OneTest [™] Performance with which you can create both functional tests and performance tests.	ported : • AFT Suite • Compound tests that con- tain any of the following types of tests: • HTML tests • Performance tests • Web UI tests • JUnit tests • JUnit tests • Functional Web UI tests • Performance tests • Rate Schedules • VU Schedules

The containerized product displays the product GUI similar to the desktop product. You must use the options similar to the desktop product to create the tests or virtual services in the containerized products.

4. Create the test or virtual services by using the containerized product.

You can refer to the product documentation of the desktop products to find information about the specific tasks that you want to perform in the containerized product. Use the following links to the product documentation:

- HCL OneTest[™] Performance documentation
- HCL OneTest[™] UI documentation
- HCL OneTest[™] API documentation
- 5. Save and commit the test assets or virtual service resources to the Git repository that is configured in your project from the containerized product.
- 6. Delete the containerized product session by closing the browser tab of the containerized product, and then click **Delete session**.

The test assets that you created in the containerized product are displayed in the **TESTS** tab. The virtual services that you create are displayed on the **Resources** page.

- 7. Click Author > Changes.
- 8. Select the Git repository to which the test asset or resource was committed in the containerized product.
- 9. Click Publish.

Publishing the test assets or resources to the Git repository makes the test assets or resources to be available to other members of your project.

Results

You created a test by using the containerized product on HCL OneTest[™] Server.

What to do next

You can configure a run of the tests that you created. See Test run configurations on page 327.

If you created virtual services in the containerized HCL OneTest[™] API product, you can configure a run of the virtual services. See Configuring a run of a virtual service on page 478.

Editing a test

You can modify an existing test asset that you created from the desktop product or a test that you created in the containerized product on HCL OneTest[™] Server. After you publish the edited test to a branch in your project repository, you can run the test on HCL OneTest[™] Server.

Before you begin

You must have completed the following tasks:

- Created a project in HCL OneTest[™] Server. See Adding a project on page 727.
- Added a Git repository to your project. See Adding repositories to a server project on page 728.
- Created a test asset by using the containerized product on HCL OneTest[™] Server. See Creating tests or virtual service resources on page 134.
- 1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

2. Open the project, and then click **Author > Tests**.

The existing test assets in the branch of the project repository are displayed if they exist.

The details such as test design considerations, the load test profile, or other details that you entered as properties of the test asset in the desktop products are displayed in the **Description** column.

3. Select the branch of the repository that contains the test assets.

The test assets that are contained in the selected branch of the repository are displayed in the following tabs on the **Tests** page:

Tab	Description
SUITES	Lists all suites, compound tests, JMeter tests, JUnit tests, Postman tests, Rate Sched- ules, or VU Schedules that are in the selected branch of the repository.
TESTS	Lists all API tests, functional tests, or performance tests that are in the selected branch of the repository.
ADVANCED	Lists all assets that are displayed when custom filters are applied for assets in the se- lected branch of the repository.

- 4. Identify the test asset that you want to edit by performing any of the following actions:
 - Scroll through the list.



Tip: You can hover over the icon in the Type column to know the type of the test asset.

Note: You can also identify the type of the asset from the icon that represents the test type as shown in the following table:

lcon	Represents	Listed in the SUITES tab	Listed in the TESTS tab	Listed in the AD- VANCED tab
-63-	API test		0	0
۲	Functional test		0	0
٢	Performance test		0	0
	AFT Suite	0		0
4	API Suite	0		0

lcon	Represents	Listed in the SUITES tab	Listed in the TESTS tab	Listed in the AD- VANCED tab
8 9	Compound Test	0		0
0	HCL AppScan CodeSweep	0		0
/JMeter"	JMeter Test	0		0
Ju	JUnit Test	0		0
0	Postman test	0		0
0	Rate Schedule	0		0
9	VU Schedule	0		0

- Enter any text, that is contained in the test asset name, in the Search field.
- Click the **Filter** icon **Y** in the **SUITES** or **TESTS** tab to filter the displayed assets based on the asset type.

For example, select **API Suite** in the **SUITES** tab to display all the API suites or select **Functional Test** in the **TESTS** tab to display all the functional tests that are available in the selected branch of the repository.

- Click the **Filter** icon **W** in the **ADVANCED** tab, and then create a filter query by using the **New filter** option by performing the following steps:
 - a. Click New filter.
 - b. Enter a name for the filter.
 - c. Select an operator, and add a rule, or a group of rules.
 - d. Add or enter the relevant parameters and either select or enter the condition and the criteria for the condition.

You can select a parameter from the following list:

- Type
- Test Asset Name
- Test Asset Path
- Description

e. Save the filter query to save and apply the filter query to filter the assets based on the query.

The test assets that match the filter criteria are displayed.

 Retrieve and apply a saved filter query, if you have saved filter queries previously by performing the following steps:

Note: The filter query applied previously is selected and the assets based on that filter query are displayed. To apply a different filter query, you must have created and saved the filter query.

a. Click the **Filter** icon \mathbf{Y} in the **ADVANCED** tab.

The filter queries that you created and saved are displayed.

b. Click the filter that you want to apply.

The test assets that match the filter criteria are displayed.

You have identified the test asset that you want to edit.

5. Click the **Edit** icon \checkmark in the **Actions** column of the test asset.

Based on the type of test asset that you select, the corresponding containerized product is displayed in a new browser tab as detailed in the following table.

Note: If you are presented with a message prompting you to allow the content to be copied on the clipboard, select **Allow** and continue with your task.

Test asset type selected	Containerized product displayed
 API Test Suite API tests Postman tests 	HCL OneTest™ API
 AFT Suite Compound tests that contain any of the following types of tests: 	HCL OneTest™ UI

Test asset type selected	Containerized product displayed
 HTML tests Performance tests Web UI tests JMeter tests JUnit tests Functional Web UI tests Performance tests Rate Schedules VU Schedules 	Note: This is a shell-shared version with HCL OneTest [™] Performance with which you can create both functional tests and performance tests.

The containerized product displays the product GUI similar to the desktop product. You must use the options similar to the desktop product to edit the tests in the containerized products.

6. Edit the test by using the containerized product.

You can refer to the product documentation of the desktop products to find information about the specific tasks that you want to perform in the containerized product. Use the following links to the product documentation:

- HCL OneTest[™] API documentation
- HCL OneTest[™] UI documentation
- HCL OneTest[™] Performance documentation
- 7. Save and commit the test assets or virtual service resources to the Git repository that is configured in your project from the containerized product.
- 8. Delete the containerized product session by closing the browser tab of the containerized product, and then click **Delete session**.
- 9. Click Author > Changes.
- 10. Select the Git repository to which the test asset or resource was committed in the containerized product.
- 11. Click Publish.

Publishing the test assets or resources to the Git repository makes the test assets or resources to be available to other members of your project.

Results

You edited a test by using the containerized product on HCL OneTest[™] Server.

What to do next

You can configure a run of the tests that you edited. See Test run configurations on page 327.

Editing virtual service resources

You can modify an existing virtual service resource that you created from the desktop product or a virtual service resource that you created in the containerized product on HCL OneTest[™] Server. After you commit the edited virtual

service resource to a branch in your project repository, you can start an instance of the virtual service resource on HCL OneTest[™] Server.

Before you begin

You must have completed the following tasks:

- Created a project in HCL OneTest[™] Server. See Adding a project on page 727.
- Added a Git repository to your project. See Adding repositories to a server project on page 728.
- Created virtual service resources by using the containerized product on HCL OneTest[™] Server. See Creating tests or virtual service resources on page 134.
- 1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

 Open the project that contains the virtual service resources in the test assets by clicking Projects > My Projects > project_name.

The **Overview** page is displayed.

3. Click Virtualization > Resources in the navigation pane.

The **Resources** page is displayed.

4. Select the branch of the repository that contains the virtual services that you want to edit from the list in the **Branch** field.

All virtual services in the selected branch are displayed on the Resources page.

- 5. Identify the virtual service by completing any of the following steps:
 - Search for the virtual service by entering the name or the path of the virtual service in the repository in the Search field box.
 - Create a filter query by using the New filter option and complete the following steps:
 - a. Create a rule with an appropriate operator.
 - b. Select criteria such as *Name, Path, Instance number,* or *Instance state.* Select the condition and enter the value for the criteria. Apply the filter query.

The virtual services that match the filter criteria are displayed.

- c. Save the filter query for retrieving it from the saved filters list.
- Retrieve a saved filter by using the **Open filters** icon = by completing the following steps:

Note: To open the filter query, you must have created and saved a filter query.

- a. Select the saved filter.
- b. Apply the filter.

The virtual services that match the filter criteria in the filter that is applied are displayed.

6. Click the **Edit** icon \checkmark in the **Actions** column of the virtual service resource.

The containerized HCL OneTest[™] API UI is displayed in a new browser tab.



Note: If you are presented with a message prompting you to allow the content to be copied on the clipboard, select **Allow** and continue with your task.

7. Edit the virtual service resource by using the containerized product.

You can refer to the HCL OneTest[™] API product documentation to find information about the specific tasks that you want to perform. See HCL OneTest[™] API Product Documentation.

- 8. Save and commit the virtual service resources to the Git repository that is configured in your project from the containerized product.
- 9. Delete the containerized product session by closing the browser tab of the containerized product, and then click **Delete session**.

Results

You edited the virtual service resources by using the containerized product on HCL OneTest[™] Server.

What to do next

You can configure a run of the virtual service resource that you edited. See Configuring a run of a virtual service on page 478.

Datasets overview

A dataset provides tests with variable data during a run. The test that uses a dataset at run time replaces a value in the recorded test with variable test data that is stored in the dataset.

In HCL OneTest[™] Server, you can create a dataset and use it to replace the dataset values with original values during run time, when you want to run test assets that contain the dataset.

Actions	Descriptions	
View	You can view the contents of a dataset. See Viewing a dataset on page 161.	

You can perform the following actions from Author > Datasets:

Actions	Descriptions	
Create	You can create a dataset to use it during a test or schedule run. See Creating a dataset on page 144.	
Edit	You can edit a dataset when you want to run a test asset with different dataset values. See Edit- ing a dataset on page 150.	
Delete	You can delete the dataset when it is not required in your test environment. See Deleting a dataset on page 163.	
Save As	You can save a copy of a dataset in a different folder or make a copy with a different name by clicking the Menu icon and then by selecting the Save As option.	
Branch selection	You can view the dataset listed in the other branches of the repository by selecting the name of the branch from the Branch list. When you access the Datasets page for the first time after adding the repository, the global branch is set to the default branch of the repository. When multiple repositories are added to the same project, the following events occur: • The datasets stored in the selected branch of all the repositories are displayed. • All the branches in all the repositories are listed in the drop-down list. • If the selected branch is not present in a repository, then datasets from that repository are not displayed.	

Notes:

- Only a project **Owner** or a project member whose role is a **Tester** can view and edit the dataset.
- To view the content of an encrypted dataset, you must provide an encryption key that you set while encrypting the dataset column.
- As a **Viewer**, when you try to access the **Datasets** page, an error message is displayed because you do not have the permission to view this page.

You can create a dataset in HCL OneTest[™] Server by using any of the following method:

- Empty dataset
- CSV file
- Data fabrication

Creating a dataset

You can create datasets in HCL OneTest[™] Server to replace the values of existing dataset with the values of new dataset during a test or schedule run.

Before you begin

You must be a member of the project with the **Owner** or **Tester** role, and you must have completed the following tasks:

- Created a project in HCL OneTest[™] Server. See Adding a project on page 727.
- Added a Git repository to your project. See Adding repositories to a server project on page 728.

About this task

The default dimension of the dataset that you create in HCL OneTest[™] Server is 1 Row, 1 Column (1R X 1C) dataset. You can enter the number of columns and rows required for the dataset during the creation of dataset.

When you want to create or modify any dataset, you must have an edit branch. You can create the edit branch during the creation of dataset. All your dataset reside in the edit branch until you publish or discard the changes.

After you create the dataset, you can either publish your changes to a remote Git repository or you can discard the changes made to the dataset. The edit branch automatically disappears from the **Branch** list as well as from the remote Git repository and sets the global branch to the previously selected branch in the following conditions:

- When you publish changes to the remote Git repository.
- When you discard the changes made in the dataset.
- 1. Log in to HCL OneTest[™] Server if you are not already logged in.
- 2. Open a project from the team space.
- 3. Go to Author > Datasets, and then select the Branch from the list where you want to store the dataset.
- 4. Click Create dataset.

Based on the Branch that you selected, the following window is displayed:

- Edit Branch If you selected other than the edit branch.
- Create dataset If you selected the edit branch.
- 5. Perform one of the steps described in the following table to select or create the edit branch:

Step description	Step no
To select the edit branch	Perform 5.a on page 145
To create the edit branch	Perform 5.b on page 145

- a. Perform the following steps to select the edit branch:
 - i. Choose the edit branch from the **Select branch** drop-down list if the edit branches are already existing.
 - ii. Click **Ok**.
- b. Perform the following steps to create the edit branch:
 - i. Select Create new branch.
 - ii. Provide a name for the edit branch.
 - iii. Click Save.
- 6. Enter a name for the dataset in the Asset name field.
- 7. Select the place where you want to save the dataset in the Location field, and then click Next.
- 8. Choose Create an empty dataset from the Select source list.
- 9. Enter the number of columns and rows required for the dataset that you want to create.
- 10. Click Create.

Result

The new dataset opens in a CSV Editor in a web browser. The dataset created is listed on the Datasets page.

Results

You have created the dataset in your project.

What to do next

You can perform the following tasks:

- Add, modify, or remove data in the dataset. See Editing a dataset on page 150.
- Publish the dataset to the Git repository so that other members of the project can use the dataset. See Publishing a dataset on page 160.

Creating a dataset by using a CSV file

When a CSV files contains a large amount of data, you can use such CSV fie to create a dataset in HCL OneTest[™] Server.

Before you begin

You must be a member of the project with the **Owner** or **Tester** role, and you must have completed the following tasks:

- Created a project in HCL OneTest[™] Server. See Adding a project on page 727.
- Added a Git repository to your project. See Adding repositories to a server project on page 728.
- Saved a CSV file that contains variable data on your computer.

About this task

When you want to create or modify any dataset, you must have an edit branch. You can create the edit branch during the creation of dataset. All your dataset reside in the edit branch until you publish or discard the changes.

After you create the dataset, you can either publish your changes to a remote Git repository or you can discard the changes made to the dataset. The edit branch automatically disappears from the **Branch** list as well as from the remote Git repository and sets the global branch to the previously selected branch in the following conditions:

- When you publish changes to the remote Git repository.
- When you discard the changes made in the dataset.
- 1. Log in to HCL OneTest[™] Server if you are not already logged in.
- 2. Open a project from the team space.
- 3. Go to Author > Datasets, and then select the Branch from the list where you want to store the dataset.
- 4. Click Create dataset.

Based on the Branch that you selected, the following window is displayed:

- Edit Branch If you selected other than the edit branch.
- Create dataset If you selected the edit branch.
- 5. Perform one of the steps described in the following table to select or create the edit branch:

Step description	Step no
To select the edit branch	Perform 5.a on page 147
To create the edit branch	Perform 5.b on page 147

- a. Perform the following steps to select the edit branch:
 - i. Choose the edit branch from the **Select branch** drop-down list if the edit branches are already existing.
 - ii. Click Ok.
- b. Perform the following steps to create the edit branch:
 - i. Select Create new branch.
 - ii. Provide a name for the edit branch.
 - iii. Click Save.
- 6. Enter a name for the dataset in the Asset name field.
- 7. Select the place where you want to save the dataset in the Location field, and then click Next.
- 8. Choose Import from a CSV file from the Select source list.
- 9. Click Select File and choose the CSV file that contains variable data to import into the dataset.
- 10. Enable First row contains headers by using the toggle icon if the CSV file contains the header.
- 11. Click Create.

Result

The new dataset opens in a CSV Editor in a web browser. The dataset created is listed on the Datasets page.

Results

You have created the dataset by using the CSV file in your project.

What to do next

You can perform the following tasks:

- Add, modify, or remove data in the dataset. See Editing a dataset on page 150.
- Publish the dataset to the Git repository so that other members of the project can use the dataset. See Publishing a dataset on page 160.

Creating a dataset by using data fabrication

When you create a schema to generate different types of data by using data fabrication, you can use that schema to create a dataset in HCL OneTest[™] Server.

Before you begin

You must be a member of the project with the **Owner** or **Tester** role, and you must have completed the following tasks:

- Created a project in HCL OneTest[™] Server. See Adding a project on page 727.
- Added a Git repository to your project. See Adding repositories to a server project on page 728.
- Created a schema fabrication in your project. See Schema fabrication on page 165.

About this task

In HCL OneTest[™] Server, from the **Data Fabrication** page, you can create schemas that can be used to create a dataset.

For example, after you record a test, the test captures interactions between the client and the server. When you run the test, it uses the same data that you used during the recording. When you want to test the application with random test data, you can create the dataset by using a schema that you created from the **Data Fabrication** page of HCL OneTest[™] Server.

When you want to create or modify any dataset, you must have an edit branch. You can create the edit branch during the creation of dataset. All your dataset reside in the edit branch until you publish or discard the changes.

After you create the dataset, you can either publish your changes to a remote Git repository or you can discard the changes made to the dataset. The edit branch automatically disappears from the **Branch** list as well as from the remote Git repository and sets the global branch to the previously selected branch in the following conditions:

- When you publish changes to the remote Git repository.
- When you discard the changes made in the dataset.
- 1. Log in to HCL OneTest[™] Server if you are not already logged in.
- 2. Open a project from the team space.
- 3. Go to Author > Datasets, and then select the Branch from the list where you want to store the dataset.
- 4. Click Create dataset.

Based on the Branch that you selected, the following window is displayed:

• Edit Branch - If you selected other than the edit branch.

• Create dataset - If you selected the edit branch.

5. Perform one of the steps described in the following table to select or create the edit branch:

Step description	Step no
To select the edit branch	Perform 5.a on page 149
To create the edit branch	Perform 5.b on page 149

- a. Perform the following steps to select the edit branch:
 - i. Choose the edit branch from the **Select branch** drop-down list if the edit branches are already existing.
 - ii. Click Ok.
- b. Perform the following steps to create the edit branch:
 - i. Select Create new branch.
 - ii. Provide a name for the edit branch.
 - iii. Click Save.
- 6. Enter a name for the dataset in the Asset name field.
- 7. Select the place where you want to save the dataset in the Location field, and then click Next.
- 8. Choose Fabricate data from the Select source list.
- 9. Select a schema for data fabrication from the drop-down list.

The list displays schemas that you have created only in your project.

- 10. Enter the number of rows that you want to generate in the Number of Rows field.
- 11. Enter a seed value in the Seed (optional) field.

Whenever you generate test data to perform application testing, the generated data is different. You can produce the same set of data multiple times by setting the seed value.

For example, you have used the seed value as 1 to generate test data in a dataset. When you want to create another dataset with the same set of data instead of different data, then you can provide the seed value as 1 during the creation of the dataset.

- 12. Enable Fabricate headers by using the toggle icon if your schema contains the headers.
- 13. Click Create.

Result

The new dataset opens in a CSV Editor in a web browser. The dataset created is listed on the Datasets page.

Results

You have created the dataset by using the fabricate data in your project.

What to do next

You can perform the following tasks:

- Add, modify, or remove data in the dataset. See Editing a dataset on page 150.
- Publish the dataset to the Git repository so that other members of the project can use the dataset. See Publishing a dataset on page 160.

Editing a dataset

You can add, modify, remove, import, or export data from a dataset by using the CSV Editor. The working principle of the CSV Editor is similar to that of a spreadsheet.

Before you begin

You must have created a dataset or configured a repository that contains the dataset.

About this task

If you are a project **Owner** or **Tester** in HCL OneTest[™] Server 10.1.0 or later, you can perform basic tasks in the CSV Editor by right-clicking any row, column, or cell in the dataset to organize your data in a better way. For example, you can perform tasks such as updating data in a cell, inserting or deleting rows and columns, or renaming column names.

When you edit the dataset in the CSV Editor, you can use the following keyboard shortcuts to control the cursor selection in the CSV Editor:

- Tab To move the cursor control to the next available option.
- Shift-Tab To move the cursor control to the previous option.
- Shift+F10 To open the context menu from the dataset cell.

After you edit the dataset, you can save the changes made to the dataset, and then you can publish the dataset to the Git repository. If you save and close the edited dataset, the **Changes** page lists the edited dataset and later you can publish to the Git repository for other members to use.

When you or other members of the project edit the same dataset, you can view an icon with the initials of the member next to the name of the dataset on the **Datasets** and **Changes** pages. If you do not view the icon, you must refresh the **Datasets** page to view the icons. The **Changes** page denotes conflicting edits when another member publishes their edited dataset first.

Dataset name	Table matrix	Actions
> AdditionalLocations (AS) (JD) LogData/Logical/Locations/AdditionalLo	2 Col × 7 Row	× 🚽 E
> Locations LogData/Logical/Locations/Locations.sit	3 Col × 3 Row	- :

When a member with conflicting edits tries to publish the edited dataset, an error about conflicting changes is displayed. However, the member can use the **Save As** option to save and publish a copy of the dataset edits under a new asset name. The member must discard the edits that were made to the original dataset.

For example, consider a scenario when Amy Smith and John Doe edit the same dataset, and Amy Smith edits and publishes the dataset. On the **Changes** page, a message that indicates number of commits ahead and behind in the branch is displayed when John Doe tries to publish the same dataset.

Note: You cannot resize the width of rows in the CSV Editor. When you have a large amount of data in a cell, you can right-click the cell and select **Copy** (or Ctrl+C), and then paste it into a text-editing program to view the content. Alternatively, you can hover the mouse over the cell to view the content.

When you have a CSV file that has data separated from a character, then you can import that CSV file into the dataset. You can select any of the following separator characters from the **Configure Dataset** window, and the selection can be the separator character that you used in the CSV file:

- Comma
- Semicolon
- Space
- Tab
- Other

Consider that you have the data in the CSV file in the following format:

Name;CCNum
John;1234 5678 1234 5678
Bob;1122 3344 5566 7788
Amy;2233 4455 6677 8899

When you import the CSV file in the dataset, and then select the separator value as **Semicolon**, the data in the dataset is displayed as follows:

	Name	CCNum
1	John	1234 5678 1234 5678
2	Bob	1122 3344 5566 7788
3	Amy	2233 4455 6677 8899

If you want the data in its original format, that is, a semicolon (;) character to separate the data, then you can choose any other separator value from the **Configure Dataset** window.



Note: The default separator value is Comma.

1. Log in to HCL OneTest[™] Server if you are not already logged in.

- 2. Open a project from the team space.
- 3. Go to Author > Datasets, and then select the Branch from the list to find the dataset which you want to edit.

4. Click the **Edit** icon \checkmark from the **Actions** column of the dataset.

Based on the Branch that you selected, the following events occur:

- The Edit Branch window is displayed if you selected other than the edit branch.
- The dataset opens in the CSV Editor in a web browser if you selected the edit branch.
- 5. Perform one of the steps described in the following table to select or create the edit branch:

Step description	Step no
To select the edit branch	Perform 5.a on page 152
To create the edit branch	Perform 5.b on page 152

a. Perform the following steps to select the edit branch:

- i. Choose the edit branch from the **Select branch** drop-down list if the edit branches are already existing.
- ii. Click Ok.
- b. Perform the following steps to create the edit branch:
 - i. Select Create new branch.
 - ii. Provide a name for the edit branch.
 - iii. Click Save.
- 6. Perform the following actions to use the options available in the CSV Editor:

Options	Actions
Find	To find:
and Re-	a. Click the Find and Replace icon 🭳 .
place	b. Enter the content that you want to search in the Find field.
	c. Select any or all the following options to find the search content more effectively:
	 Select the Case sensitive checkbox to search the content that is the exact letter
	case of the content entered in the Find field.
	 Select the Match entire cell contents checkbox to search for cells that contain only
	the characters that you have entered in the Find field.
	 Select the Search using regular expression checkbox to search the pattern that
	matches strings.

Options	Actions
	For example, to search a cell that contains any number between 0 to 9, do the fol-
	lowing:
	i. Enter \ <i>d</i> in the Find filed.
	ii. Select the Search using regular expression checkbox.
	iii. Click Find.
	d. Click Find. If the text is found, the cell containing that text is selected.
	e. Click Find again to find further instances of the search text.
	To find and replace:
	a. Click the Find and Replace icon Q .
	b. Enter the content that you want to search in the Find field.
	c. Enter the content that you want to replace in the Replace field.
	d. Select any or all the following options to find and replace the content more effectively:
	 Select the Case sensitive checkbox to find the content that is the exact letter case
	of the content entered in the Find field.
	 Select the Match entire cell contents checkbox to find and replace for cells that
	contain only the characters that you have entered in the Find and Replace fields.
	 Select the Search using regular expression checkbox to find and replace the pat-
	tern that matches strings.
	e. Click Replace to replace the individual instances.
	f. Click Replace All to replace every instance of the content throughout the dataset.
Un-	a. Click the Undo icon ⁵ .
Cob	b. Select the recent changes from the list that you want to undo, and then click the list.
	The Undo option undoes anything you do in the dataset. The CSV Editor saves the unlimited un-
	do-able action. You can perform the undo action even after you save your changes made to the
	dataset.
Redo	a. Click the Redo icon C.
C	b. Select the recent changes from the list that you want to redo, and then click the list.
	The CSV Editor saves the unlimited redo action.
Import	You can import variable data into a dataset from the following sources:
-21	\circ When there are large amount of data stored in a CSV file.
	$_{\circ}$ When you create a schema to generate different types of data by using data fabrication.

Options	Actions
	a. Click the Import icon 🛃 .
	b. Select Import from CSV a file from the drop-down list.
	c. Click Select file and choose the CSV file that contains variable data to import into the dataset.
	d. Enable the First row contains headers by using the toggle icon if your CSV file contains the header.
	e. Select one of the following options to append or overwrite data in the dataset:
	 Enable Overwrite existing data by using the toggle icon to add the rows and columns from the beginning of the dataset.
	 Enable Append existing data by using the toggle icon to add rows and columns to the end of the dataset.
	f. Click Import.
	Importing data by using data fabrication
	a. Click the Import icon 🛃 .
	b. Select Fabricate data from the drop-down list.
	c. Select a schema for data fabrication from the drop-down list.
	Note: The list displays schemas that you have created only in your project.
	d. Enter the number of rows that you want to generate in the Number of Rows field.
	e. Enter a seed value in the Seed (optional) field.
	Whenever you generate test data to perform application testing, the generated data is dif- ferent. You can produce the same set of data multiple times by setting the seed value.
	For example, you have used the seed value as 1 to generate test data in a dataset. When you want to create another dataset with the same set of data instead of different data, then you can provide the seed value as 1 during the creation of the dataset.
	f. Enable Fabricate headers by using the toggle icon if your schema contains the headers.
	g. Select one of the following options to append or overwrite data in the dataset:

Options	Actions
	 Enable Overwrite existing data by using the toggle icon to add the rows and columns from the beginning of the dataset. Enable Append existing data by using the toggle icon to add rows and columns to the end of the dataset.
	h. Click Import .
Export	You can export variable data from the dataset into a CSV file to reuse in future tests when re- quired. You must have a dataset that you want to export.
	Click the Export icon to download the dataset as a CSV file.
Set as current	During the test run, if you want variable data to be selected from a current row instead of the first row in a dataset, right-click any cell in a row and select Set as current row .
row	Also, you can set the current row from the Datasets page by clicking Menu , and then the Configure option.
	When rows are deleted:
	If you delete any row between row 1 to current row, the current row data is taken from the next row. For example, when you set the current row as 6, and then you delete any row between row 1 to row 6, the current row remains at row 6, but the content of row 7 is moved to row 6.
	When rows are inserted:
	If you insert any new row between row 1 to the current row, the current row data is taken from the previous row. For example, when you set the current row as 6, and then you insert any row be- tween row 1 to row 6, the current row remains at row 6, but the content of row 5 is moved to row 6.
Dataset Config- uration	In the Configure Dataset window, you can change the row and column settings and configure the string values in the dataset that contains variable data for tests to use when they run.
¢	a. Click the Menu icon [•] , and then select the Configure option.
	b. Select any of the separator values that you used in the CSV file.
	The available options are Comma, Semicolon, Space, Tab , and Other . In the CSV file, if you have any other separator characters other than the available options, then you can select the Other option, and then can specify a value.
	For example, if the data in the CSV file is separated by a character #, then select the Other option and enter # in the field.

Options	Actions
	c. Configure the following options to change the row and column settings:
	Column header - Use an up-down control button to increment or decrement the val- ue of the column header.
	 Data start point - Use an up-down control button to increment or decrement the val- ue of the data starting pointer.
	 Current row - Use an up-down control button to increment or decrement the value of the current row.
	d. Configure the following options to change the string values in the dataset:
	 Treat as null - Enter a string value that is to be treated as null when running the test.
	 Treat as empty - Enter a string value that is to be treated as empty when running the test.
	For example, when you run the test and the data <i>123</i> in the dataset to be treated as empty, then you can specify <i>123</i> in the Treat as empty field.
	 Treat empty text as null - Select this field when you want the dataset that contains any blank cells, and the value of those blank cells to be interpreted as null.
	e. Click Update to apply the changes.
Discard	Click the Menu icon and select Discard to discard the changes made to the dataset.

- 7. Click the **Save** icon **to** save the changes made to the dataset.
- 8. Click the **Publish** icon to publish the dataset to the Git repository, and then close the CSV editor.

Results

You have edited the dataset.

Dataset encryption

Encrypted datasets are useful when you want to run tests that contain confidential information such as a set of passwords or account numbers.

When you run a test that uses an encrypted dataset, then you must provide an encryption key for decrypting the encrypted data in columns so that the data can be used in the test. If the test uses data from the multiple encrypted dataset columns, you must enter the same encryption key for every encrypted dataset column that the test uses.

When you run the test that uses the dataset with the encrypted column, the value of the column is decrypted at a run time. The data in the column is sent as a clear-text string in requests to the server. The actual values of the encrypted dataset variables are not displayed in the test log. The test log displays asterisks for the encrypted dataset variables.

You can use only one encryption key to encrypt data in the columns in any dataset.

Important:

The encryption keys that you use to encrypt data in a dataset are not stored on the server nor can be retrieved from the server. Therefore, you must remember to store the encryption keys in a secure location. You must use the same encryption keys to perform the following operations:

- · View the encrypted values
- Decrypt data
- · Enable the use of the encrypted dataset during test runs

Encrypting a dataset column

To secure test data, you must encrypt datasets. You can encrypt data in the columns of a dataset by using an encryption key. When you run a test that utilizes a dataset with encrypted variables, you must enter the encryption key for the encrypted column that the test uses.

Before you begin

You must have created a dataset. See Creating a dataset on page 144.

- 1. Log in to HCL OneTest[™] Server if you are not already logged in.
- 2. Open a project from the team space.
- 3. Go to Author > Datasets, and then select the Branch from the list to find the dataset that you want to encrypt.
- 4. Click the **Edit** icon \checkmark from the **Actions** column of the dataset.

Based on the Branch that you selected, the following events occur:

- The Edit Branch window is displayed if you selected other than the edit branch.
- The dataset opens in the CSV Editor in a web browser if you selected the edit branch.
- 5. Perform one of the steps described in the following table to select or create the edit branch:

Step description	Step no
To select the edit branch	Perform 5.a on page 158
To create the edit branch	Perform 5.b on page 158

- a. Perform the following steps to select the edit branch:
 - i. Choose the edit branch from the **Select branch** drop-down list if the edit branches are already existing.
 - ii. Click **Ok**.
- b. Perform the following steps to create the edit branch:
 - i. Select Create new branch.
 - ii. Provide a name for the edit branch.
 - iii. Click Save.
- 6. Right-click any cell in a column that you want to encrypt and select Encrypt column data.

Result

The Encrypt Column window is displayed.

7. Enter an encryption key in the Encryption Key field to encrypt the data in the column.

Â

Remember: When you have already encrypted other columns in the dataset, you must enter the same encryption key that you used previously. You can use only one encryption key to encrypt columns in a dataset.

Important:

The encryption keys that you use to encrypt data in a dataset are not stored on the server nor can be retrieved from the server. Therefore, you must remember to store the encryption keys in a secure location. You must use the same encryption keys to perform the following operations:

- View the encrypted values
- Decrypt data
- Enable the use of the encrypted dataset during test runs

8. Click Encrypt Column.

Result

Asterisks are displayed instead of actual data for the encrypted column.

Results

You have encrypted the dataset column in your project.

What to do next

You can publish the dataset to the Git repository so that other members of the project can use the dataset. See Publishing a dataset on page 160.

Decrypting a dataset column

To view the content of an encrypted dataset, you can decrypt the dataset column. Removing encryption from a dataset revokes the protection offered to the test data.

Before you begin

You must have created at least one dataset and encrypted the dataset with an encryption key. See Creating a dataset on page 144 and Encrypting a dataset column on page 157.

- 1. Log in to HCL OneTest[™] Server if you are not already logged in.
- 2. Open a project from the team space.
- 3. Go to Author > Datasets, and then select the Branch from the list to find the dataset that you want to decrypt.
- 4. Click the Edit icon 2 from the Actions column of the dataset.

Based on the Branch that you selected, the following events occur:

- The Edit Branch window is displayed if you selected other than the edit branch.
- The dataset opens in the CSV Editor in a web browser if you selected the edit branch.
- 5. Perform one of the steps described in the following table to select or create the edit branch:

Step description	Step no
To select the edit branch	Perform 5.a on page 159
To create the edit branch	Perform 5.b on page 159

- a. Perform the following steps to select the edit branch:
 - i. Choose the edit branch from the **Select branch** drop-down list if the edit branches are already existing.
 - ii. Click Ok.
- b. Perform the following steps to create the edit branch:

- i. Select Create new branch.
- ii. Provide a name for the edit branch.

iii. Click Save.

6. Right-click encrypted cells that display the contents with asterisks, and then select **Decrypt column data**.

Result

The Decrypt Column window is displayed.

7. Enter the encryption key that you used to encrypt the data in the column in the Encryption Key field.

8. Click Decrypt Column.

Result

Asterisks are replaced with the actual data in the decrypted column.

Results

The encryption is removed from the selected column in the dataset. When you run a test that uses a dataset that contains decrypted data, the variable data is substituted for the original data in the recorded test without prompting for the encryption.

What to do next

You can publish the dataset to the Git repository so that other members of the project can use the dataset. See Publishing a dataset on page 160.

Publishing a dataset

After you create or edit any datasets in HCL OneTest[™] Server, you can publish your changes to a remote Git repository. Therefore, after you publish the dataset, other members in the project can use your dataset in their test run, if required. The Edit branch automatically disappears from the **Branch** drop-down list and changes made to the datasets are merged into the previously selected branch name.

Before you begin

You must have created, edited, or deleted dataset assets in HCL OneTest[™] Server.

About this task

When you create or edit multiple datasets, the **Changes** page lists all datasets in the corresponding Edit branches. When you have many datasets listed on the **Changes** page, you cannot publish or discard a single dataset. You must either publish all datasets or discard all changes made to datasets. If you do not modify any datasets, the **Changes** page displays a message that indicates there are no changes in any of the datasets.

The **Changes** page also provides you with information about the number of commits that the Edit branch is ahead and behind. You can click the **(n) commits ahead** option, and then click **Reset** to revert your changes. Similarly, you can also click the **(n) commits behind** option, and then click **Merge** to merge the changes of other member into the Edit branch.

You can publish the dataset to the remote Git repository either from the **Changes** page or from the CSV Editor. When you modify the dataset and publish it to the Git repository, the other members who have access to that dataset can view the updated dataset.

You can click the **Menu** icon to perform the following actions from the **Changes** page:

Options	Actions
Edit	Click Edit to make any updates to the dataset before publishing.
Discard	Click Discard to remove the changes that you made to the dataset asset.
Save As	Click Save As to save a copy of the dataset.

- 1. Log in to HCL OneTest[™] Server if you are not already logged in.
- 2. Open a project from the team space.
- 3. Go to Author > Changes.
- 4. Click Publish changes.
- 5. Enter a description for the changes made to the dataset, and then click **Publish**.

Result

A notification is displayed for successful pushing of changes to the Git repository.

Results

You have published the modified dataset into the Git repository.

Viewing a dataset

When test assets includes datasets, you can view the contents of a dataset from HCL OneTest[™] Server. The datasets residing in the Git repository are listed in the **Datasets** page.

Before you begin

You must be a member of the project with the **Owner** or **Tester** role, and you must have completed the following tasks:

- Created a project in HCL OneTest[™] Server. See Adding a project on page 727.
- Added a Git repository to your project. See Adding repositories to a server project on page 728.
- Created at least one dataset and encrypted the dataset with an encryption key. See Creating a dataset on page 144 and Encrypting a dataset column on page 157.
- Created a classification for an encrypted dataset. See Creating a classification on page 754.
- 1. Log in to HCL OneTest[™] Server if you are not already logged in.
- 2. Open a project from the team space.
- 3. Go to Author > Datasets, and then select the Branch from the list.

4. Find the dataset that you are interested in, and then expand the dataset by clicking the **Expand** icon **>**.

Note: You can click the **Dataset name** field to sort the datasets by name in alphabetical order. Alternatively, you can use the **Search** field to search the dataset by name.

Results

You have viewed the contents of the dataset.

Viewing an encrypted dataset

You can use the **Dataset** page to view the contents of an encrypted dataset from HCL OneTest[™] Server.

- 1. Go to the **Datasets** page, find the encrypted dataset that you are interested in, and then expand the dataset by clicking the **Expand** icon >.
- 2. Perform the following steps, if you have created a classification but yet to add the encrypted dataset to it:
 - a. Find the encrypted dataset that you are interested in, and then click the **Lock** icon 📥 from the **Actions** column of the dataset.
 - b. In the **Change the classification for the dataset** window, select a classification from the list and enter the encryption key set for the dataset.
 - c. Click Save to save the classification details.
- 3. Right-click the encrypted column and click **Show encrypted data**.

You can right-click the decrypted column and select Hide encrypted data to encrypt the data again.

!

Important: The **Show encrypted data** option is available only when you have added the encrypted dataset to the respective classification.

Results

You have viewed the contents of an encrypted dataset.

Changing classification for an encrypted dataset

To move the encrypted dataset from one classification to another, you can change the classification for an encrypted dataset from the **Dataset** page.

Before you begin

You must have created at least two or more classifications. See Creating a classification on page 754.

- 1. Go to the **Datasets** page and find an encrypted dataset for which you want to change the classification.
- 2. Click the **Lock** icon 🛱 from the **Actions** column of a dataset.
- 3. In the Change the classification for the Dataset window:

- a. Choose the classification from the list.
- b. Enter the encryption key for the dataset that was set while encrypting the dataset column.
- c. Save the classification details.



Remember: You can perform this task only if you know the encryption key set for the dataset while encrypting the dataset column.

Results

You have changed the classification for an encrypted dataset.

Related information

Managing an encrypted dataset on page 754 Creating a classification on page 754

Deleting a dataset

You can delete the dataset when it is not required in your test environment.

Before you begin

You must have at least one dataset asset in your Git repository that you have configured.

About this task

You can delete datasets in HCL OneTest[™] Server in the following scenarios:

- Datasets that you created in the desktop clients and that are cloned to the repository in your project on HCL OneTest[™] Server.
- Datasets that you created in HCL OneTest[™] Server and that are published to the repository in your project.
- Datasets that are in the .csv file format.

You cannot delete the following datasets:

- Datasets that you created or edited in HCL OneTest[™] Server and that are not published to the repository in your project.
- Datasets that are in the .sit file format.
- 1. Log in to HCL OneTest[™] Server if you are not already logged in.
- 2. Open a project from the team space.
- 3. Go to Author > Datasets, and then select the Branch from the list to find the dataset that you want to delete.
- 4. Click the Menu icon from the Actions column of a dataset, and then click Delete.

Based on the **Branch** that you selected, the following events occur:

- The Edit Branch window is displayed if you selected other than the edit branch.
- The Delete dataset window is displayed if you selected the edit branch.
- 5. Perform one of the steps described in the following table to select or create the edit branch:

Step description	Step no
To select the edit branch	Perform 5.a on page 164
To create the edit branch	Perform 5.b on page 164

- a. Perform the following steps to select the edit branch:
 - i. Choose the edit branch from the **Select branch** drop-down list if the edit branches are already existing.
 - ii. Click Ok.
- b. Perform the following steps to create the edit branch:
 - i. Select Create new branch.
 - ii. Provide a name for the edit branch.
 - iii. Click Save.
- 6. Perform any of the following actions to decide from where the dataset is to be deleted:

Choose from:

- Select the Publish deletion from <branch name of the Git repository> to <branch name of the Git repository> checkbox to delete the dataset from the remote Git repository.
- Clear the Publish deletion from <branch name of the Git repository> to <branch name of the Git repository> checkbox to delete the dataset from the project.
 - Note: When you clear the Publish deletion from *<branch name of the Git repository>* to *<branch name of the Git repository>* option, the deletion of the dataset does not reflect in the remote Git repository. Therefore, the other members of the project can still use the dataset that you have deleted. If you want, later you can publish the dataset to the Git repository from the Changes page.
- 7. Perform the following actions to delete the dataset:

Option	When	Action
Publish deletion from <branch git<="" name="" of="" th="" the=""><th>Select- ed ⊠</th><th>a. Enter a description for deleting the dataset in the Descrip- tion of change field.</th></branch>	Select- ed ⊠	a. Enter a description for deleting the dataset in the Descrip- tion of change field.
repository> to <branch name<br="">of the Git repository></branch>		b. Click Delete and Publish .
	Cleared □	Click Delete .

Results

You have deleted the dataset.

Generation of test data

To test an application, you use data that is passed to get real-time results. Since creating test data manually is timeconsuming, you can use HCL® OneTest[™] Data, an automated tool to generate random test data. You can generate the test data in various file formats.

Test data is a core element in the process of testing any application. A sufficient amount of data is necessary to test all the possible scenarios of any application. HCL® OneTest[™] Data requires a schema to generate the test data.

When you want to generate the test data, then you must fabricate a schema or generate a schema by using any external resource. After you fabricated a schema, you must define types of the schema and set properties for each type. You can then generate the test data for one or multiple schemas at a time. You must generate multiple schemas in HCL® OneTest[™] Data by using the schemas created in the JDBC supported databases.

Schema fabrication

A schema is a graphical structure to represent different types of data. You can fabricate a schema for the generation of test data.

HCL® OneTest[™] Data supports the following ways to fabricate the schema:

- Import a schema from local file system into HCL® OneTest[™] Data.
- Generate a schema in external resource by using HCL® OneTest[™] Data.
- Create a schema by using HCL® OneTest[™] Data.

You can fabricate a schema by using various methods. You can also manage the schema for your project to generate the test data.

Schema import

HCL® OneTest[™] Data requires a schema to generate the test data. If you have a schema in your local file system, then you can import the same schema into your project.

HCL OneTest Data supports the import of the schema, which is either in JavaScript Object Notation (JSON) or XML Schema Definition (XSD) file format.

After you import the schema, you can perform all the following tasks to the imported schema:

- Defining types
- Setting type properties
- Setting restrictions
- Applying functions

N Restriction: You cannot modify the properties of the types in an XSD or a JSON schema.

Importing XSD or JSON files from the local file system

When you have an XSD or a JSON format file in your local file system, you can import the same files from the local file system into your HCL® OneTest[™] Data project.

Before you begin

- You must have created a project.
- You must have an XSD or a JSON format file in your local file system.

About this task

XSD or JSON files are in schema format. To create a schema, you can import an existing schema that is in the XSD or JSON format from your local file system.

Restriction: You cannot modify all the properties of the types in an XSD or a JSON schema.

The following table shows the list of properties supported by JSON or XSD schema:

Properties	Read-only JSON schema	Editable JSON schema	XSD schema
JavaScript rules	Yes	Yes	No
Regular expression	Yes	Yes	No
Restrictions	No	Yes	No
Default values	No	Yes	No



If a schema that you import resembles the JSON structure, then that schema is represented as a *read-only* JSON schema. However, when a schema that you import resembles the JSON data, then that schema is represented as an *editable* JSON schema.

- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.

Result

The Overview page is displayed.

- 3. Click Author > Data Fabrication.
- Result

The Data Fabrication page is displayed.

- 4. Click the Schemas tab.
- 5. Click XSD/JSON from the Schemas menu.

Result

The Import XSD/JSON dialog is displayed.

- 6. Select the JSON or XSD file that you want to import.
- 7. Provide a schema name with a brief description and keywords as Tags.
- 8. Click **OK** and save the changes.

Results

You have successfully imported XSD or JSON files from the local file system.

What to do next

You must define the types in the schema. See Defining Types on page 174.

You can also perform the following actions:

- View the imported file listed under the Schemas tab.
- Use the Search field to search for any schema from the existing schemas.
- Sort the list of schemas by name, folder, and recently used schemas.

Related information

JSON Schemas

Schema generation

When you want to generate the test data in any external resource, you must generate the schema by using that specific resource.

To generate the schema, you must establish a connection between HCL® OneTest[™] Data and the external resource.

HCL® OneTest[™] Data supports the establishment of connections with the following external resources:

- Java Database Connectivity (JDBC)
- Systems, Applications, and Products in Data Processing (SAP)
- MongoDB
- Excel

Note: After you generate schema by using any external resource, you can perform all the following tasks to the generated schema in HCL® OneTest[™] Data:

- Defining types
- Setting type properties
- Setting restrictions
- Applying functions

Tasks	More information
Generate test data in JDBC-supported databases	HCL OneTest Data support to write the generated test data in JDBC-supported databases on page 194
Generate test data for SAP IDOC or DXOB	HCL OneTest Data support to generate test data for an SAP IDoc or DXOB file on page 201
Generate test data for SAP BAPI	HCL OneTest Data support to generate test data for SAP BAPI on page 205
Generate test data in MongoDB	HCL OneTest Data support to write the generated test data in MongoDB on page 208
Generate test data for an Excel file	HCL OneTest Data support to generate test data for an Excel file on page 213

The following topics show how HCL® OneTest[™] Data connects with an external resource and generates the test data.

Schema creation

When you do not have an existing schema or you do not want to generate a schema in any database, then you can create a schema by using HCL® OneTest[™] Data.

To create a schema, you need to design a schema by defining the types, setting the properties for each type of schema, and designing a structural view of schema. You can also set restrictions or apply functions to the defined types.

Composing a schema

To generate the test data, you require a schema. You can compose a new schema if you do not have an existing schema or you do not want to generate the schema by using any external resource.

Before you begin

You must have a project.

- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.

Result

The **Overview** page is displayed.

3. Click Author > Data Fabrication.

Result

The Data Fabrication page is displayed.

4. Click New from the Schemas. Otherwise, select Create a schema from Quick Links.

Result

The New Schema dialog is displayed.

- 5. Provide a schema name.
- 6. Select the default project folder or enter any project folder name.
- 7. Enter keywords as tags which can help for quick search.
- 8. Provide a brief description of the schema and click **OK**.

Result

The schema opens in the schema designer as Root as the data dictionary. You can view the schema name as a tab in the workspace.

Results

The schema is displayed in the schema designer.

What to do next

You must define the types in your schema. For information about defining types, see Defining types on page 174.

Importing data from local file system

If you have data or a sample file, you can import it into your project and can use that data to design a schema.

Before you begin

- You must have created a project.
- You must have a data file in your local file system in CSV or Excel files.

About this task

The **Files** tab on the **Data Fabrication** page is one of the design components of a project. By clicking this tab, you can create a file. This tab helps you to import an existing file from the local file system, for which you want to generate test data.

- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.

Result

The **Overview** page is displayed.

3. Click Author > Data Fabrication.

Result

The Data Fabrication page is displayed.

- 4. Click the Files tab.
- 5. Click New from the Files to create a file.

Result

The New File dialog is displayed.

- 6. Select a file that you want to import from your local file system.
- 7. Provide a name to a file, folder details, keyword as Tag for quick search, and a brief description of the file.
- 8. Click **OK** to import and create a file.

Results

You achieved the following results:

- View the list of all the files imported for this project in the Files tab.
- Use the **Search** field to search any file from the existing files.
- · Sort the list of files by name, folder, and recently used files.

What to do next

After you have created a file into your project, you can import a file into schema designer to create a schema.

Related information

Integrating sample files into a schema on page 182

Importing files into schema designer

To create a schema by using the data you imported, you must import the data file into schema designer.

Before you begin

You must have imported a data file into your project from the local file system.

About this task

When you want to create a schema, you require data. You can use the data which you have imported from your local file system.

1. Click Import from the Schemas.

Result

The Import dialog box is displayed.

- 2. Select the file type as CSV.
- 3. Select the file that you want to import from the Sample File Path and define the import properties of the data.
- 4. Provide a schema name for this data and click Import.

Result

The schema appears in the schema designer.

5. Save the changes.

Results

You can view the imported file listed under the Schemas tab.

What to do next

You must define the types in the schema. For information about defining types, see Defining types on page 174.

Copying artifacts of a schema to another schema

When a schema in your project includes artifacts, and you want to reuse those artifacts in another schema in the same project, then you can copy the artifacts of a schema to another schema by using HCL® OneTest[™] Data.

Before you begin

You must have a schema in your HCL® OneTest[™] Data project.

About this task

While you copy the artifacts of the schema, you can either create a schema or select an existing schema.



Restriction: You cannot copy an XSD or a JSON schema to another schema.

- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.

Result

The **Overview** page is displayed.

3. Click Author > Data Fabrication.

Result

The Data Fabrication page is displayed.

- 4. Open your schema from the Schemas tab.
- 5. Select a category, group, or item type from **Dictionary**, and then click **Copy to Schema** from the menu. **Result**

The **Copy Type** dialog is displayed.

6. Toggle the **Create New Schema** switch to select the destination schema. You can either create a schema or select an existing schema.

Choose from:

- To copy the artifacts of a schema into a new schema, go to step 5.
- To copy the artifacts of a schema into an existing schema, go to step 6.
- 7. Copy the artifacts to a new schema by performing the following steps:
 - a. Toggle the Create New Schema switch to the on position to create a schema.
 - b. Enter a name for the new schema.
 - c. Toggle the Copy Child Types switch to the on position to copy all the child types of the selected type.
 - d. Toggle the **Copy Referenced Types** switch to the on position if you want to copy the types referenced as the components of the group.



Note: The referenced types are always copied to the same path as the source schema.

- 8. Copy the artifacts to an existing schema by performing the following steps:
 - a. Toggle the Create New Schema switch to the off position to select an existing schema.
 - b. Select a schema from the Schema drop-down list.
 - c. Toggle the **Retain Same Type Paths** switch to the on position if you want to copy the types to the same path in the destination schema.

Note: If you toggle the switch to the off position, then you must provide the type path in the **Type Path** field.

- d. Toggle the **Copy Child Types** switch to the on position to copy all the types and the child types of the selected type.
- e. Toggle the **Copy Referenced Types** switch to the on position if you want to copy the types referenced as components of the group.
- f. Toggle the **Overwrite Existing Types** switch to the on position to overwrite the type in the destination schema that already exists.

9. Click Copy.

10. Save the changes.

Results

You have successfully copied the artifacts of a schema into another schema.

Schema management

In a schema you can perform certain tasks such as editing and deleting of a schema. You can also split a schema view.

Editing a schema

At any point in time, you can edit the details of a schema of your project.

Before you begin

You must have completed the following tasks:

- Logged into HCL OneTest[™] Server.
- Created schemas in HCL® OneTest[™] Data. See Schema fabrication on page 165.
- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.

Result

The **Overview** page is displayed.

3. Click Author > Data Fabrication.

Result

The Data Fabrication page is displayed.

- 4. Click the Schemas tab to view the list of schemas.
- 5. Identify the schema that you want to edit.
- 6. Click the Menu icon and then click Edit.

Result

The Edit Schema dialog is displayed.

7. Edit the schema details and click OK.

Results

You have edited the selected schema.

Deleting a schema

If you do not need a schema anymore, you can remove that specific schema from your project.

Before you begin

You must have completed the following tasks:

- Logged into HCL OneTest[™] Server.
- Created schemas in HCL® OneTest[™] Data. See Schema fabrication on page 165.
- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.

Result

The **Overview** page is displayed.

3. Click Author > Data Fabrication.

Result

- The Data Fabrication page is displayed.
- 4. Click the Schemas tab to view the list of schemas.
- 5. Identify the schema that you want to delete.
- 6. Click the Menu icon , and then click **Delete**.
- 7. Click **Yes** to confirm and save the changes.

Results

You have deleted the selected schema.

Splitting a schema view

The schema designer displays a single schema. However, you can split the schema designer to view two schemas simultaneously. This is useful for copying, editing, or viewing different components of very large schemas.

Schema design overview

When you compose a schema by using HCL® OneTest[™] Data you must define the types of the schema. You can also modify the types of the schema when you import any schema from local file system or use the schema generated by using any external resource.

You can find information about the tasks that you must perform to design and create the structural view of the schema in your project.

Defining types

For optimum test data generation, you must define entire data of schema into types. Types are the components of schemas. After you design schema in the schema designer, you must define entire data as types by using type designer.

Adding types to a schema

The types in the schema are arranged in a hierarchy. A new schema by default has Root type. You can add subtypes to the Root type to define a schema.

Before you begin

You have a schema for your project.

About this task

Types are the set of data objects. A new schema has a single Root type. All types are added as subtypes of the Root type and then as subtypes of other types.

- 1. Select the type under which you want to add a subtype. For example, select "Root".
- 2. From the menu of the selected type, click Add.

Result

The subtype is created of the similar type as of the selected type and it appears under the selected type.

Note: You cannot add any type to a JSON or an XSD schema.

3. Save the changes.

Results

You can view the nested structure of types.

What to do next

You must define the properties of the types of the schema. For information about how to setup type properties, see related links at the end of this page.

Copying a type

To create more types with similar properties, you can copy an existing type.

About this task

In addition to using the drag-and-drop method, you can use the menu to copy a type.

- 1. Select the type that you want to copy and click Copy from the menu.
- 2. Select the target type-the type under which you want to copy the given type.
- 3. Click **Paste** from the menu of the target type.

Results

You can view a new type with the properties similar to an existing type.

What to do next

You can modify the name, description, and the properties of the copied type.

Deleting a type

When you want to remove any type from the schema, you can delete it.

- 1. Select the type that you want to delete and click **Delete** from the menu.
- 2. Click **Yes** to confirm and save the changes.

You can select more than one type simultaneously by using Multiselect option.



Note: You cannot delete any type of a JSON or an XSD schema.

Results

The selected type is deleted.

Related information

Objects, types, and classes on page 782

Setting type properties

After you add types to your schema, you must set type properties.

Before you begin

You must have a schema with types.

- 1. Select a type and click the menu of the type.
- 2. Click Properties.

Result

The Properties dialog is displayed.

- 3. Enter the name, class, and description details of the type.
- 4. Choose the class of the type as Category, Group, or Item.

Result

The properties of the selected type is displayed.

- 5. Define the required properties for the selected type.
- 6. Click Advanced properties to provide additional property details of the type.

You can set multiple properties for an item type.

Note: If you want to import any JSON or XSD format schema, you cannot modify the properties of any type of the schema.

7. Save your changes.

Results

You have set the type properties of schema and saved them successfully.

What to do next

When you finish setting the properties for all the types of your schema, you must prepare a structural view of the schema by using the drag-and-drop method. See Designing a structural view of the schema on page 188.



If you set multiple properties for an item type, then HCL® OneTest[™] Data considers the following order of priority while executing the properties:

- Data generation for multiple schemas based on schema integrity
- Pairwise data property
- Property to set Javascript rules



- Setting output rule in Rule Editor
- Property to set Implied Default value
- Regular expression property
- · Property to set weightage values by using a file
- Property to set restrictions

Read the following topics to understand how to set certain properties for any item type:

Related information

Type properties on page 782

Value assignation for item types

When you want to use specific item type values to generate the test data, then you can assign those values to the item types. To assign the values to any item type, you can either import the item type values or add the values manually.

Prerequisites

You must have completed the following tasks:

- Created a project in HCL OneTest[™] Server.
- Created a schema in HCL® OneTest[™] Data.

You can assign values to any item type by using any one of the following methods:

- Assigning values for item types from a file on page 177
- Inserting values for item types manually on page 178

Assigning values for item types from a file

When a file contains values for an item type on your computer, then you can assign those values to the item type to generate the test data.

Before you begin

You must have created a file with item type values on your computer.

- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.

Result

The **Overview** page is displayed.

3. Click Author > Data Fabrication.

Result

The Data Fabrication page is displayed.

- 4. Click Files and import the file of item type values from your computer into your project.
- 5. Open your schema from the Schemas tab.
- 6. Select the item type for which you want to assign the values.
- 7. Select Restrictions from the Item Properties drop-down list of the Properties dialog.
- 8. Enable the Values from file toggle button.
- 9. Provide the details of the file that you want to use to get the values of the item type in the **Values file** field. You can use any one of the following methods to provide the details of the file:

Choose from:

- Upload the file from your computer.
- Provide the name of the imported file with an extension.
- 10. Enter the column number of the file where the item type values are specified in the **Values column number** field.
- 11. Save the changes.

Results

You have successfully assigned the values for item types from a file.

What to do next

You must prepare the structural view of the schema. See Designing a structural view of the schema on page 188.

Inserting values for item types manually

When you want to assign specific values to an item type that does not exist in any file on your computer, then you can assign those values by inserting them manually.

- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.

Result

The Overview page is displayed.

3. Click Author > Data Fabrication.

Result

The Data Fabrication page is displayed.

- 4. Open your schema from the **Schemas** tab.
- 5. Select the item type for which you want to assign the values.
- 6. Assign a default value or multiple values.
- 7. Perform the following steps to assign a default value to the item type:
 - a. Select **Item Properties** from the **Properties** dialog.



- b. Click the Advanced Properties icon
- c. Enter a default value in the Implied Default field.

- 8. Perform the following steps if you want to assign multiple values to the item type:
 - a. Select Restrictions from the Item Properties drop-down list of the Properties dialog.
 - b. Click Include.
 - c. Enter the value for the selected item type in the first row.
 - d. Optional: Click Description to provide the details of the values of the item type.

e. Click Menu , and then click the Value include restrictions icon to add another row.
9. Save the changes.

Results

You have successfully inserted the values for item types manually.

What to do next


You must prepare the structural view of the schema. See Designing a structural view of the schema on page 188.

Setting weightage values

You can set weightage values for an item type to determine how often the value of that item type can be displayed in the generated test data.

Before you begin

- You must have a project and a schema.
- · You must have created a weightage file that can be of CSV or Microsoft Excel Open XML format.



About this task

The property of weightage values is set as a restriction on an item type. The probability to get higher accuracy increases in the results of the weightage values in the following scenarios:

- When HCL® OneTest[™] Data processes a large amount of data.
- When there is a large difference between the weightage values.

Computation of weightage value

The probability of occurrence of any item type value in the generated test data can be computed by using the following formula:

Probability of occurrence of any item type value = Weight of each item type value / Total weight of all the item type values

The following table shows an example when you have a weightage file with five item type values and its corresponding weightage values:

Item type values	Weightage values
Red	50000
Blue	5000
Green	500
Orange	50
Purple	5

The total weightage value of all the item type values = 50000 + 5000 + 500 + 50 + 5 = 55555.

The probability of occurrence of each item type value in the generated test data can be computed as shown in the following table:

Item type values	Probability of occurrence	Computed values
Red	50000/55555	0.9
Blue	5000/55555	0.09
Green	500/55555	0.009
Orange	50/55555	0.0009
Purple	5/55555	0.00009

From the computed values, Red has a higher probability value than other colors.

When you use this weightage file to set the weightage value for any specific item type and generate the test data, then you can find the generated test data with more occurrences of Red as compared to the other colors.

- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.

Result

The **Overview** page is displayed.

3. Click Author > Data Fabrication.

Result

The Data Fabrication page is displayed.

- 4. Click Files and import the weightage file from the local file system into your project.
- 5. Open your schema from the Schemas tab.
- 6. Select the item type on which you want to apply the weightage value.
- 7. Select Restrictions from the Item Properties drop-down list of the Properties dialog.
- 8. Enable the Values from file toggle button.

- 9. Provide the name of the weightage file in the Values file field.
- 10. Enter the column number in Values column number and Weights column number.
- 11. Click Save.
- 12. Select the group and generate the test data.

Results

You can view more occurrences of the values that are set with higher weightage values as a result of the test data generation.

What to do next

You must prepare the structural view of the schema. See Designing a structural view of the schema on page 188.

Related information Value assignation for item types on page 177

Setting regular expressions

When you want values of an item type to appear in a certain pattern in the generated test data, you must set the **Regular Expression** property for that item type in a defined schema.

Before you begin

- You must have logged in to HCL OneTest[™] Server.
- · You must have created a project and a schema.

About this task

The regular expression is a special text to describe a pattern. For example, you can specify regular expressions for email address, phone number, or website. HCL® OneTest[™] Data provides you some sample regular expressions.

To set regular expressions to any item type, you can either insert a value or select from the sample list of regular expressions that best suits your testing requirements. HCL® OneTest[™] Data then validates the value you inserted for the **Regular Expression** field and generates the values of the selected item type in a similar pattern.

- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.

Result

The **Overview** page is displayed.

3. Click Author > Data Fabrication.

Result

The Data Fabrication page is displayed.

- 4. Open your schema from the Schemas tab.
- 5. Select the item type for which you want to set regular expressions.

6. Click **Regular Expression** from the **Properties** dialog.

The sample list of regular expressions is displayed.

- 7. Set the regular expression in the **Regular Expressions** field by using any one of the following methods:
 - ∘ Type the regular expression. HCL® OneTest™ Data then validates the regular expression.

For example, [0-9]{18}

- **Tip:** If you want to reuse the validated regular expression then click **Add to sample list**, to add the expression in the list.
- Select the regular expression from the sample list. The selected regular expression is displayed in the **Regular Expressions** field.
- 8. Click Save.

Results

You have successfully set the regular expression for the selected item type.

What to do next

You must prepare the structural view of the schema. See Designing a structural view of the schema on page 188.

Related reference

Regular expressions on page 806

Integrating sample files into a schema

When you want to generate the test data, you must define a schema. HCL® OneTest[™] Data provides sample files with item type values so that you can integrate the sample file into a schema by mapping it to any item type.

Before you begin

- You must have logged in to HCL OneTest[™] Server.
- · You must have created a project and a schema.

About this task

The **Files** tab on the **Data Fabrication** page is one of the design components of a project. From the **Files** tab, you can integrate a file into a schema by using any one of the following options:

- Create a file by retrieving the data.
- Upload a file from the local file system.
- · Use any sample file.

Sample files contain the values for a specific item type. The sample files are in CSV and Excel file formats. You can map these sample files to an item type in a schema.



Note: You can map only one sample file to one item type in a schema.

You can use the **Search** field to search for any specific sample file from the **Sample Files** list. After you select a sample file, you can use the menu to manage the file for the following actions:

- Edit: You can modify the file name and the description of the selected sample file.
- Delete: You can delete the selected sample file from the list of files you can view in the File tab.
- Download: You can download the selected sample file into your local file system.



Note: If you want to modify the selected sample file, you must first download the file into your local file system, and then edit the file for changes.

1. Log in to HCL OneTest[™] Server and open the team space that contains your project.

- 2. Open your project.
- Result

The Overview page is displayed.

3. Click Author > Data Fabrication.

Result

The Data Fabrication page is displayed.

4. Click Use sample from the Files tab.

The Sample Files dialog is displayed.

- 5. Select one or more sample files that you want to import into your project, and then click Select.
- 6. Click the Files tab, and then download the selected sample file that you imported into your project.



Note: You can open the sample file and check the column number of the file that you want to map with the item type.

- 7. Open your schema from the Schemas tab.
- 8. Select Restrictions from the Item Properties drop-down list of the Properties dialog.
- 9. Enable the Values from file toggle button.
- 10. Provide the file name of the selected sample file with an extension in the Values file field.
- 11. Enter the column number of the sample file where the item type values are specified in the **Values column number** field.
- 12. Click Save.

Results

- You can view the list of all the sample files you have selected in the Files tab.
- You have successfully integrated the sample file into a defined schema.

What to do next

You must prepare the structural view of the schema. See Designing a structural view of the schema on page 188.

Adding JavaScript rules

When you have a JavaScript file with defined rules to create values for any item type, then you can add the JavaScript rules to create the values for the mapped item type.

Before you begin

- You must have created a project and a schema.
- You must have created a JavaScript file with defined rules in your local file system.

About this task

If you want to add the JavaScript rules to create the values for the mapped item type, then you must use the following command to define the rules in the JavaScript file:

function getData()

You can additionally set any one of the following properties for the mapped item type by using the JavaScript rules:

- Regular expression: The JavaScript rule uses the regular expression that you enter in the **Properties** dialog as an input for the regular expression rule.
- Seed value: The JavaScript rule uses the seed value that you enter in the **Generate Data** dialog as an input for the seed value rule.

To set either regular expression or seed value property, you must define the rules in the JavaScript file by using the following commands:

Property	Command	Parameter description
Regular expressions	function getData(param)	(param) : Represents the regular expres- sion pattern in the Regular Expression field.
Seed value	function getData (param)	(param): Represents the seed value in the Numeric Seed Value field of the Generate Data dialog.

Note: If you set the values for both regular expression and seed value properties in HCL® OneTest[™] Data and define the rule in the JavaScript file by using the command function getData(param), then only the value set for regular expression property is accepted while creating the item type values.

After you define rules in the JavaScript files, you can import the JavaScript file from your local file system into your project, and then map the file to any item type in a schema.

- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.

Result

The Overview page is displayed.

3. Click Author > Data Fabrication.

Result

The Data Fabrication page is displayed.

- 4. Click Files and import the JavaScript file from the local file system into your project.
- 5. Open your schema from the Schemas tab.
- 6. Select the item type for which you want to create the values by using the JavaScript file.
- 7. Select Item Properties from the drop-down list of the Properties dialog.
- 8. Select Text in the Item Subclass field.
- 9. Click the Advanced Properties icon 💷 .
- 10. Optional. Provide the pattern in the **Regular Expression** field, if you want to set the regular expression for the mapped item type.
- 11. Provide the name of the JavaScript file with an extension in the JavaScript Name field.

Important: You must enter the correct file name of the JavaScript file that you imported into your project. For example, address.js.

Results

You have successfully added the JavaScript rules for the item type.

What to do next

You must prepare the structural view of the schema. See Designing a structural view of the schema on page 188.

The pairwise data generation method

When you test any application, you might want to ensure that the test data that you use covers all possible combinations of item type values. To achieve this goal of maximum coverage of all possible scenarios, you must apply the pairwise data generation method on the required item types of a schema.

[!]

^{12.} Click Save.

For testing any application, you must attain the maximum test coverage. You can achieve the maximum test coverage and discover more defects with less effort and time by applying the pairwise data generation method. The pairwise data generation method in HCL® OneTest[™] Data helps to generate all the possible combinations of the item type values for each pair of item types. The use of this method decreases the number of the generated test data but covers all the possible combinations of the item type values.

For example, consider that there are three item types in a schema such as a list box with five values (zero, one, two, three, four), one radio button with two values (selected or unselected), and one check box with two values (selected or cleared). Therefore, the combination becomes 5x2x2 as the generated test data, which is equal to 20 values. These 20 values are required to cover all combinations of the item types of the schema without applying the pairwise data generation method. After you apply the pairwise data generation method, you can observe that the generated test data comprises all combinations of item type values for the three pairs of item types among the three item types. This pairing of item types results in 12 combinations of values of the generated test data.

For more information about how to set the pairwise data generation method in HCL® OneTest[™] Data, see Setting the pairwise data property on page 186.

Setting the pairwise data property

When you want to generate an optimum test data that covers all possible combinations of item type values for each pair of item types in a schema, you can set the pairwise data property for those item types.

Before you begin

You must have completed the following tasks:

- Created a schema in HCL® OneTest[™] Data.
- Read the details about how to assign the values to an item type. See Value assignation for item types on page 177.

About this task

The pairwise data generation method is a combinational method to find all the possible values of the selected pairs of item types. The pairwise data generation method is efficient when you have a large number of item types and the item type values in a schema. When you apply the pairwise data generation method in such cases, the number of generated test data decreases drastically although covering all the combinations. To implement the pairwise data generation method, you must have multiple item types in a group type of a schema. To assign item type values, you must either import the values of item type from a file or insert values for each item type.

- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.
- Result

The **Overview** page is displayed.

3. Click Author > Data Fabrication.

Result

The Data Fabrication page is displayed.

- 4. Open your schema from the Schemas tab.
- 5. Select the item type from **Dictionary** for which you want to set the pairwise data property.
- 6. Select Restrictions from the Item Properties drop-down list of the Properties dialog.
- 7. Set values for the selected item type by using any one of the following methods:

Choose from:

- Import item type values from the file by using Values from file.
- Include values for the selected item type in the Properties dialog.
- 8. Save the changes.
- 9. Select Item Properties from the drop-down list of the Properties dialog.
- 10. Click the Advanced Properties icon 💷.
- 11. Select Yes from the Pairwise Data drop-down list.



Note: The default value of the Pairwise Data drop-down list is No.

12. Save the changes.



Important: You must select multiple item types to apply the pairwise data generation method.



Note: When you want to apply the pairwise data generation method for each item type, you must repeat step 4 through step 10.

Results

You have successfully set the pairwise data property for the selected item type.

What to do next

You must select a group type to generate the test data of a schema. See Generating test data on page 217.

Note: The group type that you select to generate the test data can comprise both the item types set for the pairwise data property and the item types that are not set for this property.

Important: When you generate the test data for a group type with a few or all of the item types set for the pairwise data property, then during the test data generation, the value you enter for the Number of records field is ignored. Based on the pairwise data property, HCL® OneTest[™] Data auto calculates the number of records.

Related information

Value assignation for item types on page 177

Designing a structural view of a schema

To define how the item and group types are organized and are related to each other, you must design the structural view of a schema before generating the test data.

Before you begin

You must have a group type in your schema.

About this task

When you design the structural view of a massive schema, you can filter the item or group types of your schema by using **Filter**.

1. Double-click any group type from Dictionary.

Alternatively, you can click the menu of the selected group, and then select Structure.

Result

The Structure dialog appears.

2. Drag and drop the types from Dictionary to the Structure dialog to map Item and Group types.



Note: You can use the **Category** type to organize the data dictionary entities. You cannot map the **Category** type in the structure view.

3. Save the changes.

What to do next

You can set restrictions and apply functions to define the component rules to any item type. You can also generate the test data without applying restrictions and functions. See Generating test data on page 217.

Setting a range

After you define the structure of a schema, you can set a number range to specify the number of occurrences to generate an item type in the test data.

Before you begin

- · You must have a group type in your schema.
- · You must have a structural view of your schema.

About this task

You can set the number range only for item types and group types of your schema.

- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.

Result

The Overview page is displayed.

3. Click Author > Data Fabrication.

Result

The Data Fabrication page is displayed.

4. Select the generated schema from the **Schemas** tab.

For example, *schema_<number>*

5. Click the **Menu** icon • of the group type of the schema and select **Structure**.

The structural view of the schema is displayed.

6. Click the **Menu** icon item types in the **Structure** dialog to set the restriction for several occurrences of the item types in the generated test data.

You can set the following restriction rules:

- Set Optional
- Set Required
- Set Range
- Set Unlimited

In the following table, you can find the value of the minimum and maximum occurrences that you can set as restrictions for the item types:

Item properties	Minimum occurrences	Maximum occurrences
Optional	0	1 or more
Required	1	1
Unlimited	1	1 or more
Set Range	Any minimum value Note: Minimum value should be equal to or less	Any maximum value
	than the maximum value	

7. Save the changes.

You can modify the properties of the selected item type by using Properties in the context menu.

Results

You have set the number range for the selected item types.

What to do next

You can apply functions to define component rules to any item type. You can also generate test data without applying functions. See Generating test data on page 217.

Related information

Restrictions settings on page 843

Applying functions

You can apply functions on the item types of a schema to define the component rules.

Before you begin

You must have a defined schema in a schema designer. See Schema design overview on page 174.

About this task

You can also apply functions on the types of the imported JSON or XSD schemas.

- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.

Result

The **Overview** page is displayed.

3. Click Author > Data Fabrication.

Result

The **Data Fabrication** page is displayed.

- 4. Click Schemas, and then select the schema for which you want to generate the test data.
- 5. Select the group type, and then open the structural view of the schema.
- 6. Select the item type on which you want to apply the function, in the Structure dialog.
- 7. Click the menu on the right side of the Structure dialog.

Result

A blank field is displayed next to the item type.

8. Click the blank field.

Result

The Rule Editor pane is displayed on the page.

- 9. Enter the equal sign (=) in the **Rule Editor** pane.
- 10. Provide the function in the Rule Editor pane.

You can enter the function by performing any one of the following methods:

Choose from:

- Enter the function manually.
- Select from the list of functions by using the following steps:

- a. Click the Insert mapping functions icon 🍂
- b. Select the function that you want to apply as a component rule, and then click **Insert** from the menu of the selected function.

For example, if you want the generated value of an item type in uppercase, then you must enter or select the UPPERCASE() function.

=UPPERCASE(RANDDATA())

11. Optional: Enter a parameter for the selected function.

You can provide the parameter value either as a constant value or as a reference of the item type.

You must use the following syntax to provide the parameter in any function:

<item type name>:Out1

where:

- item type name Represents the name of the item type.
- :Out1 Represents a standard output argument.

For example, consider that you have a group type as Flowers with Colors and Pattern as two item types. If you want to generate the value of Colors item type in uppercase, then you can select the item type Pattern in the **Structure** dialog. You must open the **Rule Editor** pane, and then select the UPPERCASE() function with reference of Colors item type as the parameter.

= Uppercase (Colors:Out1)

12. Press the Enter key.

Result

The selected function is displayed in the item type field of the Structure dialog.

13. Save the changes.

Results

You have successfully applied the function on an item type of the schema.

What to do next

You can generate the test data for the designed schema. See Generating test data on page 217.

Related information

Functions and expressions on page 882

Designing a structural view of a schema on page 188

Setting a function to concatenate the values of item types on page 192

Setting a function to concatenate the values of item types

You can set a function to concatenate the values of multiple item types so that the values are displayed as the value of another item type.

Before you begin

You must have completed the following tasks:

- Defined a schema. See Schema design overview on page 174.
- Created the structural view of the schema. Designing a structural view of a schema on page 188.
- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.
 - Result

The Overview page is displayed.

3. Click Author > Data Fabrication.

Result

- The Data Fabrication page is displayed.
- 4. Click Schemas, and then select the schema for which you want to generate the test data.
- 5. Open the structural view of the schema.

!

Important: You must have all the item types in the same group type for the values that you want to concatenate.

Result

The Structure dialog is displayed.

6. Select the item type for which you want the values of the generated test data in the concatenated format.

Note: You must not place the item type, for which you want the values in the concatenated format, in the same group type.

For example, consider that a schema includes a group type, group_name1 and three item types such as item type1, item type2, and item type3. If you want to concatenate the values of item type1 and item type2 as the generated value of item type3, then you must add item type1 and item type2 item types in the group_name1 group type. You must ensure that item type3 does not exist in the group_name1 group type.

7. Click the menu on the right side of the Structure dialog.

Result

A blank field is displayed next to all the item types.

8. Click the blank field of the item type for which you want to set the function for concatenation.

Result

The Rule Editor pane is displayed on the page.

9. Enter the equal sign (=) in the Rule Editor menu.

10. Select the seriestotext() function from the Insert mapping functions 🍂 icon.



Note: You can also provide the following rule manually in the **Rule Editor** pane: "item type1" + "item type2".

11. Provide the name of the group type as the parameter for this function.

For example, if you have a group_name1 group type, then you must provide the following function:

SERIESTOTEXT(group_name1:OUT1)

12. Press Enter.

Result

The selected function is displayed in the item type field of the Structure dialog.

13. Save the changes.

Results

You have successfully set the function to concatenate the values of multiple item types.

What to do next

You can generate the test data for the designed schema. See Generating test data on page 217.

Related information

Functions and expressions on page 882

Test data generation from structured schemas

When you want to test your application by using randomly generated test data, then you must generate the test data from the structured schemas.

You can generate the test data for schemas that you import, create, or generate in HCL® OneTest[™] Data by using any external resource. You can generate the test data simultaneously for multiple schemas that are related to each other through common item types. The item types of the child schema refer to the item types of the parent schema. After you view the relationship among the selected schemas, you can generate the test data. When you generate the test data by using the related schemas, the generated values of referring item types of the child schema are available in the generated values of the referred item types of the parent schema, based on referential integrity.

You can also establish or delete parent and child relationships among multiple non-JDBC schemas, based on referential integrity.





- When you generate the test data by using multiple schemas, you must select either JDBC-supported or non-JDBC schemas.
- If you generate the test data for JDBC-supported schemas, then all the selected schemas must be generated from the same JDBC connection.

When you generate the test data for JDBC-supported schemas, then you can either download the generated test data or can insert it into the connected database. You can insert the test data into the following databases if there is a successful connection between HCL® OneTest[™] Data and the database:

- JDBC-supported databases
- MongoDB

HCL OneTest Data support to write the generated test data in JDBC-supported databases

When you want the generated test data in any Java Database Connectivity (JDBC) supported database, you can generate the test data by using HCL® OneTest[™] Data. Subsequently, HCL OneTest Data inserts the generated test data directly in the configured JDBC-supported database.

To enable HCL® OneTest[™] Data to write the generated test data in the database, you must create a sample schema with tables in the installed JDBC-supported database, establish a connection with the installed database, select the generated schema in HCL® OneTest[™] Data, and then generate the test data of the selected schema.

HCL® OneTest[™] Data supports the following JDBC-supported databases:

- IBM DB2
- MySQL Server
- Microsoft SQL Server
- Oracle database

HCL® OneTest[™] Data supports the test data generation for the following data types:

- INTEGER
- VARCHAR
- CHAR
- DATETIME
- DATE
- TIME
- BOOLEAN

🖍 No

Note: You must add the restriction values for BOOLEAN data type as ${\scriptstyle 0}$ and ${\scriptstyle 1.}$

Prerequisites

The following prerequisites must be met to enable HCL OneTest Data to write the generated test data:

- You must have access to HCL OneTest[™] Server.
- You must have installed a JDBC-supported database.

Task flow

You must perform the following tasks in sequence to enable HCL OneTest Data to write the generated test data directly in the JDBC-supported database. The table also provides you the links to the information about the tasks.

Task	More Information
Create a sample schema in a database	Creating a sample schema in a database on page 195
Establish a JDBC connection with HCL OneTest Data	Establishing a JDBC connection with HCL OneTest Data on page 197
Generate a schema in HCL OneTest Data	Generating a schema in HCL OneTest Data on page 199
Insert the generated test data in the database	Inserting the generated test data in a database on page 200

Creating a sample schema in a database

To generate a schema in HCL® OneTest[™] Data, you must create a schema with a table in the database.

About this task

After you download the connector jar files of the JDBC-supported database, you must copy the jar files from your computer to the pods such as *HIP REST* and *HIP Server*. These pods are responsible for the following actions:

- *HIP Server* is responsible to establish a connection with the JDBC-supported database. This pod also generates a schema by using the tables of the database. The structure of a schema is a flat hierarchy, where all the item types are in a single group called a *Row*. The item types in a schema refer to the columns of the table.
- *HIP REST* is responsible to run the map and generate the data. This pod also writes the generated data to the JDBC-supported database.

Both the pods use the connector jar file to communicate with the JDBC-supported database.

You can download the connector jar files from the following locations:

Connector jar	Location
Mysql Server connector jar	https://dev.mysql.com/downloads/connector/j/
Microsoft SQL Server connector jar	https://docs.microsoft.com/en-us/sql/connect/jd- bc/download-microsoft-jdbc-driver-for-sql-serv- er?view=sql-server-ver15
IBM DB2	https://www.ibm.com/support/pages/db2-jdbc-dri- ver-versions-and-downloads

1. Download the JDBC-supported database connector jar file to your local file system.



Note: You must download the connector jar file that is compatible with the database server.

2. Copy the connector jar file from your local file system to the pods by using the following commands from the command prompt.

For example, run the following commands if you are using the MySQL database:

For HIP REST

```
kubectl cp /<source path>/mysql-connector-java-8.0.19.jar {my-ots}-<hip rest podname>:/opt/runtime/
extjar/mysql-connector-java-8.0.19.jar -n test-system
```

For HIP Server

```
kubectl cp /<source path>/mysql-connector-java-8.0.19.jar {my-ots}-<hip server podname>:/opt/hcl/hip/
extjar/mysql-connector-java-8.0.19.jar -n test-system
```

Notes:

- Depending on the database you use, you must copy different connector jar files to the pods.
- While copying the jar files to the pods, you must ensure that the names of pods are same as those installed on HCL OneTest[™] Server.

For example:

- HIP Rest is displayed as {my-ots}-hip-rest-6757c99d9-4qjtl
- HIP Server is displayed as {my-ots}-hip-server-0
- ∘ When you install or restore HCL® OneTest[™] Data, you must copy the connector jars files again.
- 3. Create a schema with a table in the database by using the following commands from the command prompt.

For example, you can use the following command to create a table in a schema:

```
create schema <schema_name>;
use <schema_name>;
    CREATE TABLE IF NOT EXISTS <table_name> (
    Column1 <DataType> Constraint,
```

```
Column2 <DataType> Constraint,
Column2 <DataType> Constraint,,,,,
);
```

Remember: In HCL® OneTest[™] Data, you must refer to the schema name and the table name that you created by using this command.

Results

You have created a sample schema with a table in the database.

What to do next

After you create a schema in the database, you must establish the connection between HCL® OneTest[™] Data and the JDBC-supported database. See Establishing a JDBC connection with HCL OneTest Data on page 197.

You can view the schema name that you created in the database as the value of the **Catalog** or **Schema** property in HCL® OneTest[™] Data.

Establishing a JDBC connection with HCL OneTest Data

You must establish a connection between HCL® OneTest[™] Data and the JDBC supported database to generate the schema and to write the generated test data in the database.

Before you begin

You must have created a sample schema in the database. See Creating a sample schema in a database on page 195.

- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.

Result

The **Overview** page is displayed.

3. Click Author > Data Fabrication.

Result

The Data Fabrication page is displayed.

- 4. Click **New** from the **Connections** tab to create a new connection.
- 5. Select JDBC as a connection type and click Next.
- 6. Enter the following properties of the connection in the **Properties** dialog.
 - a. Enter the URL of the database.

You must provide the URL in the following format:

jdbc:<DatabaseType>://<HostName/IPAddress>:<PortNumber>/<CustomSettings>

For example, the URL for a MySQL database server can be jdbc:mysql://10.0.2.15:8081 or for a Microsoft SQL database Server can be jdbc:sqlserver://10.134.59.16:1433.



 When you want to establish a connection with IBM DB2, you must provide the database name as the <CustomSettings>.

For example, the URL for IBM DB2 can be jdbc:db2://10.134.59.16:50000/ testdb.

 When you want to establish a connection with an Oracle database, you must enter details in the following format:

jdbc:<DatabaseType>:<client_Type>//<HostName/ IPAddress>:<PortNumber>:<ServiceID/Service_Name>

For example, jdbc:oracle:thin:@10.543.89.22:1521:ORCLCDB.

You can get the details of the service ID or service name from the properties of the Oracle database that you set up.

- b. Enter the name and password to access the database.
- 7. Click Test to verify whether the connection is established successfully.

Note: If the connection fails to establish, it can be because of any of the following reasons:

- Mismatch in the version of the drivers.
- Unreachable database.
- Missing database.
- Unsuccessful copying of the connector jar file.

You can run the following command to check the logs of *HIP Server* to get more information about the reason of failure:

kubectl logs {my-ots}-hip-server-0 -n test-system

Results

You have successfully established the connection between HCL® OneTest[™] Data and the database.

What to do next

You must provide a name for the connection, and then generate a schema. See Generating a schema in HCL OneTest Data on page 199.

Generating a schema in HCL OneTest Data

After you establish the connection between HCL® OneTest[™] Data and the JDBC-supported database, you can generate a schema in HCL® OneTest[™] Data from the configured database.

- 1. Click the **Connections** tab and select the connection that you created.
- 2. Click the context menu and select New Action.
- 3. Select Target as the Action Type in the New Action dialog and click Next.
- 4. Enter the following properties of the schema that you want to generate, and then click Next.

Properties	Actions	Required/Optional
Target	Select the target as <i>Table</i> that you created in the database from the list.	Required
Catalog	Select the schema that you created in the data- base from the list.	Required
Schema	Select the schema that you created in the data- base from the list. The name of schema is displayed either in the Catalog or in the Schema field for the selected database.	Optional
Table	Select the table that you created in the data- base from the list.	Required



Note: You can click the Advanced Properties icon 🗉 to set the additional properties of the schema.

5. Click Generate.

The schema is generated in HCL® OneTest[™] Data by using the schema you created in the database. HCL® OneTest[™] Data generates the schema name as *schema_<number>*.



Note: You must select this schema name as the schema for HCL® OneTest[™] Data to generate the test data.

- 6. Select the schema type as Row and click Next.
- 7. Provide the identification details of the new action, and then click OK.

The new action is created and is listed under the JDBC connection.

Results

You have successfully generated the schema in HCL® OneTest[™] Data.

Important: If you want to generate schemas for other tables in the same database, then instead of creating a new connection, you must click **New Action** on the existing JDBC connection.

What to do next

You can provide the action name under the **Identification** dialog, and then generate the test data in the database. See Inserting the generated test data in the database on page 200.

Inserting the generated test data in a database

After you generate the schema from the configured database in HCL® OneTest[™] Data, you can directly insert the generated test data into the database.

Before you begin

You must have generated the schema by using the database. See Generating a schema in the database on page 199.

1. Select the schema that you generated with the following name from the Schema tab:

schema_<number>

2. Click the menu of the group type of the schema and select Structure.

You can view the list of all item types associated with the selected group type in the structure view.

3. Click the menu for all the item types to set the property as Set Required, and then click Save.



Note: If you have a numeric item type, you must set Min size (digits) and Max size (digits) properties.

For example, when you select Integer as **Presentation** then you can set the **Min size (digits)** as 1 and the **Max** size (digits) as 9.

4. Select the group type in the Dictionary dialog and click Generate Data from the menu.

The Generate Data dialog is displayed.

5. Select the Connection option and provide values for the Number of records and Numeric Seed Value.

The seed value acts as an instance of random data that can produce the same set of data multiple times. By default, the seed value is blank.



Note: The following table lists the maximum values for numeric seed value and number of records:

Description	Maximum values
Numeric Seed Value	8 digits (99,999,999)
Number of records	9 digits (999,999,999)

6. Select the connection type from the list, and then click **OK**.

Results

You have successfully inserted the generated test data from HCL® OneTest[™] Data in the JDBC supported database.

What to do next

You can click the Jobs tab to view the status of the job. The tooltip of the job displays the following details:

- URL of the connection.
- Name of the table.
- · Schema name from which the test data is generated.

Important:

You cannot download the generated test data from the **Jobs** page because the test data is written to the configured database and is not available in HCL® OneTest[™] Data.

You can log in to the configured database to view the generated test data.

HCL OneTest Data support to generate test data for an SAP IDoc or DXOB file

When you want to generate the test data for an SAP Intermediate Document (IDoc) or Data Transfer Object (DXOB) file, you can generate a schema in HCL® OneTest[™] Data by using the structured schema of the SAP IDoc or DXOB file. You can then generate the test data by using the generated schema in HCL® OneTest[™] Data.

The SAP applications provide file-based interfaces, such as the SAP IDoc and DXOB interfaces. The SAP IDoc interface supports Application Link Enabling (ALE) and Electronic Data Interchange (EDI) file formats, and the SAP DXOB interface supports the DXOB files.

You must perform the following tasks to generate the test data for any SAP IDoc or DXOB file:

- Schema generation for an SAP IDoc or DXOB file on page 202
- Generating test data on page 217

Related information SAP applications on page 774

Schema generation for an SAP IDoc or DXOB file

When you want to generate the test data for an SAP IDoc or DXOB file, then you must generate a schema for the selected SAP IDoc or DXOB file.

The SAP IDoc or DXOB file is a standard data structure in SAP applications to transfer data between SAP system applications and external resources. Every SAP IDoc or DXOB file has a unique number.

If you have an SAP IDoc or DXOB file that you want to use for test data generation in your local file system, then you must import the file into your HCL® OneTest[™] Data project. After importing the file, you must establish a connection between the SAP IDoc or DXOB interface and HCL® OneTest[™] Data. The established connection helps to transfer and interpret the data of the imported SAP IDoc or DXOB file. The interpreted information then helps HCL® OneTest[™] Data to generate a schema.

You must perform the following tasks to generate a schema in HCL® OneTest[™] Data for the SAP IDoc or DXOB file:

Importing an SAP IDoc or DXOB file

When you want to establish a connection with an SAP IDoc or DXOB interface, you must import the SAP IDoc or DXOB file into your HCL® OneTest[™] Data project from your local file system.

Before you begin

You must have completed the following tasks:

- Created a project.
- Created the SAP IDoc or DXOB file in your local file system.
- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.

Result

The Overview page is displayed.

3. Click Author > Data Fabrication.

Result

The Data Fabrication page is displayed.

4. Click Files, and then click New to import the SAP IDoc or DXOB file from the local file system into your project.

Results

You have successfully imported the SAP IDoc or DXOB file from the local file system into your project.

What to do next

You must establish a connection between the SAP IDoc or DXOB interface and HCL® OneTest[™] Data. See Establishing an SAP IDoc or DXOB interface connection with HCL OneTest Data on page 203.

Establishing an SAP IDoc or DXOB interface connection with HCL OneTest Data

When you want to generate a schema for an SAP IDoc or DXOB file, you must establish a connection with the SAP IDoc or DXOB interface.

Before you begin

You must have imported the SAP IDoc or DXOB file into your project.

- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.
 - Result
 The Overview page is displayed.
- 3. Click Author > Data Fabrication.
 - Result

The Data Fabrication page is displayed.

- 4. Click Connections.
- 5. Click **New** to create a new connection type.

The New Connection dialog box is displayed.

- 6. Select SAP IDoc from the Type drop-down list, and then click Next.
- 7. Set the following properties under Connection Properties:
 - Enable Bypass Client Connection.
 - Select 2 (Unicode) as Bytes Per Character.
- 8. Click Next, and then provide a name to the established connection.
- 9. Click **OK**.

You can see the name of the SAP IDoc connection under the Connections tab.

Results

You have successfully established the connection between HCL® OneTest[™] Data and the SAP IDoc or DXOB interface.

What to do next

You must generate a schema in HCL® OneTest[™] Data by using the SAP IDoc or DXOB file. See Generating schema by using an SAP IDoc or DXOB file. on page 203

Generating schema by using an SAP IDoc or DXOB file

When you want to generate the test data for an SAP IDoc or DXOB file, then you must generate a schema for the selected SAP IDoc or DXOB file.

Before you begin

You must have established the connection with the SAP IDoc or DXOB interface.

- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.

Result

The **Overview** page is displayed.

3. Click Author > Data Fabrication.

Result

The Data Fabrication page is displayed.

- 4. Click Connections.
- 5. Select the SAP IDoc connection name that you established, and then click New Action from the menu.

The New Action dialog is displayed.

- 6. Select Target as the action type, and then click Next.
- 7. Enter the following properties for the new action:
 - a. Select one of the following file types from the Data record type drop-down list.
 - ALE 1000 byte segments (ALE/RFC port)
 - · EDI Segments terminated by line feed (file port)
 - DXOB Data Transfer Object
 - b. Select the imported SAP IDoc or SAP DXOB file name from the IDoc or DXOB File drop-down list.
 - c. Select Native from the Character set drop-down list.
- 8. Click Next.
- 9. Click Generate to generate a new schema by using the imported SAP IDoc or SAP DXOB file.

A schema is generated as anonymous_schema_<number>.

10. Select Schema type.

- 11. Click Next.
- 12. Provide the name to the new action, and then click OK.

The new action is created and listed under the SAP IDoc or DXOB connection name that you established.



Note: You can create multiple actions for each established connection.

13. Click Save.

Results

You have successfully generated a schema for the SAP IDoc or DXOB file in HCL® OneTest[™] Data.

Note: You can modify the schema name anonymous_schema_<number> from the Schemas tab.

What to do next

You can generate the test data by using the generated schema. See Generating test data on page 217.

HCL OneTest Data support to generate test data for SAP BAPI

When you want to generate test data for SAP Business Application Programming Interface (BAPI), you can generate a schema in HCL® OneTest[™] Data based on structured schema of SAP BAPI function modules. You can then generate the test data by using the generated schema in HCL® OneTest[™] Data.

SAP BAPIs are API methods of SAP Business Object Types. HCL® OneTest[™] Data uses SAP BAPI to access the application layer of the SAP System.

Prerequisites

You must have access to HCL OneTest[™] Server.

Task flow

You must perform the following tasks in sequence to generate the test data for SAP BAPI in HCL® OneTest™ Data.

The table also provides you the links to the information about the tasks:

Task	More Information
Install SAP connector files in HCL® OneTest [™] Data	Installing the SAP connector files in HCL OneTest Data on page 205
Establish an SAP BAPI connection with HCL® OneTest™ Data	Establishing an SAP BAPI connection with HCL OneTest Data on page 206
Generate a schema in HCL® OneTest™ Data	Generating a schema in HCL OneTest Data on page 207
Generate test data in HCL® OneTest™ Data	Generating test data on page 217

Related information


SAP applications on page 774

Installing the SAP connector files in HCL OneTest Data

To generate a schema in HCL® OneTest[™] Data, you must install the SAP connector files in HCL® OneTest[™] Data.

- 1. Download the SAP connector files libsapjco3.so and sapjco3.jar to your local file system.
- 2. Copy the connector files from your local file system to the *HIP Server* pod by using the following commands from the command prompt:

```
kubectl cp /source path/libsapjco3.so {my-ots}-hip-server-0:/opt/hcl/hip/libs/libsapjco3
kubectl cp /source path/sapjco3.jar {my-ots}-hip-server-0:/opt/hcl/hip/libs/sapjco3.jar
```



3. Enter the following command to change the current user as the root user:

chown <user>:root libsapjco3.so sapjco3.jar

4. Run the following command to modify the access permissions of the connector file:

chmod 777 libsapjco3.so sapjco3.jar

Results

You have successfully installed the SAP connector files in HCL® OneTest[™] Data.

What to do next

You must establish the connection between HCL® OneTest[™] Data and the SAP BAPI connector. See Establishing an SAP BAPI connection with HCL OneTest Data on page 206.

Establishing an SAP BAPI connection with HCL OneTest Data

When you want to generate a schema for SAP BAPI, you must establish a connection between HCL® OneTest[™] Data and SAP BAPI.

Before you begin

You must have installed the SAP connector files in HCL® OneTest[™] Data. Ensure that you have installed the connector files a few minutes back. See Installing SAP connector files in HCL OneTest Data on page 205

- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.
- Result

The Overview page is displayed.

- 3. Click Author > Data Fabrication.
 - Result

The Data Fabrication page is displayed.

- 4. Click Connections.
- 5. Click **New** to create a new connection type.

The New Connection dialog box is displayed.

- 6. Select SAP BAPI from the Type drop-down list, and then click Next.
- 7. Set the following properties under Connection Properties, and then save the changes:

- Enter the SAP System host name in the Host ID field.
- Enter Client Number and System ID of the SAP System.
- Provide the SAP System credentials in the User and Password fields for authentication.
- 8. Go to the **Connection Properties** pane of the **Data Fabrication** page, and then click **Test** to verify whether the connection is established successfully.

Note: Your connection might fail to establish because of any one of the following reasons:

- Trouble at the SAP server port.
- ∘ Firewall blockage between HCL OneTest[™] Server and the SAP server.
- Unsuccessful copying of the connector files.
- Unsuccessful refresh of the HIP Server pod.
- 9. Click Next, and then provide a name for the SAP BAPI connection that you established.
- 10. Click OK.

You can view the name of the SAP BAPI connection under the Connections tab.

Results

You have successfully established the connection between HCL® OneTest[™] Data and SAP BAPI.

What to do next

You must generate a schema in HCL® OneTest[™] Data by using the SAP BAPI. See Generating a schema in HCL OneTest Data on page 207.

Generating a schema in HCL OneTest Data

After you establish the connection between HCL® OneTest[™] Data and an SAP BAPI, you can generate a schema in HCL® OneTest[™] Data.

- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.
 - Result

The Overview page is displayed.

3. Click Author > Data Fabrication.

Result

The Data Fabrication page is displayed.

- 4. Click Connections.
- 5. Select the SAP BAPI connection name that you established, and then click New Action from the menu.

The **New Action** dialog is displayed.

- 6. Select Target as the action type, and then click Next.
- 7. Enter the following properties for the new action:

- a. Click Fetch to select the function module category from the BAPI Function Module category dropdown list.
- b. Click **Fetch** to select the function module of the selected function module category from the **BAPI Function Module** drop-down list.
- 8. Click Next.
- 9. Select New, and then click Generate to generate a new schema in HCL® OneTest[™] Data.

The schema with a name as schema_<number> is generated in HCL® OneTest[™] Data.

The Schema Type is populated automatically based on the selected BAPI function module.

Note: You must select this schema name as the schema for HCL® OneTest[™] Data to generate the test data.

10. Click Next, and then provide the identification details of the new action.

11. Click OK.

The new action is created and is listed under the SAP BAPI connection.

Results

You have successfully generated a schema for SAP BAPI in HCL® OneTest[™] Data.

Note: You can modify the schema name schema_<number> from the Schemas tab.

What to do next

You can generate the test data by using the generated schema. See Generating test data on page 217.

HCL OneTest Data support to write the generated test data in MongoDB

When you use MongoDB as a database in your application testing environment and you want the generated test data in MongoDB, then you can generate the test data by using HCL® OneTest[™] Data. Subsequently, HCL® OneTest[™] Data inserts the generated test data directly in MongoDB.

To enable HCL® OneTest[™] Data to write the generated test data in the database, you must either import or create a schema in HCL® OneTest[™] Data, and then establish a connection with MongoDB. After you establish the connection, you must associate the selected schema with MongoDB, and then generate the test data by using HCL® OneTest[™] Data. Subsequently, HCL® OneTest[™] Data writes the generated test data directly in MongoDB.

Important: HCL® OneTest[™] Data always writes the generated test data in MongoDB in the JSON format.

Prerequisites

You must have access to HCL OneTest[™] Server.

Task flow

You must perform the following tasks in sequence to enable HCL® OneTest[™] Data to write the generated test data directly in MongoDB. The table also provides you the links to the information about the tasks.

Task	More information
Create a schema in HCL® OneTest™ Data Import a JSON or XSD into HCL® OneTest™ Data project	Create a schema in HCL OneTest Data on page 169 Import a JSON or XSD into HCL OneTest Data project on page 166
Establish a MongoDB connection with HCL® OneTest™ Data	Establishing a MongoDB connection with HCL OneTest Data on page 209
Associate a schema with MongoDB	Associating a schema with MongoDB on page 210
Insert the generated test data in a database	Inserting the generated test data in a database on page 212

Establishing a MongoDB connection with HCL OneTest Data

You must establish a connection between HCL® OneTest[™] Data and MongoDB to associate a schema with the database.

Before you begin

You must have completed the following tasks:

- Created or imported a schema in the HCL® OneTest[™] Data project.
- Installed MongoDB on your computer and the MongoDB instance must be ready to connect. For more information, refer to Install MongoDB.
- Created a database in MongoDB. For more information, refer to Database Methods.
- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.

Result

The **Overview** page is displayed.

3. Click Author > Data Fabrication.

Result

The Data Fabrication page is displayed.

- 4. Click Connections.
- 5. Click **New** to create a new connection.

The New Connection dialog is displayed.

- 6. Select MongoDB as a connection type and click Next.
- 7. Enter the following properties of the connection in the Properties dialog:
 - a. Enter the host name of MongoDB in the Host field.
 - b. Enter the server port number of the computer where MongoDB is running in the Port field.
 - c. Enter the user name and password to access MongoDB.
- 8. Click **Test** to verify whether the connection is established successfully.



Note: If the connection fails to establish, it can be because of any one of the following reasons:

- Unreachable database.
- Missing database.
- Incorrect host name and port number.
- 9. Click **Fetch** to upload all the databases available in the configured MongoDB in the **Database** drop-down list, and then select the database that you want to use to write the generated test data.
- 10. Click Next, and then provide a name to the established MongoDB connection.
- 11. Click OK.

You can see the name of the MongoDB connection under the Connections tab.

Results

You have successfully established the connection between HCL® OneTest[™] Data and MongoDB.

What to do next

You must associate a schema with a database of MongoDB. See Associating a schema with MongoDB on page 210.

Associating a schema with MongoDB

After you establish the connection between HCL® OneTest[™] Data and MongoDB, you must associate a schema with a database of MongoDB. You must select the schema that you want to use to generate the test data.

Before you begin

You must have created a collection in the selected MongoDB database.

For more information, refer to db.createCollection() section of Database Methods.

About this task

You can associate any schema with the MongoDB database that can generate the test data in the JSON format.

The following schema formats support the output format in JSON:

- Excel
- JDBC
- XSD
- CSV

1. Log in to HCL OneTest[™] Server and open the team space that contains your project.

2. Open your project.

Result

The **Overview** page is displayed.

3. Click Author > Data Fabrication.

Result

The Data Fabrication page is displayed.

- 4. Click the Connections tab and select the MongoDB connection name that you created.
- 5. Click the menu and select New Action.
- 6. Select Target as the Action Type in the New Action dialog, and then click Next.
- 7. Click **Fetch** to extract a list of all the collections of the selected database, and then select a collection from the **Collection** drop-down list.



You can retain the default property settings for all other boxes.

- 8. Click Next to provide the schema details.
- 9. Click the Schema drop-down list to select the schema that you want to use to generate the test data.
- 10. Click the **Schema Type** drop-down list to select the group type for which you want to generate the test data, and then click **Next**.
- 11. Provide the identification details of the new action, and then click OK.

The new action is created and listed under the MongoDB connection.

Results

You have successfully associated the schema with the database.

i Tip: If you want to associate any other schema in the same database, then you must click **New Action** on the existing MongoDB connection. You need not create a new connection.

What to do next

You can generate the test data from the schema that you associated with the database of MongoDB. The generated test data is directly inserted into the database. See Inserting the generated test data in a database on page 212.

Inserting the generated test data in a database

After you associate a schema with a database of MongoDB, you can generate the test data and insert the generated test data directly in the database by using HCL® OneTest[™] Data.

Before you begin

You must have associated the schema with MongoDB. See Associating a schema with MongoDB on page 210.

- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.
- Result
- The **Overview** page is displayed.
- 3. Click Author > Data Fabrication.

Result

The Data Fabrication page is displayed.

- 4. Select the schema that you associated with the database from the Schemas tab.
- 5. Select the group type of the schema for which you want to generate the test data.
- 6. Click the menu of the selected group type, and then click Generate Data.

You can view the list of all item types associated with the selected group type in the structure view.

Result

The Generate Data dialog is displayed.

- 7. Select the **Connection** option.
- 8. Select the **MongoDB** connection name that you established from the **Connections** drop-down list.

Note:

When you select MongoDB to insert the generated test data, you can generate only one record of test data at a time.

9. Provide a value for Numeric Seed Value, and then click OK.

Results

You have successfully generated and inserted the test data in MongoDB.

What to do next

You can click the **Jobs** tab to view the status of the job. When you hover over the status of the job, you can view the following details in the tooltip:

- Connection URL that includes details of host name and port number.
- Name of the collection.
- Database name with which the schema is associated.

Important:

You cannot download the generated test data from the **Jobs** page because the test data is written directly in the MongoDB database and the generated test data is not available in HCL® OneTest[™] Data.

You must log in to the database to view the generated test data.

HCL OneTest Data support to generate test data for an Excel file

When you use Microsoft Excel as a database in your application testing environment and you want to use the structure of an Excel file to generate test data, then you can generate the test data for the selected Excel file by using HCL® OneTest[™] Data.

When you want to generate the test data for the Excel file, then you must import the file into your HCL® OneTest[™] Data project. After importing the file, you must establish a connection between Excel and HCL® OneTest[™] Data. The established connection helps to transfer the data and interpret the data of the imported Excel file into your HCL® OneTest[™] Data project. The interpreted information then helps HCL® OneTest[™] Data to generate a schema. You can then use the generated schema to generate the test data in HCL® OneTest[™] Data.

Prerequisites

The following prerequisites must be met to enable HCL® OneTest[™] Data to write the generated test data:

- You must have access to HCL OneTest[™] Server.
- You must have an Excel file on your computer.

Task flow

You must perform the following tasks in sequence to enable HCL® OneTest[™] Data to generate the test data for the Excel file. The table also provides you the links to the information about the tasks.

Task	More Information
Import an Excel file.	Importing an Excel file. on page 214
Establish a connection between Excel and HCL® OneTest™ Data.	Establishing a connection between Excel and HCL OneTest Data on page 214.

Task	More Information
Generate a schema based on an Excel file.	Generating a schema based on an Excel file on page 215.
Generate test data by using the generated schema.	Generating test data by using the generated schema on page 216.

Importing an Excel file

When you want to establish a connection between HCL® OneTest[™] Data and an Excel file, you must import the Excel file into your HCL® OneTest[™] Data project from your computer.

Before you begin

You must have completed the following tasks:

- Created a project in HCL OneTest[™] Server.
- Opened an Excel file or created a file if it did not exist.
- 1. Select your project in HCL OneTest[™] Server and navigate to the **Data Fabrication** page.
- 2. Click Files, and then click New to import the Excel file from the computer into your project.

Results

You have successfully imported the Excel file from the computer into your project.

What to do next

You must establish a connection between Excel and HCL® OneTest[™] Data. See Establishing a connection between HCL OneTest Data and Excel on page 214.

Establishing a connection between HCL OneTest Data and Excel

When you want to generate a schema based on an Excel file, you must establish a connection between HCL® OneTest[™] Data and Excel.

Before you begin

You must have imported an Excel file from your computer into your project. See Importing an Excel file on page 214.

- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.

Result

The **Overview** page is displayed.

3. Click Author > Data Fabrication.

Result

The **Data Fabrication** page is displayed.

- 4. Click Connections.
- 5. Click **New** to create a new connection.

The New Connection dialog is displayed.

- 6. Select Excel as a connection type, and then click Next.
- 7. Provide a name for this connection.
- 8. Click **OK**.

You can see the name of the connection under the Connections tab.

Results

You have successfully established the connection between HCL® OneTest[™] Data and Excel.

What to do next

You must generate a schema in HCL® OneTest[™] Data based on the Excel file. See Generating a schema based on Excel file on page 215.

Generating a schema based on an Excel file

After you establish the connection between HCL® OneTest[™] Data and Excel, you can generate a schema that is based on an Excel file in HCL® OneTest[™] Data.

- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.

Result

The Overview page is displayed.

3. Click Author > Data Fabrication.

Result

The Data Fabrication page is displayed.

- 4. Click the **Connections** tab and select the connection that you created.
- 5. Click the menu, and then select New Action.
- 6. Select Target as the Action Type in the New Action dialog, and then click Next.
- 7. Enter the following properties of the schema that you want to generate, and then click Next:
 - Select the Excel file that you imported into your project from the Excel File drop-down list.
 - \circ Click Fetch to upload all the worksheets of the Excel file in the Worksheet drop-down list.
 - Select the worksheet from the Worksheet drop-down list.



You can retain the default property settings for all other fields.

8. Select New, and then click Generate.

The schema is generated in HCL® OneTest[™] Data. HCL® OneTest[™] Data generates the schema name as schema_<number>.

Note: You must select this schema name as the schema for HCL® OneTest[™] Data to generate the test data.

- 9. Select the schema type as Sheet.
- 10. Click Next to provide the identification details of the new action, and then click OK.

The new action is created and listed under the connection that is established between HCL® OneTest[™] Data and Excel.

Results

You have successfully generated the schema in HCL® OneTest[™] Data.



You can modify the schema name schema_<number> from the Schemas tab.

Tip: If you want to generate schemas for other Excel files, then you must click **New Action** on the existing Excel connection. You need not create a new connection.

What to do next

You can view the generated schema listed under the **Schemas** tab. You can generate the test data for the generated schema in HCL® OneTest[™] Data. See Generating test data by using the generated schema on page 216.

Generating test data by using the generated schema

After you generate the schema in HCL® OneTest[™] Data, you can use this schema to generate the test data in HCL® OneTest[™] Data.

Before you begin

You must have generated the schema by using the connection that is established between HCL® OneTest[™] Data and Excel. See Generating a schema based on Excel file on page 215.

- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.

Result

The Overview page is displayed.

3. Click Author > Data Fabrication.

Result

The Data Fabrication page is displayed.

4. Select the schema name schema_<number> from the Schemas tab.

Result

The schema is displayed.

5. Select the **Sheet** group type, and then select **Structure** from the menu.

You can view a group as **Row** in the structure of the schema. All item types of a schema are listed under the **Row** group type.

- 6. Click the menu for the Row group type, and then set the property as Set Required.
- 7. Click the menu for all the item types that you want to use to generate the test data, and then set the property as **Set Required**.



Note: If you have a numeric item type, you must set Min size (digits) and Max size (digits) properties.

For example, when you select Integer as **Presentation**, then you can set the **Min size (digits)** as 1 and the **Max** size (digits) as 9.

- 8. Click Save.
- 9. Select the Sheet group type in the Dictionary dialog, and then click Generate Data from the menu.

The Generate Data dialog is displayed.

- 10. Provide the number of records that you want to generate in Number of records.
- 11. **Optional:** Provide a seed value that acts as a reference number to generate the same set of data in **Numeric Seed Value**.
- 12. Select the output file format for the generated test data from the list, and then click OK.

Results

You have successfully generated the test data by using the generated schema.

What to do next

You can click the **Jobs** tab to view the status of the job. You can then download the generated test data of the jobs that are completed successfully.

Generating test data

When you have a defined and structured schema for the entire data, you can generate test data to perform application testing.

Before you begin

The following prerequisites must be met to generate the test data:

- You must have created a project.
- The schema must have a group type.
- You must have a structured view of your defined schema.

About this task

You can generate the sample test data from the group type of schema. When you import the XSD format schema, then HCL® OneTest[™] Data generates only XML test data. If you import JSON format as input, the application generates only JSON test data.

- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.

Result

The **Overview** page is displayed.

3. Click Author > Data Fabrication.

Result

The Data Fabrication page is displayed.

- 4. Click the Schemas tab and select the schema for which you want to generate the test data.
- 5. Select the group type that you want to use to generate the test data from the Dictionary dialog.
- 6. Click Generate Data from the menu.

Result

The Generate Data dialog is displayed.

7. Enter the number of records that you want to generate in the **Number of records** field.

Important: When you select the pairwise data generation property for any item type, then the number of records you enter is ignored. Based on the pairwise data generation approach, HCL® OneTest[™] Data autocalculates the number of records.

8. Enter seed value in the Numeric Seed Value field.

The seed value acts as an instance of random data that can produce the same set of data multiple times. By default, the seed value is blank.



Note: The following table lists the maximum values for numeric seed value and number of records:

Description	Maximum values
Numeric Seed Value	8 digits (99,999,999)

Description	Maximum values
Number of records	9 digits (999,999,999)

9. Choose the output file format of the test data that you want to generate from the **Output File Format** list. HCL® OneTest[™] Data supports the following formats:

- ∘ CSV
- Native
- JSON
- $\circ \text{XML}$
- Excel



- \circ If you create a schema by using the schema designer, by default, the output file format is CSV.
- If you import a schema into your project or have a schema with nested groups, you can select only the Plain text file as the output file format.
- You can generate line numbers in the output by creating an auto-increment rule by using functions and expressions.

10. Click OK.

Results

The test data is generated successfully.

Note: The column headings for the generated test data are available only for the CSV and Excel file output formats.

What to do next

You can view and download the generated test data on the **Jobs** page. See Status of generated test data on page 243.

Generating the test data by using multiple schemas

You can generate the test data either by using multiple JDBC-supported or non-JDBC schemas.

Before you begin

You must have completed the following tasks:

- Logged into HCL OneTest[™] Server.
- Installed any JDBC-supported database, such as Oracle, MySQL, and so on, for generating the test data from JDBC-supported schemas.

About this task

You can generate the test data for multiple schemas simultaneously. To generate the test data you can either use only JDBC-supported schemas or non-JDBC schemas.

To generate the test data by using multiple JDBC-supported schemas, you must create tables in a database that are supported by the JDBC connection. After you establish the JDBC connection between the database and HCL® OneTest[™] Data, you must generate multiple schemas. You can then import the selected schemas into the **Schema Canvas** page. After you import the schemas into the **Schema Canvas** page, you can view an existing parent-child relationship. You must select a single schema or multiple schemas for which you want to generate the test data, and then generate the test data.

To generate the test data by using multiple non-JDBC schemas, you must create a schema in HCL® OneTest[™] Data. You must then define the properties and structural view of the schemas. When the schemas are created, you can import the selected schemas into the **Schema Canvas** page. After you import the schemas into the **Schema Canvas** page, you can view an existing parent-child relationship or establish a relationship among the schemas. You must select the schemas, and then generate the test data.



- When you generate the test data by using multiple schemas, you must select either JDBC-supported or non-JDBC schemas.
- When you select a child schema on the **Schema Canvas** page, the parent schema is automatically selected. Similarly, if you select a parent schema, then all the child schemas are selected on the **Schema Canvas** page.

The output formats that are supported in HCL® OneTest[™] Data for the generation of test data for multiple schemas by using referential integrity are CSV, Excel, Native, JSON, and XML. You can also insert the generated test data into the database by using the JDBC connection.

Note: You can generate the test data among the common output formats that are supported by all selected schemas.

- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.

Result

The Overview page is displayed.

3. Click Author > Data Fabrication.

Result

The Data Fabrication page is displayed.

4. Choose any one of the following types of schemas that you want to use to generate the test data: **Choose from:**

• JDBC

You must perform the following tasks to generate the test data in HCL® OneTest[™] Data for multiple JDBC-supported schemas:

- a. Create a sample schema in a database on page 195.
- b. Establish a JDBC connection with HCL OneTest Data on page 197.
- c. Generate a schema in HCL OneTest Data on page 199.
- d. Define properties of schemas on page 222.
- e. Import schemas into Schema Canvas on page 224.
- f. Select schemas on page 231.
- g. Generate test data for selected schemas on page 219.
- Non-JDBC

You must perform the following tasks to generate the test data in HCL® OneTest[™] Data for multiple non-JDBC schemas:

- a. Create schemas on page 169.
- b. Design schemas on page 174.
- c. Import schemas into Schema Canvas on page 224.
- d. Establish a parent-child relationship among schemas on page 228.
- e. Select schemas on page 231.
- f. Generate test data for selected schemas on page 219.

Results

You have generated the test data by using multiple schemas simultaneously.

Selecting multiple schemas

After you define the properties of schemas, you must select schemas and view the relationships among them to generate the test data for multiple schemas simultaneously.

Before you begin

You must have completed the following tasks:

- 1. Created a project.
- 2. Generated schemas in HCL® OneTest[™] Data by using a JDBC connection. See Generating a schema in HCL OneTest Data on page 199.
- 3. Defined properties for the generated schemas. See Defining properties of schemas on page 222.
- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.

Result

The Overview page is displayed.

3. Click Author > Data Fabrication.

Result

The Data Fabrication page is displayed.

4. Click Schema Integrity to select schemas.

Result

The Select Schemas dialog is displayed.

- 5. Click the field to view the list of schemas that are generated by using the JDBC connection.
- 6. Select multiple schemas.



Note: You can select a maximum of 10 schemas.

7. Click Import to import the selected schemas into the Schema Integrity page.

You can find the structural view of all the selected schemas with their relationships with each other.



Note: You can use the scroll wheel or pinch-to-zoom option on the **Schema Integrity** page to view the structural view of all schemas and relationships.

- 8. Verify the relationships among the selected schemas.
- 9. Select schemas based on the following criteria:
 - If a schema does not have a relationship with any other schema on the Schema Integrity page, then you must select that schema manually. Otherwise, click Select All to select all schemas to generate the test data.
 - If a schema has a relationship with other schemas and is selected, then all the related schemas get selected automatically.

Notes:

- You cannot select schemas that belong to different JDBC connections.
- \circ You can use Modify canvas to add or remove the selected schemas.
- If any of the selected schema is deleted from the workspace, then the view of the Schema Integrity page changes as the deleted schema is removed from the Schema Integrity page.

Results

You have successfully selected multiple schemas for the generation of test data.

What to do next

You can generate the test data for the selected schemas. See Generating test data for selected schemas on page 234.

Defining properties of schemas

After you generate the schema from the configured database in HCL® OneTest[™] Data, you must define the required properties for all schemas.

Before you begin

You must have completed the following tasks:

- 1. Created a project.
- 2. Generated schemas in HCL® OneTest[™] Data by using a JDBC connection. See Generating a schema in HCL OneTest Data on page 199.
- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.

Result

The Overview page is displayed.

3. Click Author > Data Fabrication.

Result

The **Data Fabrication** page is displayed.

4. Select the generated schema from the Schemas tab.

For example, schema_<number>

5. Click the **Menu** icon **i** of the group type of the schema and select **Structure**.

You can view the list of all item types associated with the selected group type in the structural view of the schema.

- 6. Click the **Menu** icon icon of all item types in the **Structure** dialog to set the following properties:
 - a. Click Set Required to get at least one occurrence of the item type in the generated test data, and then click Save.
 - b. Click Properties for the selected item types and perform the following steps for Item Properties:
 i. Verify the values of the Item Subclass and Presentation fields.

For example, if the item type is of a *number* data type, then the value for **Item Subclass** is Number and **Presentation** is Integer.

ii. Set the Min size and Max size for the item types of the schema.

If the value of **Subclass** is Number and **Presentation** is Integer for an item type, then set the value of **Min size** and **Max size** as the number of digits that can be generated in the test data.



Note: The value for Min size (digits) should be less than or equal to Max size (digits).

For example, if the item type is of a *number* data type, then you can set the **Min size (digits)** as 1 and the **Max size (digits)** as 9.



- The values of both the Min size (digits) and Max size (digits) properties for item types that act as a primary and foreign keys must be same.
- You must set the value of **Min size** and **Max size** for an Integer item type such that the number of digits of the generated test data is between the range of 1 and 9 and the generated test data is between -2147483648 to 2147483647.
- 7. Save the changes.

You must repeat steps 2 through step 5 to set the properties for all schemas.

Results

You have defined the properties for all schemas.

What to do next

You can click **Schema Canvas** to select the defined and structured schemas that you want to use to generate the test data. See Selecting multiple schemas on page 221.

Related information

Item properties on page 792

Setting a range on page 188

Importing schemas into the Schema Canvas page

When you want to generate the test data or the Data Definition Language (DDL) statements by using single or multiple schemas, you must import schemas into the **Schema Canvas** page. You can import multiple schemas simultaneously.

Before you begin

You must have fabricated schemas in HCL® OneTest[™] Data.

About this task

To import the schemas, you must select the type of schemas that you want to import. You can import either the JDBC-supported schemas or non-JDBC schemas into the **Schema Canvas** page. You can view the list of schemas under the **Schemas** tab of the **Canvas Settings** dialog. Under the **Groups** tab, you can view the list of all the group types of the schemas. You can also enter the text in the **Search** field to find the schemas or the group types that match with the characters of the search text.

The schemas or the group types that you select to import are listed under the Selected Schemas panel.

- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.

Result

The **Overview** page is displayed.

3. Click Author > Data Fabrication.

Result

The Data Fabrication page is displayed.

4. Click Schema Canvas to select the schemas.

Result

The Canvas Settings dialog is displayed.

- 5. Select any one of the following options in the Canvas Settings dialog to display the list of schemas:
 - JDBC: When you select JDBC, you can view only the list of JDBC-supported schemas. To import the JDBC schemas, go to Step 4.
 - Non-JDBC: When you select Non-JDBC, you can view only the list of non-JDBC schemas. To import the non-JDBC schemas, go to Step 5.
- 6. For JDBC schemas: Select a schema by using any one of the following methods:

Choose from:

- Use the **Database** tab:
 - a. Click the **Database** tab.
 - b. Select a schema.

The group types within the selected schemas are selected.



- You can also search for the schema by entering the name of the schema in the Search field.
- Each JDBC schema includes only one group type.
- The group types are selected automatically with the selection of schemas.

• Use the Table tab:

- a. Click the Table tab.
- b. Select the group type.

The group types along with their schemas are selected.



Note: You can find only one group type in JDBC schemas.

Result

The selected schemas are displayed in the Selected Schemas panel.



Ż

- If you select a child schema, then the parent schema is selected automatically.
- If you select a child group, then the parent group of parent schema is selected automatically.
 If you clear the selection of any group type of schema, then you can view the updated list of the selected schemas in the Selected Schemas panel.
- 7. For Non-JDBC schemas: Select a schema by using any one of the following methods:

Choose from:

- Use the Schema tab:
 - a. Click the Schema tab.
 - b. Select a schema.

The group types within the selected schema are displayed.



Note: You can also search for the schema by entering the name of the schema in the **Search** field.

c. Select the group types of the selected schema that you want to import.



Note: You can select multiple group types from a single schema.

- Use the Group tab:
 - a. Click the Group tab.
 - b. Select the group types that you want to import.

The group types along with their schemas are selected.

Result

The selected schemas are displayed in the Selected Schemas panel.

Notes:

- \circ If you select a child schema, then the parent schema is selected automatically.
- If you select a child group, then the parent group of the parent schema is selected automatically.
- If you clear the selection of any group type of schema, then you can view the updated list of the selected schemas in the **Selected Schemas** panel.

8. Click Set Canvas.

Result

The selected schemas are imported into the Schema Canvas page.



Note: If you select multiple group types from the same schema and import that schema into the **Schema Canvas** page, then the structure of each group is represented separately on the **Schema Canvas** page.

Results

You have imported the non-JDBC schemas into the Schema Canvas page.

What to do next

You must select schemas from the **Schema Canvas** page before generating the DDL statements or the test data. See Selecting schemas on page 231.

You can also establish a new parent-child relationship among non-JDBC schemas. See Establishing a parent-child relationship within different schema groups on page 228.

After you import schemas into the **Schema Canvas** page, if you want to modify or remove the selection of schemas, then you must click the **Modify canvas** button on the **Schema Canvas** page. See Modifying the selection of imported schemas on page 233.

Parent-child association among schemas

When you want to apply the referential integrity rules among multiple non-JDBC schemas, you must associate a parent-child relationship among schemas on the **Schema Canvas** page.


When you want to maintain a logical relationship among multiple schemas, then you must establish a parent-child relationship among those schemas. The parent and child schemas must be related to each other by using common item types. The item type of the parent schema is designated as the Primary key, and the related item type of child schema is designated as the Foreign key.

The referential integrity among the parent and child schemas in HCL® OneTest[™] Data supports the following relations:

- One-to-one
- One-to-many
- Many-to-one
- Self-reference



....



• The item types that relate to parent-child schemas must be of the same data type and size.

You can find information about establishing a parent-child relationship within the different schema groups in the following topic:

Establishing a parent-child relationship within different schema groups on page 228

Establishing a parent-child relationship within different schema groups

When you want the same data field to be included in the different schema groups simultaneously, you can establish a parent-child relationship between a single parent schema group with multiple child schema groups.

Before you begin

You must have completed the following tasks:

- Created a project on HCL OneTest[™] Server.
- Fabricated the schemas in HCL® OneTest[™] Data. See Schema fabrication on page 165.
- Defined the properties of schemas. See Schema design overview on page 174.
- Imported the schemas. See Importing schemas into the Schema Canvas page on page 224.

About this task

You can identify the schemas for which you want to establish a parent-child relationship in the referential integrity, and connect the item type of the parent schema to the same item type of child schemas within different schema groups.

- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.

Result

The Overview page is displayed.

- 3. Click Author > Data Fabrication.
 - Result

The Data Fabrication page is displayed.

4. Click Schema Canvas.

Result

The Schema Canvas page is displayed.

You can view the structural view of all the imported schemas and their relationships with each other.

Note: You can use the scroll wheel or pinch-to-zoom option on the Schema Canvas page to view the structural view of all schemas and relationships.

- 5. Identify the schemas for which you want to establish a parent-child relationship.
- 6. Click the item type of the parent schema that you want to use as a Primary key.
- 7. Hover the mouse from the item type of the parent schema to the item type of the child schema.

Result

A line is drawn between the parent schema and the child schema to represent the relationship among both the schemas.

8. Identify the child schemas and connect the parent schema to multiple child schemas.

Results

You have established a parent-child relationship between a single parent schema with multiple child schemas within different schema groups.

What to do next

You must select schemas on the **Schema Canvas** page to generate the test data. See Selecting schemas on page 231.

You can click the **Modify canvas** button to modify or remove the selection of schemas that you imported into the **Schema Canvas**. See Modifying the selection of imported schemas on page 233.

Modifying a relationship among schemas

When you want to alter the existing relationship between schemas, then you can modify the established relationship on the **Schema Canvas** page.

Before you begin

You must have completed the following tasks:

- 1. Created a project.
- 2. Fabricated the schemas in HCL® OneTest[™] Data. See Schema creation on page 168.
- 3. Defined properties for the fabricated schemas. See Defining properties of schemas on page 222.
- Imported schemas from the Schema Canvas page. See Importing schemas into the Schema Canvas page on page 224.
- 5. Established relationships among non-JDBC schemas. See Establishing a parent-child relationship within different schema groups on page 228.
- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.

Result

The **Overview** page is displayed.

3. Click Author > Data Fabrication.

Result

The Data Fabrication page is displayed.

4. Click Schema Canvas.

Result

The Schema Canvas page is displayed.

- 5. Identify an item type of a relationship that you want to modify.
- 6. Hover over the relationship line that you selected.
- 7. Click the end of the relationship line that points to the item type you want to modify.
- 8. Drag-and-drop the line to the item type with which you want to establish a new relationship.



- You can select an item type either from the same schema or a different schema to establish a new relationship.
- You can modify only the child schemas in a relationship.

Results

The relationship is modified among the item types of non-JDBC schemas.

What to do next

You can establish another relationship among the item types of other schemas. See Establishing a parent-child relationship within different schema groups on page 228.

You can also select the schemas on the **Schema Canvas** page to generate the test data. See Selecting schemas on page 231.

Deleting a relationship among schemas

When any established relationship among the item types of non-JDBC schemas is no longer required, you can delete that relationship on the **Schema Canvas** page.

Before you begin

You must have completed the following tasks:

- 1. Created a project.
- 2. Fabricated the schemas in HCL® OneTest[™] Data. See Schema creation on page 168.
- 3. Defined properties for the fabricated schemas. See Defining properties of schemas on page 222.
- Imported schemas from the Schema Canvas page. See Importing schemas into the Schema Canvas page on page 224.
- 5. Established relationships among non-JDBC schemas. See Establishing a parent-child relationship within different schema groups on page 228.
- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.

Result

The **Overview** page is displayed.

- 3. Click Author > Data Fabrication.
- Result

The Data Fabrication page is displayed.

4. Click Schema Canvas.

Result

The Schema Canvas page is displayed.

- 5. Identify a relationship among schemas that you want to delete.
- 6. Hover over the relationship line of the selected relationship.

Result

You can view a red cross mark 🔯 on the line that is drawn to show the relationship among the schemas.

7. Click the red cross mark 🔀 to delete the relationship.

Alternatively, click the arrow ⋗ of the drawn line, and then drag-and-drop the line anywhere on the Schema Canvas page.

Result

The Detach relationship dialog is displayed for your confirmation before the deletion of the relationship.

8. Click Detach.

Result

The line that is drawn among the schemas is erased.

Results

The relationship is deleted among the item types of non-JDBC schemas.

What to do next

You can establish another relationship among the item types of other schemas. See Establishing a parent-child relationship within different schema groups on page 228.

You can also select the schemas on the **Schema Canvas** page to generate the test data. See Selecting schemas on page 231.

Selecting schemas

After you import schemas into **Schema Canvas**, you must select schemas to view the relationships among them, generate the Data Definition Language (DDL) statements, or generate the test data for multiple schemas simultaneously.

Before you begin

You must have completed the following tasks:

- 1. Created a project.
- 2. Fabricated the JDBC-supported or non-JDBC schemas in HCL® OneTest™ Data:

- For JDBC-supported schemas, see Generating a schema in HCL OneTest Data on page 199.
- For non-JDBC schemas in HCL® OneTest[™] Data, see Schema creation on page 168.
- 3. Defined properties for the generated schemas. See Defining properties of schemas on page 222.
- 4. Imported schemas into the Schema Canvas page. See Importing schemas into the Schema Canvas page on page 224.

About this task

You can view all the imported schemas on the **Schema Canvas** page. When you select a schema on the **Schema Canvas** page, the other schemas are also selected if they are related to each other based on referential integrity. Otherwise, you can select **Select All** to select all the schemas that are imported on the **Schema Canvas**.

- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.

Result

The **Overview** page is displayed.

3. Click Author > Data Fabrication.

Result

The Data Fabrication page is displayed.

4. Click Schema Canvas.

Result

The Schema Canvas page is displayed.

You can view the structural view of all the imported schemas with their relationships with each other.

Notes:

- You can use the scroll wheel or pinch-to-zoom option on the **Schema Canvas** page to view the structural view of all schemas and relationships.
- When you rename or delete any schema or item types that are imported to the **Schema Canvas** page, the relationships are altered and this alteration results in the failure of a generation of test data.
- 5. Verify the relationships among the selected schemas.
- 6. Select schemas based on the following criteria:
 - If a schema does not have a relationship with any other schema on the Schema Canvas page, then you
 must select that schema manually. Otherwise, select Select All to select all schemas to generate the
 test data.
 - If a schema has a relationship with other schemas and if it is selected, then all the related schemas are selected automatically.

Notes:

- $\,{}_{\circ}$ You cannot select schemas that belong to different JDBC connections.
- You can use Modify canvas to add or remove the selected schemas.

You must not select schemas with nested group types for the generation of DDL statements.
 If any of the selected schemas is deleted from the workspace, then the view of the Schema Canvas page changes because the deleted schema is removed from the Schema Canvas page.

Results

You have selected multiple schemas.

What to do next

You can perform any one of the following tasks:

- Generate DDL statements for the selected schemas. See Generating DDL statements on page 242.
- Generate the test data. See Generating test data for selected schemas on page 234.

Modifying the selection of imported schemas

After you import schemas into the **Schema Canvas** page, if you want to modify or remove the selected schemas, then you can modify the **Schema Canvas** page.

Before you begin

You must have completed the following tasks:

- · Created a project.
- Fabricated the schemas in HCL® OneTest™ Data. See Schema fabrication on page 165.
- Defined the properties of schemas. See Schema design overview on page 174.
- Imported the schemas. See Importing schemas into the Schema Canvas page on page 224.

About this task

After you import the JDBC-supported or non-JDBC schemas from the **Canvas Settings** dialog into the **Schema Canvas** page, if you want to modify the selection of group types of a schema or number of schemas, then you must use the **Modify canvas** button. You can use the **Canvas Settings** dialog to reselect or clear the selection of schemas and the group types.

- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.

Result

The **Overview** page is displayed.

3. Click Author > Data Fabrication.

Result

The Data Fabrication page is displayed.

4. Click Schema Canvas to select the schemas.

Result

The Schema Canvas page is displayed.

5. Click the Modify canvas button.

Result

The Canvas Settings dialog is displayed.

- 6. Modify the selection of schemas or group types.
- 7. Click Set Canvas.

Result

The modified Schema Canvas page is displayed.

Results

You have modified the Schema Canvas page.

What to do next

You must select schemas from the **Schema Canvas** before generating the DDL statements or the test data. See Selecting schemas on page 231.

You can also establish a new parent-child relationship among non-JDBC schemas. See Establishing a parent-child relationship within different schema groups on page 228.

Generating test data for selected schemas

After you select multiple schemas on the **Schema Canvas** page, you can generate the test data of all the selected schemas simultaneously.

Before you begin

You must have completed the following tasks:

- 1. Created a project.
- 2. Fabricated the schemas in HCL® OneTest[™] Data. See Schema creation on page 168.
- 3. Defined properties for the fabricated schemas. See Defining properties of schemas on page 222.
- 4. Imported schemas from the **Schema Canvas** page. Importing schemas into the Schema Canvas page on page 224.
- 5. Established relationships among non-JDBC schemas. Establishing a parent-child relationship within different schema groups on page 228.
- 6. Selected the schemas. See Selecting schemas on page 231.

About this task

You can generate the test data for multiple schemas simultaneously. To generate the test data, you can either use only JDBC-supported schemas or non-JDBC schemas.

When you select multiple schemas from the **Schema Canvas** page, and one or more schemas among the selected schemas are enabled with the pairwise property, then the following number of records are generated for those schemas:

- If the selected schema is enabled with the pairwise property and is not referenced to any other schema, then the number of records generated are auto calculated based on the algorithm of the pairwise data generation.
- If the selected schema is enabled with the pairwise property and is referenced to at least one parent schema, then the number of records generated are among the least of the following values:
 - The number of records of each referenced parent schema.
 - \circ The auto calculated number of records of the schema with the pairwise property as enabled.
- If the selected schema is enabled with the pairwise property and is referenced by a child schema, which is not a pairwise enabled schema, then the number of records generated are among the least of the following values:
 - The number of records of each parent schema.
 - $\,\circ\,$ The value of the number of records that you enter.
- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.

Result

The Overview page is displayed.

3. Click Author > Data Fabrication.

Result

The Data Fabrication page is displayed.

4. Click Generate data to generate the test data for the selected schemas on the Schema Canvas page. Result

The Generate data dialog is displayed.

5. Select the **Connections** option for the output location to generate the test data for the JDBC-supported schemas.



Note: When you want to generate the test data for non-JDBC schemas, the options to select the output location are not displayed because the **File** option is considered as the default option.

- 6. Enter the number of records that you want to generate in the Number of records field.
- 7. Enter a seed value in the Numeric Seed Value field.

The seed value acts as an instance of random data that can generate the same set of data multiple times. The default seed value is blank.



Note: The following table lists the maximum values for numeric seed value and number of records:

Description	Maximum values
Numeric seed value	8 digits (99,999,999)

	Description	Maximum values
_	Number of records	9 digits (999,999,999)

- 8. Choose the output file format of the test data that you want to generate from the Output File Format list.
- 9. Click Analyze to validate the selected schemas.

If the selected schemas are validated successfully, then you can view the order of schemas execution for generating the test data. All the parent schemas are executed first followed by the child schemas.

Note: If the validation fails, it might be because of one of the following reasons:

- The parent schemas of all the selected schemas are missing.
- The connection and actions of selected schemas do not exist in the project.
- Any one of the following properties of all item types of the selected schemas are not set:
 - Min size (digits) and Max size (digits) properties for each integer item type.
 - Set Required property.

You must resolve the cause of failure for the successful validation of the schemas.

10. Click OK.

Results

You have generated the test data by using multiple schemas simultaneously.

HCL® OneTest[™] Data first generates the test data of the parent schema followed by the child schemas.

What to do next

You can view and download the generated test data of all the selected jobs on the **Jobs** page. See Status of generated test data on page 243.

Related information

Inserting the generated test data in a database on page 200

Item properties on page 792

Setting a range on page 188

Generating DDL statements for schemas

When you want to know the Structured Query Language (SQL) statements to create a table from non-JDBC schemas that you created in HCL® OneTest[™] Data, you can generate the Data Definition Language (DDL) statements for those selected schemas.

Before you begin

You must have completed the following tasks:

- Logged into HCL OneTest[™] Server.
- Created a project.
- Created schemas in HCL® OneTest™ Data. See Schema fabrication on page 165.

About this task

You can generate the SQL file with DDL statements to non-JDBC schemas only. You can also generate the DDL statements for multiple schemas simultaneously. To generate the DDL statements for any schema, you must create a schema in HCL® OneTest[™] Data, define the properties of the schema, and then import all the non-JDBC schemas for which you want to generate the DDL statements on the **Schema Canvas** page. After you import the schemas into the **Schema Canvas** page, you must select the schemas, and then generate the DDL statements.

You can find the generated SQL file with DDL statements for the selected schemas on the Jobs page.



- · You cannot generate the DDL statements for schemas with nested groups.
- The DDL statements for all the selected schemas that are available on the **Schema Canvas** page are generated in a single SQL file.
- 1. Create schemas on page 168.
- 2. Define properties of schemas on page 222.
- 3. Import non-JDBC-supported schemas on page 224.
- 4. Select schemas on page 231.
- 5. Generate DDL statements on page 242.

Results

You have generated the DDL statements for the selected non-JDBC schemas.

What to do next

You can download the generated DDL statements for each schema from the **Jobs** page. See Status of generated test data on page 243.

Importing schemas into the Schema Canvas page

When you want to generate the test data or the Data Definition Language (DDL) statements by using single or multiple schemas, you must import schemas into the **Schema Canvas** page. You can import multiple schemas simultaneously.

Before you begin

You must have fabricated schemas in HCL® OneTest[™] Data.

About this task

To import the schemas, you must select the type of schemas that you want to import. You can import either the JDBC-supported schemas or non-JDBC schemas into the **Schema Canvas** page. You can view the list of schemas under the **Schemas** tab of the **Canvas Settings** dialog. Under the **Groups** tab, you can view the list of all the group types of the schemas. You can also enter the text in the **Search** field to find the schemas or the group types that match with the characters of the search text.

The schemas or the group types that you select to import are listed under the Selected Schemas panel.

- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.

Result

The **Overview** page is displayed.

3. Click Author > Data Fabrication.

Result

The Data Fabrication page is displayed.

4. Click Schema Canvas to select the schemas.

Result

The Canvas Settings dialog is displayed.

- 5. Select any one of the following options in the Canvas Settings dialog to display the list of schemas:
 - JDBC: When you select JDBC, you can view only the list of JDBC-supported schemas. To import the JDBC schemas, go to Step 4.
 - Non-JDBC: When you select Non-JDBC, you can view only the list of non-JDBC schemas. To import the non-JDBC schemas, go to Step 5.
- 6. For JDBC schemas: Select a schema by using any one of the following methods:

Choose from:

- Use the **Database** tab:
 - a. Click the Database tab.
 - b. Select a schema.

The group types within the selected schemas are selected.

Notes:

- You can also search for the schema by entering the name of the schema in the **Search** field.
- Each JDBC schema includes only one group type.
- The group types are selected automatically with the selection of schemas.
- Use the **Table** tab:

- a. Click the Table tab.
- b. Select the group type.

The group types along with their schemas are selected.



Note: You can find only one group type in JDBC schemas.

Result

The selected schemas are displayed in the Selected Schemas panel.

Notes:

- If you select a child schema, then the parent schema is selected automatically.
- If you select a child group, then the parent group of parent schema is selected automatically.
- If you clear the selection of any group type of schema, then you can view the updated list of the selected schemas in the Selected Schemas panel.

7. For Non-JDBC schemas: Select a schema by using any one of the following methods:

Choose from:

- \circ Use the Schema tab:
 - a. Click the Schema tab.
 - b. Select a schema.

The group types within the selected schema are displayed.



Note: You can also search for the schema by entering the name of the schema in the **Search** field.

c. Select the group types of the selected schema that you want to import.



Note: You can select multiple group types from a single schema.

- Use the Group tab:
 - a. Click the Group tab.
 - b. Select the group types that you want to import.

The group types along with their schemas are selected.

Result

The selected schemas are displayed in the Selected Schemas panel.



- If you select a child schema, then the parent schema is selected automatically.
- If you select a child group, then the parent group of the parent schema is selected automatically.
- If you clear the selection of any group type of schema, then you can view the updated list of the selected schemas in the Selected Schemas panel.

8. Click Set Canvas.

Result

The selected schemas are imported into the Schema Canvas page.

Note: If you select multiple group types from the same schema and import that schema into the Schema Canvas page, then the structure of each group is represented separately on the Schema Canvas page.

Results

You have imported the non-JDBC schemas into the Schema Canvas page.

What to do next

You must select schemas from the **Schema Canvas** page before generating the DDL statements or the test data. See Selecting schemas on page 231.

You can also establish a new parent-child relationship among non-JDBC schemas. See Establishing a parent-child relationship within different schema groups on page 228.

After you import schemas into the **Schema Canvas** page, if you want to modify or remove the selection of schemas, then you must click the **Modify canvas** button on the **Schema Canvas** page. See Modifying the selection of imported schemas on page 233.

Selecting schemas

After you import schemas into **Schema Canvas**, you must select schemas to view the relationships among them, generate the Data Definition Language (DDL) statements, or generate the test data for multiple schemas simultaneously.

Before you begin

You must have completed the following tasks:

- 1. Created a project.
- 2. Fabricated the JDBC-supported or non-JDBC schemas in HCL® OneTest[™] Data:
 - For JDBC-supported schemas, see Generating a schema in HCL OneTest Data on page 199.
 - ∘ For non-JDBC schemas in HCL® OneTest™ Data, see Schema creation on page 168.

- 3. Defined properties for the generated schemas. See Defining properties of schemas on page 222.
- Imported schemas into the Schema Canvas page. See Importing schemas into the Schema Canvas page on page 224.

About this task

You can view all the imported schemas on the **Schema Canvas** page. When you select a schema on the **Schema Canvas** page, the other schemas are also selected if they are related to each other based on referential integrity. Otherwise, you can select **Select All** to select all the schemas that are imported on the **Schema Canvas**.

- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.

Result

The **Overview** page is displayed.

3. Click Author > Data Fabrication.

Result

The Data Fabrication page is displayed.

4. Click Schema Canvas.

Result

The Schema Canvas page is displayed.

You can view the structural view of all the imported schemas with their relationships with each other.

Notes:

- You can use the scroll wheel or pinch-to-zoom option on the **Schema Canvas** page to view the structural view of all schemas and relationships.
- When you rename or delete any schema or item types that are imported to the **Schema Canvas** page, the relationships are altered and this alteration results in the failure of a generation of test data.
- 5. Verify the relationships among the selected schemas.
- 6. Select schemas based on the following criteria:
 - If a schema does not have a relationship with any other schema on the Schema Canvas page, then you
 must select that schema manually. Otherwise, select Select All to select all schemas to generate the
 test data.
 - If a schema has a relationship with other schemas and if it is selected, then all the related schemas are selected automatically.

Notes:

- You cannot select schemas that belong to different JDBC connections.
- You can use Modify canvas to add or remove the selected schemas.



You must not select schemas with nested group types for the generation of DDL statements.
 If any of the selected schemas is deleted from the workspace, then the view of the Schema Canvas page changes because the deleted schema is removed from the Schema Canvas page.

Results

You have selected multiple schemas.

What to do next

You can perform any one of the following tasks:

- Generate DDL statements for the selected schemas. See Generating DDL statements on page 242.
- Generate the test data. See Generating test data for selected schemas on page 234.

Generating DDL statements

After you select non-JDBC schemas on the **Schema Canvas** page, you can generate the Data Definition Language (DDL) statements for all the selected schemas.

Before you begin

You must have selected non-JDBC schemas on the Schema Canvas page.

- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.

Result

The **Overview** page is displayed.

3. Click Author > Data Fabrication.

Result

The Data Fabrication page is displayed.

4. Click Schema Canvas.

Result

The Schema Canvas page is displayed.

- 5. Verify the selected schemas.
- 6. Click Generate DDL.

Result

A notification is displayed that the DDL statements for the selected schemas are successfully generated.

Results

You have generated the DDL statements of the selected schemas.

What to do next

You can view and download the generated DDL statements of the selected schemas on the **Jobs** page. See Status of generated test data on page 243.

Status of generated test data

You can view the status of all the test data generated jobs and Data Definition Language (DDL) statements generated jobs performed in your project, on the **Jobs** page.

You can view the status of test data generated jobs in the **Status** column on the **Jobs** page. When the test data generation of any schema initiates, the status of that job is shown as *Started*. As the test data generation progresses, the status of that job changes to *In Progress*. After the test data generation completes successfully, the status changes to *Complete*. If the generation of test data fails, you can view the status of that particular job as *Failed*.

Related information

Usage of test data generation job on page 243

Usage of test data generation job

The generation of test data or Data Definition Language (DDL) statements for single or multiple schemas in HCL® OneTest[™] Data is considered a job. You can view the list of all jobs on the **Jobs** page.

When the job to generate the test data or DDL statements is complete, you can download the following generated jobs files from the **Jobs** page:

- · Generated test data file
- Structured Query Language (SQL) file

You can use the job details to troubleshoot the failed jobs and to regenerate the successful jobs.

When you generate the DDL statements, each job includes one SQL file and each SQL file includes the DDL statements generated for all the selected schemas.

You can access the API history for each generation job of the test data or DDL statements. If you want to reuse any schema to generate the test data, then you can regenerate the test data.



Note: The Regenerate Job option is disabled for the Schema canvas jobs and DDL job.

You can find different methods of using the generated test data jobs.

Downloading jobs

When you want to test any application by using the generated test data or to reuse the data of any specific schema definition for some other project, you can download the test data from the job into your local file system. You can also download the Structured Query Language (SQL) file from the job that includes the generated Data Definition Language (DDL) statements of multiple non-JDBC schemas.

Before you begin

You must have completed the following tasks:

- Created a project.
- Generated the test data. See Generating test data for selected schemas on page 234.
- Generated the DDL statements. See Generating DDL statements on page 242.
- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.

Result

The **Overview** page is displayed.

3. Click Author > Data Fabrication.

Result

The Data Fabrication page is displayed.

4. Click Jobs.

Result

The **Jobs** page is displayed. You can view the list of all the jobs that include the generated test data or DDL statements.

Notes:

- If you want to view only the jobs related to referential integrity, then select Schema canvas jobs from the menu.
- If you want to view only the jobs related to DDL statements, then select DDL job from the menu.
- 5. Select a job for which you want to download the generated test data.

Notes:

- $\,\circ\,$ You can select multiple jobs at a time to download the test data.
- You can download the test data only for the jobs that are completed successfully.
- The download option is disabled for the jobs that are set to insert the generated test data into the database.
- The download option is disabled for multiple DDL jobs.
- 6. Click the **Download job(s)** button or \checkmark icon.

Results

You have downloaded any one of the following files:

• The generated test data in the compressed format in your local file system. When you download multiple jobs, then the compressed file of the jobs is organized by time.



Note: You can also download the generated test data file from the following location of the HCL® OneTest[™] Data pod:

/opt/hcl/hip-rest/
output/<accountId>/<userID>/<projectId>/<schemaId>/<genMapPath></projectId>/<schemaId>/<genMapPath></projectId>/<schemaId>/<genMapPath></projectId>/<schemaId>/<genMapPath></projectId>/<schemaId>/<genMapPath></projectId>/<schemaId>/<genMapPath></projectId>/<schemaId>/<genMapPath></projectId>/<schemaId>/<genMapPath></projectId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaId>/<schemaIdD</schemaId>/<schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD>/<schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD</schemaIdD

· An SQL file that includes the generated DDL statements of all the selected schemas.



Note: You can also download the DDL statements from the following location of the HCL® OneTest[™] Data pod:

/opt/data/hipfiles/<accountId>/<projectId>/yyyy:MM:dd-HH:mm:ss.sql

Regenerating test data

When you want to generate another set of test data by using an existing schema, then instead of defining a schema again, you can regenerate test data from the **Jobs** page.

Before you begin

- · You must have a project.
- · You must have generated test data.

About this task

On the **Jobs** page, you can view the list of all test data generated jobs. If you want to use the existing data model or schema to generate different values of test data, you must regenerate with an empty seed value. However, if the seed value is not empty, then the same test data is generated as it was generated earlier for that schema.



Note: You cannot regenerate the test data for the jobs that are generated for multiple schemas by using referential integrity and Data Definition Language (DDL) statements.

- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.

Result

The Overview page is displayed.

3. Click Author > Data Fabrication.

Result

The Data Fabrication page is displayed.

4. Click Jobs.

Result

You can view the list of data generated jobs.

- 5. Select a job for which you want to regenerate the test data.
- You can select multiple jobs at a time to regenerate the test data.
- 6. Click Regenerate data from the menu or click the Regenerate data icon 🕘.

Results

The test data for the required schema is regenerated and is listed on the **Jobs** page.

What to do next

You can download the regenerated test data. See, Downloading test data on page 243.

Configuring job settings

HCL® OneTest[™] Data periodically deletes all the generated test data and the jobs of test data generation with API history to clear the memory. However, if you want to change the default number of days to retain the generated test data jobs in memory, you must configure the job settings.

Before you begin

- You must have cluster-admin permissions.
- You must have the IP address of the computer where HCL OneTest[™] Server is installed.

About this task

As a default configuration, HCL® OneTest[™] Data retains the jobs with their generated test data and API history for five days after the jobs are completed. All the jobs that are created before five days are deleted. If you want to retain the jobs with their generated data for more number of days in HCL® OneTest[™] Data, then you must modify the value of the **data_rotation_time** property to the number of days you want to retain the jobs in the configmap file.



Note: If you modify the value of the **data_rotation_time** property to zero, then you can disable the deletion of generated test data jobs and API history.

- 1. Log in to the SSH console of HCL OneTest Server.
- 2. Run the following command to edit the configuration file:

kubectl edit configmap -n test-system {my-ots}-data-config -o yaml

Search for the data_rotation_time property in the configuration file, and then set the value to the number of days you want the jobs to retain in the server.



Note: The default value of data_rotation_time is 5.

For example, if you want to retain the jobs for 10 days, set the value of data_rotation_time property as 10.

4. Save your changes, and then exit from the configuration file.

5. Run the following command to delete and restart the *<onetest data>* pod:

kubectl delete pod {my-ots}-data-app-0

Results

You have successfully configured the setting to retain the jobs with generated test data and API history in HCL® OneTest[™] Data.

Jobs management

When you run a job to generate the test data, you can view the job details on the **Jobs** page. The **Jobs** page helps you to view and to manage the list of all the jobs that you execute.

You can perform a quick search for the test data generated jobs based on the name of the schema or the date range by selecting the *From* and *To* dates. If the *To* field is blank, you can view the results till the most recent date. After you perform the search, if you want to continue to search for any schema or specific date, you must clear the **Search** field by using the **Clear Filter** button.

You can delete and cancel the generated test data jobs.

Deleting a test data generated job

When any of the generated test data is of no further usage, you can delete that specific test data from your project.

Before you begin

- You must have a project.
- You must have generated test data.

About this task

On the **Jobs** page, you can view the list of all the projects for which you have generated the test data. You can remove the reference of any specific test data.

- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.

Result

The **Overview** page is displayed.

3. Click Author > Data Fabrication.

Result

The Data Fabrication page is displayed.

4. Click Jobs.

Result

You can view the list of data generated jobs.

5. Select a job for which you want to delete the test data.

You can select multiple jobs at a time to delete.

6. Click **Delete Job** from the menu or click the **Delete** icon III.

Results

The selected test data is deleted from your project.

Canceling a test data generation job


After initiating a test data generation job, if you want to modify the schema or terminate the job before the job completes, then you can cancel the running test data generation job.

Before you begin

You must have a test data generation job in the In Progress status.

About this task

You can cancel only one test data generation job at a time. You can view the details of API endpoints of the canceled job on the **API History** page. Later, if you want to reuse the same schema to generate the test data, you must select **Regenerate Job** to regenerate the test data. However, you cannot download the test data of the canceled job.



- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.

Result

The **Overview** page is displayed.

3. Click Author > Data Fabrication.

Result

The Data Fabrication page is displayed.

- 4. Go to the Jobs page and select the test data generation job that you want to cancel.
- 5. Click **Cancel Job** from the menu of the selected job.

A notification is displayed that the selected job is canceled.

Results

You successfully canceled the running job. The canceled job appears on the Jobs page with the status as Canceled.

What to do next

You can modify the schema by using the schema designer and generate the test data.

Chapter 6. Test Execution Specialist Guide

This guide describes tasks that you must complete before you can configure and run tests in HCL OneTest[™] Server. You can find information about configuring runs for the different test types that are supported. You can also find information about other tasks that you can perform on the Resource Monitoring Service, Virtualization, and Integrations with third-party applications. This guide is intended for testers or test execution specialists.

System modeling

In this topic, you can find information about using the system model feature. You can also find the tasks that you can perform to create a system model. You must configure a repository to save the system model that you created for the application under test.

Introduction to system model

A system model is a logical presentation of the components contained in a system under test and the relationships between components. You can create a system model when you want to visualize the different components and their relationships as a diagrammatic representation.

You can create only one system model within a team space on HCL OneTest[™] Server. A team space repository is required to contain the system model that you create. Before you can create a system model, you must add a team space repository. The system model that is created or edited is stored in the team space repository. All projects within a team space share the same system model. All members of a team space can create, edit, and view the system model.

After you log in to HCL OneTest[™] Server, you can go to the **System Model** page to create a system model for your team space. Alternatively, you can go to any of the projects in your team space and create a system model from the **System Model** page within a project. The system model is accessible from all the projects of your team space repository.

Components in a system model

Components are the basic building blocks which are used to represent a piece of software in an application.

You can model a system by using components. You can create components that represent the type of asset or resource used by the system or application under test and can be of the following types:

Component type	Description
Database	The component type represents the database resource. You can select this component type when you want to represent a database asset or resource in the system model.
Service	The component type represents the virtual service resource. You can select this component type in the system model to represent a virtual service in the team space repository or associate a virtual service resource that is in the project repository.

Component type	Description	
UI	The component type represents the User Interface (UI) resource. You can select this component	
	type when you want to represent the User Interface resource in the system model.	

You can create multiple components to depict the different resources in the system or application under test. You can also associate virtual service resources with the components. The components in the system model can then be associated with the virtual services stored in the repositories that are configured for each of the projects.

You can create the following types of relationships between the components:

- Components can be related as *child* components to *parent* components.
- Components can be related as *dependent* components. The dependency is displayed by a line-arrow with the arrow-head pointing to the dependent component. For example, if *Component A* depends on *Component B*, then the relationship is displayed with a line-arrow from *Component A* to *Component B* and the arrow points to *Component B*. If Component B is also dependent on *Component A*, then the relationship is displayed with a line-arrow from *Component A*.

Using the system model UI

The following table lists the icons used in a system model and the icons that are displayed on the **System Model** page:

Icon	Description
	Represents a system model.
1.1.1	Represents Suites and Tests in a repository.
	Represents a database resource. The component name is prefixed with this icon when you se- lect the component type as database.
Ø	Represents a service resource. The component name is prefixed with this icon when you select the component type as service.
Þ	Represents a User Interface (UI) resource. The component name is prefixed with this icon when you select the component type as User Interface.
\oplus	Used to add components, child components, and dependent components.
Q	Used to search for components in the system model.
ቆ	Represents the virtual services.
	Used to publish the system model to the team space repository.
	Represents the dependency between the components.

lcon	Description
	Represents the inherited dependencies.

You can perform the following operations when you view the model displayed on the System Model page:

Operation	Action
Pan the view of the model	 Click on the area of the model that you want to pan and move the area keeping the left mouse button pressed. Release the left mouse button to stay on the view that you panned.
Zoom-in the view of the model	 Click the Zoom-in icon Q. The view is enlarged or zoomed-in. Note: You can repeatedly click the Zoom- in icon to further enlarge the view.
Zoom-out the view of the model	1. Click the Zoom-out icon Q. The view is diminished or zoomed-out. Note: You can repeatedly click the Zoom- out icon to further diminish the view.
Reset the view	 Click the Menu icon on the System Model page. Select Reset Zoom. The view is reset to the default view without any zoom applied. If the view was zoomed-in or zoomed-out, the view is reset to 100% of the size.
Position the model view	 Click the Menu icon on the System Model page. Select from the following options:

Operation	Action
	 Center: Select this option to align the
	view of the model to the center of the
	page.
	 Fit to View: Select this option to fit the
	view of the model in the window on the
	System Model page.

Tasks in system modeling

When you want to model the system under test for the first time after you install the server software and you are a licensed user in the team space, you must first add the team space repository. See Adding a repository to a team space on page 253.

After a repository is configured as the team space repository, you can work with the system model. See Tasks for working with a system model on page 252.

When you want to change, update or delete the repository, you can work with the team space repository. See Tasks for working with the team space repository on page 253.

Task flows for working with a system model

You can find information about the tasks that you can perform when you want to create a system model, create components, associate the components, create linkages among the components, and then publish the system model to the team space repository. Also, you can find information about the tasks that you must perform when you want to modify an existing system model.

Tasks for working with a system model

You can find the tasks when you want to create a system model for the application under test in your team space.

Tasks	More information
Add a repository to the team space.	Adding a repository to a team space on page 253
Create a system model.	Creating a system model on page 256
Create components in a system mod- el.	Creating components on page 257
Create child components to existing components in a system model.	Creating child components on page 258
Define the relationship between the components in a system model.	Creating linkages between components on page 260

Tasks	More information
Delete the relationship between the components in a system model.	Deleting linkages between components on page 262
Modify components in a system model.	Modifying components on page 264
Delete components in a system mod- el.	Deleting components on page 265
Associate resources with compo- nents in a system model.	Associating resources with components on page 267
View resources associated with com- ponents in a system model.	Viewing resources associated with components on page 269
Remove resources that are associ- ated with components in a system model.	Removing resources associated with components on page 273
Publish changes made to the system model.	Publishing changes to the system model on page 266
Publish changes of associating re- sources in a project with compo- nents in the system model.	Publishing changes of associating resources with components on page 274
View system model.	Viewing the system model on page 275
Delete system model.	Deleting a system model on page 275

Tasks for working with the team space repository

You can find the tasks that you can perform when you want to work with the team space repository.

Tasks	More information
Add a repository to the team space.	Adding a repository to a team space on page 253
Delete a team space repository.	Deleting a repository that is added to a team space on page 276

Adding a repository to a team space

You must add a repository to the team space when you want to create, modify, or store a system model.

Before you begin

You must have completed the following tasks:

- Ensured that you are assigned a role as a *Team Space Owner* or an *Architect* in the team space. See Managing members and their roles in a team space on page 720.
- Been provided valid credentials to access the Git repository that you want to add.

About this task

As a *Team Space Owner* or an *Architect*, you can add a repository to the team space. You can add a repository to the team space in any of the following methods:

- Add an existing repository that can contain test assets, which are created in the desktop products.
- Add a bare repository.

Attention: The repository that you want to add must not contain any projects or .project files under the root directory.

When you add a repository, the Git repository is cloned to the team space. While adding a repository, you must provide the necessary authentication credentials that are set for the Git repository. For example, if the authentication type is SSH, then you must provide the Git URL, a deploy key, and a passphrase.

Important: You can add only one repository to the team space. After you add a repository to the team space, the option to add another repository is not available. You must delete an existing repository before you can add a different repository.

- 1. Log in to HCL OneTest[™] Server.
- 2. Open the team space to which you want a team space repository.

The Active projects page is displayed.

3. Click the Settings icon in from the left navigation pane, and then select Manage team space.

The **Details** page is displayed.

4. Click **Repository** on the left navigation pane.

The Repository page is displayed.

5. Click Add repository.

The Add repository dialog is displayed.

6. Enter the URL of the Git repository, which you want to add to the team space, in the Git Repository field.

The required fields are displayed based on the type of Git URL that you entered.

7. Enter the required credentials based on any of the following authentication methods configured in the repository.

To gain access to the repository, you must use any one of the authentication methods:

Authentication method	Credentials required
SSH	∘ Deploy key ∘ Passphrase
HTTPS	∘ User name ∘ Password
НТТР	∘ User name ∘ Password

Notes:

 You must have defined the authentication type and set the authentication credentials in the Git repository.

 If you use SSH to connect to your remote repository and HCL OneTest[™] Server displays an Auth Fail exception while using the deliver changes option, you can resolve this exception error by regenerating your SSH keys by using the -m PEM option.

8. Click Add.

The Git repository is added to the team space on HCL OneTest[™] Server.



Note: Depending on the size of the repository you are cloning, it can take a few to several minutes to clone the repository.

What to do next

You can perform the following actions on the repository that you added:

- Update the authentication credentials if they are changed in the Git repository configuration. See Updating the authentication credentials of the repository on page 743.
- Refresh a repository to fetch and synchronize changes from the remote repository. See Refreshing repositories manually on page 744.
- Configure a webhook to notify the server if there is a push event in the remote repository. See Creating webhooks on page 746.
- Add a system model to the repository. See Creating a system model on page 256.
- Delete a repository that is added to the team space, if it is no longer required. See .

Related information

Managing repositories on page 739

Creating a system model

Before you can create components in a system model, you must create an empty system model and publish the system model to the team space repository.

Before you begin

You must have completed the following tasks:

- Ensured that you are assigned a role as an *Architect* in the team space, a *Project Owner* or a *Tester* in the project. See Managing members and their roles in a team space on page 720 or Managing access to server projects on page 734.
- Added a repository to the team space. See Adding a repository to a team space on page 253.
- 1. Log in to HCL OneTest[™] Server.
- 2. Open the team space to which a team space repository is added.

The Active projects page is displayed.

- 3. Select an option to create a system model based on your role in the team space or in a project in the team space:
 - If you are a Team space owner or an Architect, go to Step 4 on page 256.
 - If you are not a *Team space owner* or an *Architect* but a project *Owner* or *Tester*, go to Step 5 on page 256.
- 4. Perform the following steps, if you are a Team space owner or an Architect:
 - a. Click System Model on the left navigation pane.

The **System Model** page is displayed.

b. Click the Add system model icon 🕀.

An empty system model is created.

- c. Go to Step 6 on page 257.
- 5. Perform the following steps, if you are not a *Team space owner* or an *Architect* but a *Project owner*:
 - a. Open your project that is displayed under My projects on the Active projects page.

The **Overview** page is displayed.

b. Click System Model on the left navigation pane.

The System Model page is displayed.

c. Click the Add system model icon 🕀.

An empty system model is created.

- d. Go to Step 6 on page 257.
- 6. Click the See unpublished commits icon , and then select the Publish changes option.

Note: If you do not want to commit the changes that you made to the system model, you can select the **Discard changes** option.

7. Enter a commit message in the Description of change field, and then click Publish.

The empty system model is committed and published to the team space repository. When the system model is published to the team space repository, other members of the team space can work with the same system model from any of their projects in the team space.

Results

You have created an empty system model and published it to the team space repository.

What to do next

You can perform any of the following tasks:

- Create components in the system model. See Creating components on page 257.
- Create child components for the components that you added to the system model. See Creating child components on page 258.

Creating components

The first step in building a system model is to create components. The components serve as the building blocks for the system model.

Before you begin

You must have completed the following tasks:

- Created and published the system model. See Creating a system model on page 256.
- 1. Log in to HCL OneTest[™] Server.
- 2. Open the team space to which a team space repository is added.

The Active projects page is displayed.

- 3. Click System Model on the left navigation pane.
 - The System Model page is displayed.
- 4. Perform the following steps to add a component to the system model:

a. Click the Add component icon \oplus in the Components row on the right pane.

The Add a component dialog is displayed.

- b. Enter a name for the component in the Name field.
- c. Select the type of component that you want to add from the following options displayed in the **Type** field.
 - Service
 Database
 UI
- d. Click Add.

The component is displayed as a circular block on the system model pane with the icon and name of the component below the block. The added component is also displayed under the **Components** list in the right pane.

You create components of other types or the same type in the system model following the preceding steps.

Results

You have created components in the system model.

What to do next

You can perform any of the following tasks:

- Publish the changes that you made to the system model. See Publishing changes to the system model on page 266.
- Create child components for the components that you added to the system model. See Creating child components on page 258.
- Create linkages between components in the system model. See Creating linkages between components on page 260.

Creating child components

You can create components as children of existing components in the system model.

Before you begin

You must have completed the following tasks:

- Created and published the system model. See Creating a system model on page 256.
- Created components in the system model. See Creating components on page 257.

About this task

You can create multiple components in your system model and multiple child components under any component in the system model. After you create a child for a component, the child is represented as a circular block within the circular component block in the system model.

- 1. Log in to HCL OneTest[™] Server.
- 2. Open the team space to which a team space repository is added.

The Active projects page is displayed.

3. Click System Model on the left navigation pane.

The **System Model** page is displayed with the existing components.

- 4. Create child components in any of the following methods:
 - To create child components from the left pane on the System Model page, go to Step 5 on page 259.
 - To create child components from the right pane on the System Model page, go to Step 6 on page 259.
- 5. Perform the following steps to create child components from the left pane:
 - a. Click the component under which you want to create child components in the left pane.

The details of the component are displayed in the right pane.

b. Click the Add child icon \bigoplus in the Children row on the right pane.

The Add a child to... dialog is displayed.

- c. Enter a name for the component in the Name field.
- d. Select the type of component that you want to add from the following options displayed in the **Type** field.
 - 🔯 Service
 - 🗐 Database
 - 🎴 UI
- e. Click Add.

The child component is displayed as a circular block within the circular block of the parent component on the system model pane. The added child component is also displayed under the **Children** list under the component in the right pane.

You create child components of other types or the same type for the same or other components in the system model following the preceding steps.

6. Perform the following steps to create child components from the right pane of the stem model page:

- a. Click the component name listed under the Components in the right pane.
- b. Click the Add child icon 🕀 in the Children row on the right pane.

The Add a child to ... dialog is displayed.

- c. Enter a name for the component in the Name field.
- d. Select the type of component that you want to add from the following options displayed in the **Type** field.
 - Image: Service
 Image: Database
 - 🎦 UI
- e. Click Add.

The child component is displayed as a circular block within the circular block of the parent component on the system model pane. The added child component is also displayed under the **Children** list under the component in the right pane.

You create child components of other types or the same type for the same or other components in the system model following the preceding steps.

Results

A component is created and it is associated as a child with the selected component and the name of the child is displayed under the **Children** section in the right pane.

What to do next

You can perform any of the following tasks:

- Publish the changes that you made to the system model. See Publishing changes to the system model on page 266.
- Create linkages between components in the system model. See Creating linkages between components on page 260.

Creating linkages between components

You can create linkages between components that display the relationship between them. The linkages can be between components or between child components of the same or different parent components.

Before you begin

You must have completed the following tasks:

- Created and published the system model. See Creating a system model on page 256.
- Created components in the system model. See Creating components on page 257.
- Created child components. See Creating child components on page 258.

About this task

You can create multiple components in your system model and multiple child components under any component in the system model. You can specify the dependency among the components.

- 1. Log in to HCL OneTest[™] Server.
- 2. Open the team space to which a team space repository is added.

The Active projects page is displayed.

3. Click System Model on the left navigation pane.

The System Model page is displayed.

- 4. Perform the following steps to create a relationship between the components in the system model:
 - a. Click the component that you want.

The details of the component are displayed in the right pane.

b. Select from the following types of relationships that you want to create:

Option	Action	
Depends on	 Perform the following steps, if the component you selected is dependent on another component: i. Click the Add dependency icon in the row of the Depends on in the right pane. The Add dependency dialog is displayed. 	
	 ii. Select the component from the list of components displayed under Depends on. iii. Click Add. 	
	The components linked are listed under Depends on in the right pane. The linkage between the first to the second component you select is shown with an arrow that starts from the first and ends in the second component.	
Is a dependency of	Perform the following steps, if the component you selected has a depen- dency of another component:	

Option	Action
	i. Click the Add dependent icon \oplus in the row of the Is a dependency
	of in the right pane.
	The Add dependent dialog is displayed.
	ii. Select the component from the list of components displayed under
	Is a dependency of.
	iii. Click Add.
	The components linked are listed under Is a dependency of in the right
	pane. The linkage between the first to the second component you select is
	shown with an arrow that starts from the second and ends in the first com-
	ponent.

Results

You have created linkages between components in the system model.

What to do next

You can publish the changes that you made to the system model. See Publishing changes to the system model on page 266.

Deleting linkages between components

When you do not want to retain the linkages between components that you created in the system model, you can delete the linkages.

Before you begin

You must have completed the following tasks:

- Created and published the system model. See Creating a system model on page 256.
- Created components in the system model. See Creating components on page 257.
- Created child components. See Creating child components on page 258.
- Created linkages between components in the system model. See Creating linkages between components on page 260.
- 1. Log in to HCL OneTest[™] Server.
- 2. Open the team space to which a team space repository is added.

The Active projects page is displayed.

3. Click System Model on the left navigation pane.

The System Model page is displayed.

- 4. Perform the following steps to delete a relationship between the components in the system model:
 - a. Click the component that you want.

The details of the component are displayed in the right pane.

b. Select from the following types of relationships that you want to delete:

When	Action	
The component de- pends on another com- ponent.	 Perform the following steps, if the component you selected is dependent on another component: Select the component from the list of components displayed under the Depends on section in the right pane. Click the Delete selected icon in the right pane. The Delete relationship dialog is displayed with the details of the component and the dependent component. Click Delete. 	
The component has a dependency by another component.	 Perform the following steps, if the component you selected has a dependency of another component: Select the component from the list of components displayed under the Is a dependency of section in the right pane. Click the Delete selected icon in the right pane. The Delete relationship dialog is displayed with the details of the component and the component dependency. Click Delete. 	

Results

You have created linkages between components in the system model.

What to do next

You can publish the changes that you made to the system model. See Publishing changes to the system model on page 266.

Modifying components

At any point in time, after you create a component, you can modify and update the details of the components such as the component type, and the relationships with other components.

Before you begin

You must have completed the following tasks:

- Created and published the system model. See Creating a system model on page 256.
- Created components in the system model. See Creating components on page 257.
- Created child components. See Creating child components on page 258.
- 1. Log in to HCL OneTest[™] Server.
- 2. Open the team space to which a team space repository is added.

The Active projects page is displayed.

3. Click System Model on the left navigation pane.

The System Model page is displayed.

4. Click the component that you want to edit.

The component details are displayed in the right pane.

5. Perform the actions for the task to modify components as listed in the following table:

Task	Action	
Change the component type.	 Perform the following steps: a. Identify the component that you want to modify from the components listed under Components in the right pane. b. Click the component checkbox. 	
	The Edit selected icon 🖄 is enabled.	
	c. Click the Edit icon 🖉.	
	The Edit component dialog box is displayed.	
	d. Select the component type.	
	e. Click Modify	
	The type of the component is modified.	
Change the name of a component.	Perform the following steps:	

Task	Action	
	a. Identify the component that you want to modify from the com-	
	ponents listed under Components in the right pane.	
	b. Click the component checkbox.	
	The Edit selected icon 🖄 is enabled.	
	c. Click the Edit icon 🖄.	
	The Edit component dialog box is displayed.	
	d. Edit the component name in the Name field.	
	e. Click Modify .	
	The name of the component is modified.	
Change the parent of a compo-	Perform the following steps:	
nent.	a. Identify the component that you want to modify from the com-	
	ponents listed under Components in the right pane.	
	b. Click the component checkbox.	
	The Change parent icon 🕙 is enabled.	
	c. Click the Change parent icon 🥹.	
	The Change parent dialog box is displayed.	
	d. Select another parent for the selected components that are list-	
	ed under the Parent list.	
	e. Click Change .	
	The parent of the component is changed.	

Results

You have edited components and updated the details successfully.

What to do next

You can publish the changes that you made to the system model. See Publishing changes to the system model on page 266.

Deleting components

When you do not require a component, you can delete the component.

Before you begin

You must have completed the following tasks:

- Created and published the system model. See Creating a system model on page 256.
- Created components in the system model. See Creating components on page 257.
- 1. Log in to HCL OneTest[™] Server.
- 2. Open the team space to which a team space repository is added.

The Active projects page is displayed.

3. Click System Model on the left navigation pane.

The System Model page is displayed.

4. Click the component that you want to delete.

The component details are displayed in the right pane.

5. Click the **Delete component** icon 🔟 inline with the component name.

The Delete component dialog is displayed.

6. Click Delete.

Results

You have deleted a component from the system model.

What to do next

You can perform any of the following tasks:

- Publish the changes that you made to the system model. See Publishing changes to the system model on page 266.
- Create components in the system model. See Creating components on page 257.

Publishing changes to the system model

When you create, delete, or modify components in a system model, the changes are saved locally and are not visible to the other project members or team space members. You must publish the system model changes to the team space repository to make your changes visible for all users of the team space.

Before you begin

You must have completed the following tasks:

- Created and published the system model. See Creating a system model on page 256.
- Performed actions to add or modify the system model that you want to publish.

- 1. Log in to HCL OneTest[™] Server.
- 2. Open the team space to which a team space repository is added.

The Active projects page is displayed.

3. Click System Model on the left navigation pane.

The System Model page is displayed.

- 4. View the uncommitted changes made to the system model that is displayed along with the **See unpublished commits** icon
- 5. Click the See unpublished commits icon , and then select the Publish changes option.

Note: If you do not want to commit the changes that you made to the system model, you can select the **Discard changes** option.

6. Enter a commit message in the Description of change field, and then click Publish.

Results

You have published the changes that you made in the system model to the team space repository. Other members of the team space can now view and use the system model.

Associating resources with components

After creating components in the system model, you can navigate to a project in the team space to associate the Suites, tests or virtual service resources in the project repositories with the components in the system model.

Before you begin

You must have completed the following tasks:

- Ensured that you are assigned a role as a *Project Owner* or *Tester* in the project. See Managing access to server projects on page 734.
- Created and published the system model. See Creating a system model on page 256.
- Created components in the system model. See Creating components on page 257.
- 1. Log in to HCL OneTest[™] Server.
- 2. Open the team space to which a team space repository is added.

The Active projects page is displayed.

3. Click Active projects > My projects > project_name to open the project that contains the test assets.

The **Overview** page of the project is displayed.

4. Click System Model on the left navigation pane.

The System Model page is displayed.

5. Click the component that you want to associate with the Suites, Tests, or virtual service resources.

The component details are displayed in the right pane.

- 6. Click the Associate tab, and then perform the following steps:
 - a. Click Add.
 - b. Select the type of resource that you want to associate with the component from the following options:
 - Suites and Tests
 - Virtual services

Note: You can select either of the options or both the options.

The Edit branch dialog is displayed.

- c. Select your action that depends on the existence of an Edit branch:
 - Select an existing *Edit* branch that you created previously from the list of branches listed in the **Select branch** field, and then click **Save**.
 - Click Create new branch, enter a name for the branch, and then click Save, if you want to create a new branch.

The **Associate Assets** dialog is displayed. The list of resources that are contained in the branch of the project repository are listed. The name of the component and the branch also are displayed.

The **Suites and Tests** option is selected and the assets are listed if you selected the **Suites and Tests** option.

The **Virtual services** option is selected and the virtual service resources are listed if you selected the **Virtual services** option.

If you selected both the types of resources, then assets and virtual services in the branch are listed.

- d. Identify the assets or virtual resources that you want to associate with the component in the system model by performing any of the following actions:
 - Search for the resource by entering the asset name in the **Search** field.
 - Find the assets by scrolling through the list of assets.
- e. Select the resources, and then click Add

The selected resources are associated with the component.

You can view the associated resources that are displayed in the **Associate** tab and in the **Overview** tab. The test assets are listed under the **Suites and Tests** section and the virtual service resources are listed under the **Virtual services** section.

If you want to associate other resources to the same component, you can add them by clicking the **Add association** icon (+) next to the resource type. You can then select the resource and add the resource to the selected component.

Results

You have associated Suites, tests, or virtual service resources with a component in the system model.

What to do next

You can perform any of the following tasks:

• Publish the changes made in the system model for associating resources with components. See Publishing changes to the system model on page 266.

Viewing resources associated with components

After you associate Suites and Tests or virtual services resources with components in the system model, you can view the associated resources from the **System Model** page. You can opt to start an instance of the associated resource or stop a running instance of the associated resource.

Before you begin

You must have completed the following tasks:

- Ensured that you are assigned a role as a *Project Owner* or *Tester* in the project. See Managing access to server projects on page 734.
- Created and published the system model. See Creating a system model on page 256.
- Created components in the system model. See Creating components on page 257.
- Associated resources in a project with components in the system model. See Associating resources with components on page 267.
- 1. Log in to HCL OneTest[™] Server.
- 2. Open the team space to which a team space repository is added.

The Active projects page is displayed.

3. Click Active projects > My projects > project_name to open the project that contains the test assets.

The **Overview** page of the project is displayed.

4. Click System Model on the left navigation pane.

The System Model page is displayed.

5. Click the component that you associated with the resources in the project repository.

The resources associated with the component are displayed under the resource type in the Associate tab.

6. Click the **Overview** tab, if it is not already displayed.

The resources that are associated with the component are displayed under the **Suites and Tests** or **Virtual Services** sections.

- 7. View and perform the actions for the resource type that you want from the following options:
 - For Suites and Tests resources, go to 8 on page 270.
 - For Virtual Services resources, go to 9 on page 271.
- 8. Identify the test resource that are listed under the **Suites and Tests** section, and perform the action that you want described in the following table:

Task	Description	Action
Collapse icon 💙	You can collapse the resource sections by clicking the Collapse icon V .	Click the icon to toggle between the collapsed and expand- ed display of the Suites and Tests section.
	Note: When the section is collapsed, you can view the number that is displayed of the re- sources that are associ- ated.	
Туре	You can view the type of the Suite or test.	Hover over the Suites and Tests icon under the Type col- umn to view the type of Suite or test.
Name	You can view the name of the associated Suite or test and the path in the repository.	There is no action to perform.
Status	You can view the details of the test runs.	Click each of the squares to view the details of the specific test run. For example, if the status of a test run is represented as shown in the image equals , then it indicates that the Suite or test has run only two times. After you click any colored square, the Results page is displayed.
Action	You can start the execution of the Suite or test from the Exe -	Click the Show in execution page icon C to view the Suite or test on the Execution page. The Suite or test is displayed on the Execution page.

Task	Description	Action
	cution page when you click the	
	Show in execution page icon	

9. Identify the virtual service resource that are listed under the **Virtual Services** section, and perform the action that you want described in the following table:

Field	Description	Action
Collapse icon V	You can collapse the resource sections by clicking the Collapse icon ♥. Note: When the section is collapsed, you can view the number that is displayed of the re- sources that are associ- ated.	Click the icon to toggle between the collapsed and expanded display of the Virtual Services section.
Show all icon	You can opt to view the virtual services that are associated with the component either on the Re- sources or Instances page. You can start an instance of the virtual service from the Re- sources page while you can stop a running instance from the In- stances page.	 Perform the following steps: a. Click the Show all icon ^C. b. Select any of the following actions: To start an instance of the virtual service: i. Select Show all in resources page to go to the Resources page. ii. Click the Execute icon ^O in the row of the virtual service. iii. Configure the settings for the run of the virtual service, if you want to change any of the settings, else click Execute.
		 The virtual service starts to run. To stop a running instance of the virtual service: Select Show all in instances page to go to the Instances page. Identify the instance that you want to stop and click the Stop icon in

Field	Description	Action
		the Actions column of the selected virtual service instance. iii. Click Ok in the Stop virtual service instance dialog that is displayed. The running virtual service instance is stopped.
Name	You can view the name of the as- sociated virtual service and the path in the repository.	There is no action to perform.
Instances	You can view the state of the run- ning instance of the virtual ser- vice resource. The state is dis- played as Running only if the in- stance is running.	There is no action to perform.
Action	You can go to the Resources page to view the virtual service resource when you click the Show resource icon C . You can start an instance of the virtual service from the Re- sources page.	Click the Show resource icon C to view the virtual service on the Resources page. The virtual service resource is displayed on the Resources page.
Expand icon >	You can expand the virtual ser- vice card only if the virtual ser- vice is a running instance. In the expanded card, you can view the details such as the En- vironment, the total number of requests received by the virtu- al service, and the relative time from when the virtual service was started. You can stop a running instance of the virtual service from the In-	 Perform the following steps: a. Expand the virtual service card for a running instance. You can view the details of the instance. b. Click the Show instance icon to go to the Instances page to view the running instance of the virtual service. The running instance of the virtual service is displayed on the Instances page.
	stances page.	

Results

You have either viewed the resources that are associated with a component from the System Model page.

Removing resources associated with components

When you do not want to retain the resource that you associated with a component, you can delete the resource in the system model.

Before you begin

You must have completed the following tasks:

- Ensured that you are assigned a role as a *Project Owner* or *Tester* in the project. See Managing access to server projects on page 734.
- Created and published the system model. See Creating a system model on page 256.
- Created components in the system model. See Creating components on page 257.
- Associated resources in a project with components in the system model. See Associating resources with components on page 267.
- 1. Log in to HCL OneTest[™] Server.
- 2. Open the team space to which a team space repository is added.

The Active projects page is displayed.

3. Click Active projects > My projects > project_name to open the project that contains the test assets.

The **Overview** page of the project is displayed.

4. Click System Model on the left navigation pane.

The System Model page is displayed.

5. Click the component that you associated with the resources in the project repository.

The resources associated with the component are displayed under the resource type in the Associate tab.

6. Select the resource that you want to remove from the component by clicking the checkbox of the resource.

You can select any or all resources for removal.

7. Click the **Delete selected** icon inline with the resource type.

The **Disassociate...** dialog is displayed for the type of resource that you selected. For example, the **Disassociate Cuties and Tests** dialog is displayed when you selected the test assets.

8. Click Delete.

For the changes to be reflected in the system model for all members of the project, you must publish the changes to the project repository.

9. Open the Changes page by clicking Author > Changes.

- 10. Verify the changes listed and then click **Publish changes**.
- 11. Enter a commit message in the **Description of change** field, and then click **Publish**.

Results

You have removed resources that were associated with components in the system model.

Publishing changes of associating resources with components

After you associate resources in a project with a component in the system model, you must publish the changes made to the branch in the project repository, if you want the associations to be visible to the other members in the project.

Before you begin

You must have completed the following tasks:

- Created and published the system model. See Creating a system model on page 256.
- Created components in the system model. See Creating components on page 257.
- Associated resources in a project with components in the system model. See Associating resources with components on page 267.
- 1. Log in to HCL OneTest[™] Server.
- 2. Open the team space to which a team space repository is added.

The Active projects page is displayed.

3. Click Active projects > My projects > project_name to open the project that contains the test assets.

The Overview page of the project is displayed.

4. Open the Changes page by clicking Author > Changes.

The **Changes** page is displayed. You can find the following information about the changes that you made to the system model when you associated resources with components:

- The *Edit* branch that you selected to contain the changes is displayed in the **Branch** field. You can select the *Edit* branch that you used before associating resources to components, if it is not already displayed as selected.
- The resources that you associated with components are listed under the Asset name column.
- $\circ\,$ The type of change is listed under the **Changes** column.
- The name of the member who made the change is displayed under the Last changed by column.
- The relative time when the change was made is displayed under the Last updated column.
- The number of changes that the *Edit* branch is ahead of from the project repository branch is indicated by the **commits ahead** option. You can view the details by clicking the **commits ahead** option. You can discard the pending commits by clicking the **Reset** option.
- The number of changes that the *Edit* branch is behind from the project repository branch is indicated by the **commits behind** option. The *Edit* branch can be behind the project repository branch if another

member has published or committed other changes in the system model to the same project repository branch. You can view the details by clicking the **commits behind** option. You can merge all the changes to your *Edit* branch, so that the *Edit* branch is on par with all the changes made in the project repository branch.

5. Click the **Publish changes** option.



Note: If you do now want to commit the changes you made to the system model, you can select the **Discard changes** option.

6. Enter a commit message in the **Description of change** field, and then click **Publish**.

Results

You have published the changes that you made in the system model to the repository in the project. Other members of the team space can now view and use the system model.

Viewing the system model

You can view an existing system model or you can create a system model if a system model does not exist on the **System Model** page.

Before you begin

You must be a licensed user.

- 1. Log in to HCL OneTest[™] Server.
- 2. Click System Model.

The System Model page is displayed.

- 3. Perform any of the following actions:
 - Add a team space repository, if no repository is configured as the team space repository.
 - Create a system model, if no model is created or exists.
 - View the system model that exists.
 - Modify the existing system model.

Results

You have viewed an existing system model from the System Model page.

Deleting a system model

When you want to remove an existing system model to create a new system model, you can delete the existing system model.

Before you begin

You must have ensured that a system model exists in the Initial Team Space.

- 1. Log in to HCL OneTest[™] Server.
- 2. Click System Model.

The System Model page is displayed.

- 3. Click the **Open action menu** icon **1** in the right-pane.
- 4. Click the Delete icon III.

The Delete System Model dialog is displayed.

5. Click Delete.

Results

You have deleted the system model from the team space repository.

What to do next

You must publish the changes to the team space repository. See Publishing changes to the system model on page 266.

Deleting a repository that is added to a team space

You can delete a repository that you added to the team space when you do not want to use a team space repository.

Before you begin

You must have completed the following tasks:

- Ensured that you are assigned a role as a *Team Space Owner* or an *Architect* in the team space. See Managing members and their roles in a team space on page 720.
- Added a repository to the team space. See Adding a repository to a team space on page 253.
- 1. Log in to HCL OneTest[™] Server.
- 2. Open the team space to which a team space repository is added.

The Active projects page is displayed.

3. Click the **Settings** icon from the left navigation pane, and then select **Manage team space**.

The **Details** page is displayed.

4. Click Repository on the left navigation pane.

The **Repository** page is displayed.

- 5. Click the Open action menu icon .
- 6. Click Delete in the action menu list.

The **Delete repository** dialog is displayed.

7. Select the I understand... checkbox, and then click Delete.

Results

You have deleted the ream space repository.

Restriction: When you delete the team space repository, the system model if created is also deleted, and you or other members of the team space cannot add a system model.

Prerequisites to running tests

Before you can run a test asset in a project on HCL OneTest[™] Server, you must read the information about the different tests assets. You can add a remote static agent, Docker host, or Kubernetes cluster to the project and then select it as an alternate location to run the test assets.

You can find the following information about the prerequisite tasks:

- Test run considerations for AFT Suites or Functional tests on page 277
- Test run considerations for API Suites or API tests on page 279
- Test run considerations for schedules on page 282
- Considerations for using Jaeger traces in reports on page 283
- Test run considerations for JMeter tests on page 284
- Test run considerations for JUnit tests on page 286
- Test run considerations for Postman tests on page 286
- Management of agents on page 288
 - Test run considerations for running tests on remote performance agents on page 289
- Management of Docker hosts on page 296
 - Test run considerations for running tests on remote Docker hosts on page 296
- Management of remote Kubernetes clusters on page 312
 - Considerations for using a remote Kubernetes cluster on page 313

Related information

Test run configurations on page 327

Test run considerations for AFT Suites or Functional tests

Before you configure an AFT Suite or a Functional test run, you must first read the considerations that you need to take into account.

When you want to run an AFT Suite or Functional test in a project on HCL OneTest[™] Server, you can check if the AFT Suite or Functional test meets any of the following conditions:

If	Then
The AFT Suite or Functional test uses the settings con- figured in an AFT XML file for a remote agent	You must ensure that you have configured the location element in the AFT XML to point to a remote agent. For more information about setting the location element, refer to Using an XML file to run multiple Web UI tests and compound tests simultaneously.
You want to run an AFT Suite or Functional test on a re- mote agent	 You must run the test on the remote agent before you commit the test asset to the remote repository. When you run the test on the remote agent, the following events occur: The agent is added as the location in the AFT XML file, on which the test is to be run. The agent is displayed as the agent on which the test is to be run, under the Host column within the Location tab in the Execute test asset dialog.
You commit the test asset to the remote repository with- out running the test on the remote agent	The agent is not displayed under the Host column within the Location tab in the Execute test asset dialog.

Before you configure the run for an AFT Suite or a Functional test, you must complete the following tasks, if they are applicable:

- Add the remote agents, on which the test is to be run, to the project on HCL OneTest[™] Server. See Adding a performance agent to a project on page 291.
- After you add the agent, you can select the agent configured in the AFT XML file as the location for the test run or select the remote agents that you add to the project, when you configure a run for an AFT Suite.

The remote agents are shown as the agents available for selection under the **Override** column within the **Location** tab in the **Execute test asset** dialog.

You can then select the remote agent as the location to run the AFT Suite or Functional test when you are configuring the test run. Alternatively, you can enter the argument -swaplocation <configured_agent_location>:<overriding_agent_location> in the **Program Arguments** field in the **Advanced Setting** dialog when you are configuring the test run.

For running an AFT Suite, see Configuring an AFT Suite run on page 333.

Related information Test run configurations on page 327

Test run considerations for API Suites or API tests

Before you configure an API Suite or API test run, you must first read the considerations that you need to take into account.

You can find the following information about API Suites:

- Important information about API Suites or tests on page 279
- Important information about report configuration in API Suites or tests on page 281

Important information about API Suites or tests

When you want to run an API Suite or test from a project on HCL OneTest[™] Server and the test asset in HCL OneTest[™] API meets any of the following conditions:

- The Suite or test refers to local stubs that use a transport other than HTTP or MQ.
- The Suite or test refers to local stubs that use the HTTP transport.
- The transport used in the tests or Suite is configured with the host name set to *localhost* for the HTTP/TCP proxy.
- The Suite or test has tests that use a transport and the transport requires third-party application Jar files for a successful run.

You must then refer to the following table for the next steps:

If	Then
The test asset refers to local stubs that use a transport other than HTTP or MQ.	 You must perform any of the following actions before you commit the test asset to the remote repository: Remove the reference to the local stub from the test asset. Publish the stubs to HCL® Quality Server. To publish and edit stubs, see Publishing stubs.
The tests refer to local stubs that use the HTTP transport.	You must perform the following actions before you com- mit the test asset to the remote repository:

If	Then
	 Create a test or test Suite that contains the stub and tests that run on the stub. Configure the physical HTTP transport with the following parameters in the Client tab in the Physical View: Set the Host name or IP address of the HTTP Proxy server in the Proxy Host field. Set 3128 as the proxy server port in the Proxy Port field. Set the reference to the stub for the tests in the test suite scenario from the Scenario Editor dia- log from the Test Factory view by selecting the <i>Live system</i> option in the Satisfied by column to run the stubs on the HTTP proxy registered with HCL OneTest[™] Server. Save the project.
The transport used in the Suite or tests is configured with the host name set to <i>localhost</i> for the HTTP/TCP proxy.	You must replace the host name with <i>fully-qualified-do-main-name</i> or <i>IPAddress</i> of the proxy host in the tests before you commit the test asset to the remote repository.
You plan to run the API Suite or test on the computer where HCL OneTest [™] Server is installed and the API Suite or test that use a transport from any of the follow- ing third-party applications: • Camel • CentraSite • CICS • Coherence • Database • IMS • Integra • JMS • SAP RFC • Software AG Universal Messaging • TIBCO EMS • TIBCO Rendezvous	 You must complete the following tasks: 1. Identify the location of the third-party application JAR files. You can use Library Manager to know the location where the third-party application JAR files are saved. 2. Copy the third-party application JAR files to the computer where HCL OneTest[™] Server is installed. See Copying third-party application Jars to Kubernetes on page 100.

lf	Then
TIBCO SmartSockets WebSphere Application Server Service Integra-	
tion Bus (SiBus)	
• WebLogic	
Software AG webMethods	
• WebSphere MQ	
You plan to run the API Suite or test on a remote Dock-	You must complete the following tasks:
er host and the API Suite or test contains tests that use	
a transport from any of the following third-party applica-	1. Identify the location of the third-party application
tions:	JAR files. You can use Library Manager to know
	the location where the third-party application ${\tt JAR}$
• Camel	files are saved.
CentraSite	2. Copy the third-party application ${\tt JAR}$ files to the
• CICS	computer where the remote Docker host is in-
Coherence	stalled.
Database	
• IMS	See Copying third-party application Jars to a remote
• Integra	Docker host on page 301.
• JMS	
• SAP RFC	
Software AG Universal Messaging	
TIBCO EMS	
TIBCO Rendezvous	
TIBCO SmartSockets	
WebSphere Application Server Service Integra-	
tion Bus (SiBus)	
• WebLogic	
Software AG webMethods	
WebSphere MQ	

Important information about report configuration in API Suites or tests

You must configure test Suites or tests in HCL OneTest[™] API to use a results database so that the details of the test results can be captured and displayed in the HCL OneTest[™] Server API results reports. See Configuring the project results database.

If your server projects use either a Microsoft SQL Server, MYSQL, or both as a project results database, you must copy the Microsoft SQL Server and MySQL database JAR files to the JDBC folder in the path /data/JDBC on HCL OneTest[™] Server. See Copying third-party application Jars to Kubernetes on page 100.

The database JAR files that you need are based on the version of Microsoft SQL Server or MQSQL that you use with HCL OneTest[™] API. See Adding Microsoft SQL Server and MySQL drivers.

To run an API Suite, see Configuring an API Suite or an API test run on page 343.

Related information

Scenario reference setting

Test run configurations on page 327

Test run considerations for schedules

Before you configure a Rate Schedule or VU Schedule run, you must first read the considerations that you need to take into account.

Important information about JMeter tests in schedules

When you want to run JMeter tests as part of the VU Schedule or Rate Schedule on HCL OneTest[™] Server, you must have completed the following tasks:

- Installed the HCL OneTest[™] Performance Agent on a computer.
- Installed the JMeter application on the computer where you have installed the HCL OneTest[™] Performance Agent.
- Set the environment variable **JMETER_HOME** that points to the JMeter installation directory.

Important information about Resource Monitoring sources in schedules

When you want to run schedules on HCL OneTest[™] Server, you must have completed the following tasks in HCL OneTest[™] Performance:

- Created a performance schedule of Rate or VU type.
- Added Resource Monitoring sources, or the labels of Resource Monitoring sources to a schedule. Refer to Adding resource monitoring sources to a performance schedule by using labels.

Before you configure a run of a Schedule, you must complete the following tasks in HCL OneTest™ Server:

- Add Resource Monitoring sources to your project in HCL OneTest[™] Server. See Monitoring an NGINX server on page 549.
- Enable HCL OneTest[™] Server as Resource Monitoring service only if you want to replace Resource Monitoring labels set in HCL OneTest[™] Performance with the labels that you created in HCL OneTest[™] Server. See Controlling resource monitoring sources in a schedule on page 581.
- Perform the following steps when you want to override the Resource Monitoring labels in the test asset with the Resource Monitoring labels that you create in HCL OneTest[™] Server:

1. Click the Resource Monitoring tab.

Note:

The **Resource Monitoring** tab displays only if you enabled the **Resource Monitoring from** Service option in HCL OneTest[™] Performance when you created the test asset.

2. Click , and press the ctrl + space bar keys, or enter the initial letter of a label to select a label in the list.

Note:

You can select or add labels only if you added the labels in the **Resource Monitoring Sources** page in HCL OneTest[™] Server.

For running a Rate Schedule or VU Schedule, see Configuring a run of a Rate Schedule or VU Schedule on page 428.

Related information

Test run configurations on page 327

Considerations for using Jaeger traces in reports

Before you can use Jaeger to report the test results in the supported tests, you must read the considerations that you must take into account.

When you want to enable Suites, Tests, or Schedules that are run from HCL OneTest[™] Server to use Jaeger traces for reporting the test results, you must have completed the following tasks:

- Installed Jaeger at the time of installation of the server software. See Prerequisites for installing the server software on Azure Kubernetes Service on page 46 or Prerequisites to install the server software on Ubuntu on page 37.
- Verified that Jeager is enabled and working.

After you install and verify that Jaeger is enabled, and when you want Jaeger to report the test results for the tests that you configure for a run, you must perform the following steps:

1. Click Advanced.

2. Enter -history jaeger in the Program Arguments field.

Related information Test run configurations on page 327

Test run considerations for JMeter tests

Before you can run JMeter tests on HCL OneTest[™] Server, you must read the considerations that you must take into account and complete the tasks indicated.

When you want to run JMeter tests that you create in JMeter, you must have completed the following tasks:

- You must ensure that the JMeter extension on HCL OneTest[™] Server is enabled at the time of installation of the server software or is running before you add the repository that contains JMeter tests to the server project. See Prerequisites for installing the server software on Azure Kubernetes Service on page 46 or Prerequisites to install the server software on Ubuntu on page 37.
- You must have committed the following JMeter assets or resources as a JMeter project to the remote repository:

Note: You must have created a project directory and added the associated tests or assets in sub directories, that might be required for the JMeter tests to run successfully.

- The jmeterRoot.jprj project file in the project directory.
- The JMeter tests in a sub directory with a name you provide within the project directory.
- Optionally, the Java Key Store that is required at test run time in the certs sub directory.
- Optionally, the JMeter properties files that are required at test run time in the properties sub directory.
- Optionally, the library jar files that are required at test run time in the lib sub directory.
- Optionally, the test dependencies that are required at test run time in the deps sub directory.

For example, the project directory can be *myproject* that contains the jmeterRoot.jprj project file. In the project directory, you can create the following sub directories:

- The mytests sub directory that contains the JMeter tests.
- \circ Optionally, the <code>certs</code> sub directory that contains the Java Key Store.

For example, the path to the key store can be specified in the system.properties file as follows:

javax.net.ssl.trustStore=\$(deploy.home)/certs/simpleStore.jks

Where *<simpleStore.jks>* is the Java Key Store and the *<deploy.home>* is the keyword to access the key store at the test run time.

• Optionally, the properties sub directory that contains properties files such as system.properties, jmeter.properties, reportGenerator.properties, or user.properties.

- Optionally, the lib sub directory that contains the lib and lib/ext content to be used at test run time.
- For example, the **amq client** and the **plugins** required to parse the **jmx** that contains **amqp** calls.
- Optionally, the deps sub directory that contains the test dependencies.

The resulting project directory can be as follows:

```
myproject (that contains the jmeterRoot.jprj)
myproject/mytests
myproject/certs
myproject/properties
myproject/lib
myproject/deps
```

You must ensure that you use a relative path when JMeter tests refer to other test assets. For example, if the JMeter test that is in the myproject/mytests folder refers to a mycsv.csv file that is in the myproject/ deps folder, then the mycsv.csv is referred as follows: .../deps/mycsv.csv in the JMeter test.
 You can create the JMeter project file named as jmeterRoot.jprj.

The project file is a java properties file. The JMeter project file is required so that HCL OneTest[™] Server can identify the asset as a JMeter project. You can specify additional information in the project file. You can specify the names of the sub directories created and through keywords you can specify the path in the properties files whether they are relative to the root directory or to the tests sub directory.

For example, if you have created the following sub directories in the project directory called *myproject* that contains the jmeterRoot.jprj project file:

```
o myproject/mytests
```

```
o myproject/properties
```

If the JMeter tests are contained in the following path: myproject/mytests/testplan/test1.jmx, and some dependencies that are also required to be deployed at test run time exists in the following path: myproject/mytests/testplan/localdir. You must specify these file paths in the project file as follows:

```
testDir.localtest.sub.dir=localdir
aSecondRootDir.sub.dir=dir2
athirdRootDir.sub.dir=dir3
```

Restriction: You cannot run the test assets on a remote Docker host.

Related reference

Troubleshooting issues on page 1136 Related information

Configuring a run of a JMeter test on page 408

Test run considerations for JUnit tests

Before you can run JUnit tests on HCL OneTest[™] Server, you must read the considerations that you must take into account and complete the tasks indicated.

When you want to run JUnit tests, you must have completed the following tasks:

- You must ensure that the JUnit extension on HCL OneTest[™] Server is enabled at the time of installation of the server software or is running before you add the repository that contains the JUnit tests to the server project.
 See Prerequisites for installing the server software on Azure Kubernetes Service on page 46 or Prerequisites to install the server software on Ubuntu on page 37.
- You must have created the JUnit tests that use JDK 8, as part of a Maven V3.6.3 project. The Maven project must contain the Maven Surefire plugin, which is required to run the JUnit tests contained in the Maven project. The Maven project as a pom.xml must be committed to the remote repository.



Note: If you create the JUnit tests on other versions of JDK, you must copy the JDK version to the userlibs pod under the data/junit-ext/jdks directory. See Copying third-party application Jars to Kubernetes on page 100.

Restriction: You cannot run the test assets on a remote Docker host.

Related reference Troubleshooting issues on page 1136 Related information Configuring a run of a JUnit test on page 414

Test run considerations for Postman tests

Before you can run Postman tests on HCL OneTest[™] Server, you must read the considerations that you must take into account and complete the tasks indicated.

When you want to run Postman tests that you create in Postman, you must have completed the following tasks:

 You must ensure that the Postman extension on HCL OneTest[™] Server is enabled at the time of installation of the server software or is running before you add the repository that contains Postman collections to the server project. See Prerequisites for installing the server software on Azure Kubernetes Service on page 46 or Prerequisites to install the server software on Ubuntu on page 37. **Restriction:** If you add the repository with Postman collections to a server project before you enable the Postman microservice, the Postman collections might not be displayed in the **Execution** page for you.

- You must have exported the following resources from Postman and saved the resources on your computer:
 - Collections and their associated variables and environments from Postman in which all collections are exported as a single file.



Note: You can export as many collections as you want.

For more information, refer to Exporting a collection from Postman and Exporting data dumps.

 Environments configured in Postman, if you are exporting only the environments as separate JSON files.

For more information, refer to Exporting environments from Postman.

- You must have committed the following Postman assets or resources to the remote repository:
 - Collections and their associated variables and environments that you exported. You can export all
 resources that are in your workspace in Postman. You can also export the collections along with the
 variables as a single file and the environments separately as another file.

For example, you can save the exported file as MyCollectionsVarEnv.json that contains the collections, variables, and environments or you can export only the collections and variables as MyCollectionsVar.json.

- Environments that you exported, if you are exporting only the environments as separate JSON files. For example, you can save the exported file as MyEnv.json.
- An empty text file with the .postman extension that is contained in the same directory as the other Postman resources, so that the contents in the directory are attributed as Postman resources. For example, you can create MyProject.postman.

Note: The .postman file enables HCL OneTest[™] Server to identify the test resources as Postman resources.

For example, if you have saved the Postman resources that you downloaded from Postman as follows:

• MyCollectionsVarEnv.json or MyCollectionsVar.json that contains the Postman collections.

• MyEnv. json that contains the environments associated with the Postman collection.

The project directory can be as follows:

/Project
/Project/MyProject.postman
/Project/MyCollectionsVarEnv.json

Alternatively, the directory can be as follows:

/Project
/Project/MyProject.postman
/Project/MyCollectionsVar.json
/Project/MyEnv.json

Restriction: You cannot run the test assets on a remote Docker host.

Related reference Troubleshooting issues on page 1136 Related information Configuring a run of a Postman test on page 421

Management of agents

You can find information about managing performance agents that you install on remote computers and then configure the remote agents to register with HCL OneTest[™] Server. After the agents are registered, you can add them to your projects and then select them as locations to run tests.

When you plan to run any of the tests from a project on HCL OneTest[™] Server on a remote performance agent, see Management of performance agents on page 288.

Management of performance agents

You can manage the performance agents that you want to use as locations to run tests from HCL OneTest[™] Server. When you install the agents by using your offline user token, the agents are registered with the team space in HCL OneTest[™] Server. You can view the registered agents before you add them to your projects. You can then select them as locations to run tests.

When you plan to run any of the tests on a remote performance agent from a project in HCL OneTest[™] Server, you must have completed the following tasks:

- Installed the performance agent of the same version as the version of HCL OneTest[™] Server. Refer to the HCL OneTest[™] Performance documentation for installing the performance agent at Installing HCL OneTest Performance agent.
- Configured the performance agent with your offline user token so that the performance agent can register with HCL OneTest[™] Server.

Note: When you configure the performance agent by using your offline user token, HCL OneTest™ Server considers you as the owner of the performance agent.

• Verified that you have write permissions to the majordomo.config file so that certain transactions can be written by HCL OneTest[™] Server to the majordomo.config file.



Note: You can verify if you have the *Read* and *Write* permissions by checking the properties of the majordomo.config file.

- Viewed the performance agents that are registered with HCL OneTest[™] Server. See Viewing performance agents that are registered with HCL OneTest Server on page 290.
- Added the remote performance agents that are registered with HCL OneTest[™] Server to your project on HCL OneTest[™] Server. See Adding a performance agent to a project on page 291.
- After you add the remote performance agents to your project, HCL OneTest[™] Server determines the
 capabilities that are provided by the remote performance agent and displays the details and capabilities of the
 performance agent on the Agents and Intercepts page. You can also define the capabilities that you want to
 add, and then view, edit, or delete the capabilities that you defined for the performance agents in your project.
 See Working with agent capabilities on page 294.

Test run considerations for running tests on remote performance agents

Before you configure a test to run on a remote performance agent from HCL OneTest[™] Server, you must read the considerations that you must take into account.

Supported tests

You can run the following tests that are supported to be run on a remote performance agent:

- AFT Suite
- Compound Tests that contains performance tests
- · Compound Tests that contains Web UI tests
- Compound Tests that contains traditional HTML tests
- Rate Schedule
- VU Schedule

Prerequisite tasks

Before you can run any of the supported tests on a remote performance agent from a project on HCL OneTest™ Server, you must have completed the following tasks:

- Installed the HCL OneTest[™] Performance agent on the remote computer. See Management of performance agents on page 288.
- Configured the agent with your offline user token so that the agent can connect to HCL OneTest[™] Server.
- Added the remote agents to your project on HCL OneTest[™] Server. See Adding a performance agent to a project on page 291.
- 1

Note: If you want to run an AFT Suite (that contains Web UI tests) on an agent, you must start the agent as a non-admin user so that certain browsers that are configured start correctly during the test run time.

Before you add the tests to the remote repository, you must have completed the following tasks:

- Associated the agents with the performance schedule in HCL OneTest[™] Performance.
- · Specified the host name of the remote workstation in the AFT XML file.

You can continue to configure a run for any of the following supported test types:

- Configuring an AFT Suite run on page 333
- Configuring a run of a Compound Test that contains performance tests or a Performance test on page 397
- Configuring a run of a Compound Test that contains Web UI tests or a Functional Web UI test on page 363
- Configuring a run of a Compound Test that contains HTML tests on page 354
- Configuring a run of a Rate Schedule or VU Schedule on page 428

Viewing performance agents that are registered with HCL OneTest[™] Server

After you install the remote performance agents and configure them with your offline user token, the performance agents register with HCL OneTest[™] Server and you can view the registered performance agents on the **Agents and Intercepts** page.

Before you begin

You must have completed the following tasks:

- Installed the performance agent of the same version as the version of HCL OneTest[™] Server.
- Configured the performance agent with your offline user token so that the performance agent can register with HCL OneTest[™] Server.

1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

2. Click Infrastructure > Agents and Intercepts in the navigation pane.

Note: When you configure the performance agent to connect to the server, you must specify the offline user token that you generated on HCL OneTest[™] Server. This token defines your ownership over the agent.

The Agents and Intercepts page is displayed.

You can view the Dockers, intercepts, Kubernetes clusters, or performance agents that are registered with HCL OneTest[™] Server.

- 3. You can view the agents that you own in any of the following ways:
 - \circ Search for the agent by entering the name of the agent in the Search field.

Note: You can enter either the full name or any text that is in the name. The search is enabled for case sensitive text that you can enter.

- \circ Sort the **Type** column to sort the items and display the agents in the rows at the top of the table.
- Sort the Agents column and identify the agents by their names or by their owner.

You can view the following details about the agents that are registered with HCL OneTest[™] Server:

- The projects to which the agent is added, are displayed in the Projects column.
- The status of the agent is displayed in the Status column.



Note: You can add agents that are in the Ready state to your project, and then use them as locations to run tests or virtual services.

Results

You have viewed the registered agents from the Agents and Intercepts page.

What to do next

You can perform any of the following tasks:

- You can add the performance agents that you own to your project. See Adding a performance agent to a project on page 291.
- You can add the API agents that you own to your project. See Adding a performance agent to a project on page 291.

Adding a performance agent to a project

If you have performance tests that distribute workload across different workstations or Accelerated Functional Testing (AFT) Suites that need to run on different platforms and browsers, you can add HCL OneTest[™] Performance Agents to your projects to run tests on remote workstations.

Before you begin

You must have completed the following tasks:

- Read and completed the tasks mentioned in Test run considerations for running tests on remote performance agents on page 289, if you want to use a remote agent as the location to run the test.
- Ensured that you are assigned a role as a *Member* or *Project Creator* in the team space. See Managing members and their roles in a team space on page 720.
- Ensured that you are assigned a role as a *Project Owner* or *Tester* in the project. See Managing access to server projects on page 734.
- Installed the agent by using your offline user token that makes you the owner of the agent or you are assigned the role of a *Team Space Owner*.

About this task

Only you can add or remove a performance agent that you own from the project. However, any member of your project with the permission to run the tests can initiate the run of test assets that are associated with the performance agent.

1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

2. Open your project, and then click Infrastructure > Agents and Intercepts.

The Agents and Intercepts page is displayed.

3. Click Add > Add agent.

The performance agents that you configured with your user token are displayed.



Note: You can add the performance agents that you own and that are in the *Ready* state. You can add any number of performance agents to your project.

4. Select the performance agents that you want to use in the project, and then click Add.

The performance agents that you added to the project are displayed.

- 5. Perform the following steps to view details and capabilities of the performance agents:
 - a. Expand the performance agent to view the details panel.

You can find the following details of the performance agent displayed:

Parameter	Description
Version	The version of the installed performance agent.
Address	The IP address of the computer on which the performance agent is in- stalled.
License type	The license type that is enabled for you to use the performance agent.

Parameter	Description
Load generation service	The status of the performance agent whether it can be used for load gener- ation service.
Last contact	The time of the last contact with the performance agent by HCL OneTest [™] Server.

b. Expand the capabilities panel to view the system and application capabilities.

You can find the following capabilities of the performance agent displayed:

Capabilities		Description
		The architecture of the CPU processor of the computer on which the performance agent is installed.
	MAC Address	The MAC address of the computer on which the perfor- mance agent is installed.
	Operating system	The operating system of the computer on which the per- formance agent is installed.
	RAM	The memory that is allotted to RAM in the computer on which the performance agent is installed.
Application capabil- ities	Browser	The browsers along with their version that are installed on the computer on which the agent is installed.
User Defined capa- bilities	User Defined	The capabilities that you add for a performance agent. You can also tag a performance agent so that you can identify the performance agent to select as a location.

c. Check for the status of the performance agent from the Status column.



Note: You can add performance agents that are in any state to the project.

Results

You have added remote performance agents to your project and viewed the performance agent capabilities that is displayed for each agent that you own.

What to do next

You can perform any of the following tasks:

- Run the tests on the performance agent that is added to the project from the **Execution** page. See Test run configurations on page 327.
- Define the capabilities that you want to add, and then view, edit, or delete the capabilities that you defined for the performance agents in your project. See Working with agent capabilities on page 294.

Working with agent capabilities

When you installed static agents V10.1.2 or later, and added them to your project, you can view capabilities of the agents from the **Infrastructure** page. When you installed static agents V10.2.0 or later, you can add, view, edit, or delete properties and capabilities of agents from the **User Defined** panel of that agent.

Before you begin

You must have completed the following tasks:

- Been assigned a *Member* or *Project Creator* role in a team space.
- Been assigned the Owner or Tester role in the project to which you want to add the agent.
- Owned at least one agent that is not added to the project.
- Installed the agent. See Test run considerations for running tests on remote performance agents on page 289.
- Added agents to your project. See Adding a performance agent to a project on page 291.
- 1. Log in to HCL OneTest[™] Server and open the team space.
- 2. Open your project, and then click **Manage > Infrastructure**.

The agents that you added to your project are displayed on the **Infrastructure** page.

3. Expand the agent.

The Details and Capabilities tabs are displayed.

- 4. Click Capabilities to view the capabilities of the agent.
- 5. Click User Defined.

The User Defined Capabilities dialog is displayed.

6. Complete the steps for the task that you want to perform as listed in the following table:

Task	Action
Adding capabilities	 Perform the following actions: a. Click Add new. b. Enter the name of the capability in the Capability Name field. c. Perform any of the following actions in the User Defined Category field: Select an existing category from the list. Enter a name of the category for the capability, if the category does not exist.
	Note: You can also click Add new to add a category.
	The category for the capability is either selected or created and the fields for the property name and value are displayed.

Task	Action	
	Note: The property for a capability is a <i>name-value</i> pair.	
	d. Enter a name for the property in the Property Name field and its correspon ing value in the Property Value field for the capability.	
	Note: You can add multiple properties for the same capability under the same category or under different categories by clicking Add new property , and then by entering the name and value for the property.	
	e. Click Save . The capabilities that you added are displayed.	
Viewing capabilities that you added	The User Defined Capabilities panel displays the capabilities that you added to the agent.	
Editing capabilities that you added	Perform the following actions: a. Click the Edit icon 🖍 in the row of the capability that you want to edit.	
	The user-defined capability is enabled for editing. You can edit the name of the capability, or the property name or property value.	
	b. Edit any of the items that you want for the user-defined capability. c. Click Update .	
	The updated capability of the agent is displayed.	
Deleting capabilities that you added	 a. Click the Delete icon in the row of the capability that you want to delete. b. Click Delete. The capability that you selected is deleted along with all the properties that you added for the capability. 	
Deleting a property de- fined for a capability	a. Click the Edit icon in the row of the capability that you want to edit and remove a defined property.	
	The user-defined capability is enabled for editing. b. Select and delete the contents in the Property Name field and its corre- sponding Property Value field. c. Click Update . The property is removed for the capability.	

Results

You have added, viewed, edited, or deleted a property or the user-defined capability of an agent.

What to do next

You can run the tests on the agent from the **Execution** page. See Test run configurations on page 327.

Management of Docker hosts

You can find information about the tasks that you can perform on remote Docker hosts. After you set up a remote Docker host, you can register the Docker host with HCL OneTest[™] Server. You must then add the registered remote Docker host to your project before you can run tests on the remote Docker host location.

You can find the following information about managing Dockers:

- Test run considerations for running tests on remote Docker hosts on page 296
- Setting up a remote Docker host computer on page 298
- Setting up a secure remote Docker host computer on page 300
- Copying third-party application Jars to a remote Docker host on page 301
- Registering a remote Docker host on page 303
- Viewing remote Docker hosts that are registered with HCL OneTest Server on page 305
- Adding a remote Docker host to the project for running tests on page 306
- Editing configurations of a remote Docker host on page 307
- Removing a remote Docker host from a project on page 310
- Unregistering a remote Docker host from HCL OneTest Server on page 311

Test run considerations for running tests on remote Docker hosts

Before you can configure a test to run on a remote Docker host, you must read the considerations that you must take into account.

You can run all the tests that are supported on HCL OneTest[™] Server on remote Docker hosts.

Important: You can run virtual services only in the Default Cluster location of HCL OneTest[™] Server. You cannot run virtual services on a remote Docker host.

When you plan to run any of the tests on a remote Docker host from a project on HCL OneTest[™] Server, you must complete the following tasks:

	Tasks	More information
1.1	Set up non-secure remote Docker hosts.	Setting up a remote Docker host computer on page 298
1.2	Set up secure remote Docker hosts.	Setting up a secure remote Docker host computer on page 300

	Tasks	More information
2	Register the remote Docker host on HCL OneTest™ Server.	Registering a remote Docker host on page 303
3	View the registered Docker hosts.	Viewing remote Docker hosts that are registered with HCL OneTest Server on page 305
4	Add a remote Docker host to the HCL OneTest [™] Serv- er project.	Adding a remote Docker host to the project for run- ning tests on page 306
5	 Configure a run for your test that you want to run on the remote Docker host by performing the following actions: 1. Go to Test run configurations on page 327. 2. Check for the prerequisite tasks that you must perform before you configure a test run for the test. 3. Select the task for the test that you want to configure for a run, and then follow the steps to run the test. 	 Test run configurations on page 327 Prerequisites to running tests on page 277 Test run configurations on page 327

If you plan to run API Suites that use a transport and the transport requires third-party application Jar files for a successful run on a remote Docker host, then you must perform the following task:

• You must copy the third-party application Jar files to the third-party application folder on the computer where the remote Docker host is installed. See Copying third-party application Jars to a remote Docker host on page 301.

After you set up and register the remote Docker host with HCL OneTest[™] Server, you can add the remote Docker hosts to your project on HCL OneTest[™] Server. See Adding a remote Docker host to the project for running tests on page 306.

You can find information about the tasks that you can perform when you use remote Docker hosts that are set up and registered with HCL OneTest[™] Server.

- When you configure a test run and in the step in which you select the remote Docker, if you encounter any of the following conditions because these were changed on the remote Docker host:
 - $\circ\,$ The host name or port of the remote Docker is not displayed correctly.
 - \circ You want to change the mode of authentication with the remote Docker host.

You must edit the configuration settings for the remote Docker host. See Editing configurations of a remote Docker host on page 307.

- When you want to delete a remote Docker host from your HCL OneTest[™] Server project, see Removing a remote Docker host from a project on page 310.
- When you want to remove or unregister a remote Docker host from HCL OneTest[™] Server, see Unregistering a remote Docker host from HCL OneTest Server on page 311.

Related information

Test run configurations on page 327 Management of Docker hosts on page 296

Setting up a remote Docker host computer

You must set up a computer to host the remote Docker host. You can set up the remote host with a non-secure mode of connection with HCL OneTest[™] Server.

Before you begin

You must have identified a remote computer or VM that has a minimum of 16 GB RAM. You must have installed Ubuntu V18.04 or later, on the remote computer.

You must have installed Docker Enterprise Edition for a non-secure mode of connection with HCL OneTest[™] Server on the remote Docker host computer. Refer to Get Docker Engine.

You must have the entitlement key that is required for you to connect to the Harbor repository to be able to pull in the software image to the remote Docker host.

About this task

You must set up a remote computer or a Virtual Machine (VM) on which you want to set up the remote Docker host. You must be a system administrator or get the remote Docker host set up by a system administrator. You must ensure that the system administrator completes the following actions:

- Enables SSH.
- Creates user credentials for you with root permissions.
- Provides the name of the Docker container.
- Provides the IP address of the remote Docker host computer.
- 1. As a system administrator of the remote system, specify a port to access the Docker daemon in the docker.service file located in the directory /lib/systemd/system. You must add the configured port at the line in the file:

ExecStart=/usr/bin/dockerd -H fd:// -H tcp://0.0.0.0:PORT

For example, if the port configured is 4342, then the line must read as:

ExecStart=/usr/bin/dockerd -H fd:// -H tcp://0.0.0.0:4342

2. Restart the Docker service by using the following commands:

\$ sudo systemctl daemon-reload

\$ sudo systemctl restart docker

- 3. Perform the following steps as a user with root permissions or ask the system administrator to complete the following steps:
 - a. Open a terminal and connect to the remote Docker host by using an SSH tool by running the following command:

ssh root@<IP_address_of_remote_host>

b. Log in to HCL Software's Harbor container registry by running the following command:

sudo docker login hclcr.io -u <username> -p <password>

<u>></u> N

Note: You must provide the following username and password in the command to log in to the registry:

- Username as email address registered with HCL
- Password as Harbor CLI secret
- c. Run the following commands to pull the product images from the registry on to the remote Docker host computer:

Note: You must pull in the images with the version which is the same as the version of HCL OneTest[™] Server that you use to run the tests.

- sudo docker pull cp.hclcr.io/ot/hcl-onetest/studio<image_identifier>
- sudo docker pull hclcr.io/ot/hcl-onetest/virtualization<image_identifier>

Results

You have set up the remote Docker host computer that can be accessed in a non-secure mode.

What to do next

You can set up a secure remote Docker host computer optionally, that enables a secure connection with HCL OneTest[™] Server. See Setting up a secure remote Docker host computer on page 300.

You can register the remote Docker host on HCL OneTest[™] Server. See Registering a remote Docker host on page 303.

Setting up a secure remote Docker host computer

You must set up a computer to host the remote Docker host. You can set up the remote host with a secure mode of connection with HCL OneTest[™] Server by using certificates issued by the remote host computer that authenticate the connection.

Before you begin

You must have identified a remote computer or VM that has a minimum of 16 GB RAM. You must have installed Ubuntu V18.04 or later, on the remote computer.

You must have installed Docker Community Edition V18.09 or later. For instructions, refer to Get Docker Engine.

Note: For the remote Docker host to be reached in a safe manner through the network, you can enable *TLS* by specifying the **tlsverify** flag and by pointing the **tlscacert** flag of the remote Docker host to a trusted CA certificate. Refer to Protect the Docker daemon socket.

You must have the entitlement key that is required for you to connect to the Harbor repository to be able to pull in the software image to the remote Docker host.

About this task

You must set up a remote computer or a Virtual Machine (VM) on which you want to set up the remote Docker host. You must be a system administrator or get the remote Docker host set up by a system administrator. You must ensure that the system administrator completes the following actions:

- Enables SSH.
- Creates user credentials for you with root permissions.
- Provides the name of the Docker container.
- Provides the IP address of the remote Docker host computer.

Perform the following steps as a user with root permissions or ask the system administrator to complete the following steps:

a. Open a terminal and connect to the remote Docker host by using an SSH tool by running the following command:

ssh root@<IP_address_of_remote_host>

b. Log in to HCL Software's Harbor container registry by running the following command:

sudo docker login hclcr.io -u <username> -p <password>



Note: You must provide the following username and password in the command to log in to the registry:



Username as email address registered with HCL
 Password as Harbor CLI secret

c. Run the following commands to pull the product images from the registry on to the remote Docker host computer:



Note: You must pull in the images with the version which is the same as the version of HCL OneTest[™] Server that you use to run the tests.

- sudo docker pull cp.hclcr.io/ot/hcl-onetest/studio<image_identifier>
- sudo docker pull hclcr.io/ot/hcl-onetest/virtualization<image_identifier>

Results

You have set up the remote Docker host computer that can be accessed in a secure mode.

What to do next

You can optionally, set up a non-secure remote Docker host. See Setting up a remote Docker host computer on page 298.

You can register the remote Docker host on HCL OneTest[™] Server. See Registering a remote Docker host on page 303.

Copying third-party application Jars to a remote Docker host

You can run API Suites in a project on HCL OneTest[™] Server on a remote Docker host. If the API Suites use a transport and the transport requires third-party Jar files for a successful run, you must ensure that the third-party application Jar files are available at the test run time. To achieve this, you must copy the third-party application Jar files to the computer where you have set up the remote Docker host.

Before you begin

If you want to copy the third-party application Jar files to the to the computer where HCL OneTest[™] Server is installed on Kubernetes, see Copying third-party application Jars to Kubernetes on page 100.

You must have server administrator privileges.

You must have completed the following tasks:

- Set up and configured the remote Docker host. See Management of Docker hosts on page 296.
- Identified the third-party application Jar files that are required and copied the Jar files. See Test run considerations for API Suites or API tests on page 279.
- Copied the Jar files of the third-party application jars to the directory or folder on the remote Docker host from where you can run the docker commands.

About this task

You can copy the required third-party application Jar files to the folder that is specific for the application under the / myFiles/Userlibs/<application_name> folder. You need not extract the files.

You can perform this task any time after you have configured the remote Docker host and you plan to run an API Suite on the remote Docker host. The API Suite uses transports and the transports require third-party application JAR files to be available at the test run time.

You can get help on the docker commands by running the command: \$ docker help from the docker command line. For more information about the docker commands, refer to the Docker command line documentation.

1. Use the following table to find the name of the folder that corresponds to the specific third-party application for the transport used in the API Suite.



Note: You must provide the name of the folder listed for the third-party application as the <application_name> in the docker command.

Application	Name of the folder to use
Camel	Camel
CentraSite	CentraSite
CICS	CICS
Coherence	Coherence
Database	JDBC
IMS	IMS
Integra	Integra
JMS	JMS
SAP RFC	SAP
Software AG Universal Messaging	SoftwareAGUM
TIBCO EMS	TIBCO
TIBCO Rendezvous	
TIBCO SmartSockets	
WebSphere Application Server Service Integration Bus (SiBus)	WAS
WebLogic	WebLogicJMX

Table 5. Name of the folder for the application

Application	Name of the folder to use
Software AG webMethods	webMethods

2. Run the following docker command to create or update the volume that contains the application Jar files:

docker run --rm -v /<anyFolder>/UserLibs/<application_name>:/ulsrc -v userlibs/<application_name>:/uldest alpine:latest cp -r /ulsrc/. /uldest/UserLibs/<application_name>

!

Attention: You must run the docker command when no other tests are running in the Docker host to prevent concurrent access problems.

Results

You have successfully copied the third-party application Jar files to the folder in the remote Docker host.

What to do next

- You can register the remote Docker host, if you have not already done so. See Registering a remote Docker host on page 303.
- You can configure the API Suite run. See Configuring an API Suite or an API test run on page 343.

Registering a remote Docker host

You must register the remote Docker host with HCL OneTest[™] Server before you add the remote Docker host to your project in a team space, which contains the test assets that you want to run on the remote Docker host.

Before you begin

Depending on the mode of connection with HCL OneTest[™] Server, you must have set up the remote Docker host computer either for a secured mode or for an unsecured mode of connection.

1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

2. Click Infrastructure > Agents and Intercepts in the navigation pane.

The Agents and Intercepts page is displayed.

You can view the agents, intercepts or Dockers that are registered with HCL OneTest[™] Server.

3. Click Add new > Add new docker host.

The New docker host dialog is displayed.

4. Enter the *host name* and the *port* of the remote Docker host in the format *<host name or IP_address>:<port>* in the **Remote Docker Host** field.

If you do not provide the port that you configured for the remote Docker host, then the default port that is used is as follows:

- Port 2375 for the unsecured mode
- Port 2376 for the secured mode
- 5. Choose from any of the following authentication modes to establish the connection between HCL OneTest[™] Server and the remote Docker host computer:
 - For the secured mode, which is the default mode and the checkbox is displayed as selected.

Perform the following steps:

- a. Select Secure mode, if it is not selected.
- b. Click the action labels to browse and select the .pem files that correspond to ca_certificate.pem, client_certificate.pem, and client_key.pem.

P

Note: You must have generated the .pem files on the remote Docker host computer and copied the files to your local drive.

• For the unsecured mode, the Secure mode checkbox must not be selected.

Perform the following step:

- a. Clear the Secure mode checkbox, if selected.
- 6. Click **Test connection** to test if a connection is established between HCL OneTest[™] Server and the remote host computer.

Any of the following events occur when Test connection is clicked:

- On a successful connection, a message is displayed.
- On a failure to connect to the remote host computer, an error message is displayed. You must resolve the error and reattempt to establish a successful connection.

Important: The remote Docker host computer must be connected successfully before you register the remote Docker host with HCL OneTest[™] Server.

7. Click Register.

The remote Docker host that you registered is displayed.



Important: The remote Docker host must be registered successfully with HCL OneTest[™] Server in the team space before you add the remote Docker host to your project in that team space.

8. Click Close to exit.

Results

You have registered the remote Docker host in your team space with HCL OneTest[™] Server.

What to do next

You can view the Docker hosts in your team space that are registered with HCL OneTest[™] Server. See Viewing remote Docker hosts that are registered with HCL OneTest Server on page 305.

You must add the registered remote Docker host to your project in your team space before you use the remote Docker host as a location to run tests in your project. See Adding a remote Docker host to the project for running tests on page 306.

Viewing remote Docker hosts that are registered with HCL OneTest[™] Server

You must register the remote Docker host in your team space with HCL OneTest[™] Server before you add the remote Docker host to your project in that team space, which contains the test assets that you want to run on the remote Docker host.

Before you begin

Depending on the mode of connection with HCL OneTest[™] Server, you must have set up the remote Docker host computer either for a secured mode or for an unsecured mode of connection. See Setting up a remote Docker host computer on page 298 or Setting up a secure remote Docker host computer on page 300.

1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

2. Click Infrastructure > Agents and Intercepts in the navigation pane.

The Agents and Intercepts page is displayed.

You can view the agents, intercepts or Dockers that are registered with HCL OneTest[™] Server in your team space.

- 3. You can view the Dockers that you own in any of the following ways:
 - Search for the Docker by entering the name of the Docker host in the Search field.



Note: You can enter either the full name or any text that is in the name. The search is enabled for case sensitive text that you can enter.

- Sort the Type column to sort the items and then identify the Docker by the name displayed.
- \circ Sort the Agents column to sort the items and identify the Docker by the owner.

You can view the following details about the Dockers that are registered with HCL OneTest[™] Server in the team space:

- The projects in the team space to which the Docker host is added, are displayed in the **Projects** column.
- The status of the Docker host is displayed in the Status column.



Note: You can add Docker hosts that are in the Ready state to your project, and then use them as locations to run tests.

Results

You have viewed the remote Docker hosts that are registered with HCL OneTest™ Server in your team space.

What to do next

You must add the registered remote Docker host to your project in your team space before you use the remote Docker host as a location to run tests in your project. See Adding a remote Docker host to the project for running tests on page 306.

Adding a remote Docker host to the project for running tests

You can choose to run tests on Docker hosts that you have set up on remote host computers. You must register the Docker host with HCL OneTest[™] Server and then add them to your project before you run tests on the remote Docker hosts.

Before you begin

You must have completed the following tasks:

- Read about the considerations you must take into account before you configure a test run to run on a remote Docker host. See Test run considerations for running tests on remote Docker hosts on page 296.
- Set up the remote Docker host system. See Setting up a remote Docker host computer on page 298 or Setting up a secure remote Docker host computer on page 300.
- Registered the remote Docker host with HCL OneTest[™] Server. See Registering a remote Docker host on page 303.
- 1. Log in to HCL OneTest[™] Server.
- 2. Open your project.

The **Overview** page is displayed.

3. Click Infrastructure > Agents and Intercepts.

The Agents and Intercepts page is displayed.

- 4. Click Add > Add docker.
- 5. Select the Docker host that you want to add to the project from the list of Docker hosts, and then click Add.

Note: You can add the Docker hosts that you registered. You can add any number of Docker hosts to your project.

The Docker hosts that you added to the project are displayed.

You can view the details of the Docker host by clicking the **Expand** icon >.

Q Search			
Туре	Agents		
∀ ≠	10.121.104.38:80 Owned by me		
	Details	Server:	Docker Engine - Community
		Secure	No
		Version:	19.03.2
		Address:	10.121.104.38
		Port:	80
		Operating system:	linux
		Architecture:	amd64
		Api version:	1.40 (minimum version 1.12)
		Go version:	go1.12.8
		Git commit:	6a30dfc
		Built:	Thursday, August 29, 2019 5:27 AM
		Experimental:	false

What to do next

You can select any of the remote Docker hosts as an alternate location to run the test asset in your project while configuring a test run from the **Execution** page.

Related information

Test run configurations on page 327

Editing configurations of a remote Docker host

You can edit the host name or the port of the registered Docker host computer instead of registering it as a new remote host if any of the parameters are changed on the remote host computer. You can also change the mode of authentication of a registered remote Docker host.

Before you begin

You must have completed the following tasks:

- Set up the remote Docker host computer. See Setting up a remote Docker host computer on page 298 or Setting up a secure remote Docker host computer on page 300.
- Registered the remote Docker host with HCL OneTest[™] Server in your team space. See Registering a remote Docker host on page 303.
- 1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

2. Click Infrastructure > Agents and Intercepts in the navigation pane.

The Agents and Intercepts page is displayed.

You can view the agents, intercepts, Dockers, or clusters that are registered with HCL OneTest[™] Server in your team space.

- 3. You can view the Dockers that you own in any of the following ways:
 - \circ Search for the Docker by entering the name of the Docker host in the Search field.



Note: You can enter either the full name or any text that is in the name. The search is enabled for case sensitive text that you can enter.

- Sort the Type column to sort the items and then identify the Docker by the name displayed.
- Sort the Agents column to sort the items and identify the Docker by the owner.

You can view the following details about the Dockers that are registered with HCL OneTest[™] Server in your team space:

- The projects in the team space to which the Docker host is added, are displayed in the **Projects** column.
- The status of the Docker host is displayed in the Status column.
- 4. Identify the Docker host that you want to modify the configuration, and then click the **Edit** icon \mathscr{O} .

Note: The *icon* is displayed in the **Actions** column in the row of the Docker only if you own the remote Docker host.

The Update docker host dialog is displayed.

5. Change any of the configurations.

To change	Do this
Change the host name or the port of the remote	Enter the changed value of the host name or the port
Docker host.	in the Remote hostname field.

To change	Do this
Change the mode of authentication from a non-se- cure mode to a secure mode.	 a. Select the Secure mode option. b. Click the action labels to browse and select the .pem files that correspond to ca_certificate.pem, client_certificate.pem, and client_key.pem. Note: You must have generated the .pem files on the remote host computer and copied the files to your local drive.
Change the mode of authentication from a secure mode to a non-secure mode.	Clear the Secure mode option that is selected.

- 6. Click **Test connection** to test whether a connection is established between HCL OneTest[™] Server and the remote host computer:
 - On a successful connection, a message is displayed.
 - On a failure to connect to the remote host computer, an error message is displayed. You must resolve the error and reattempt to establish a successful connection.

7. Click Update.

The remote Docker host with the updated details is displayed.

Results

You have updated the registered remote Docker host with the changed parameters.

What to do next

You can now add the updated Docker host to your project. See Adding a remote Docker host to the project for running tests on page 306.

Related information

Setting up a remote Docker host computer on page 298

Registering a remote Docker host on page 303

Removing a remote Docker host from a project on page 310

Unregistering a remote Docker host from HCL OneTest Server on page 311

Removing a remote Docker host from a project

You can delete a remote Docker host that you added to your project in HCL OneTest[™] Server when you no longer need it to run tests.

Before you begin

You must have completed the following tasks:

- 1. Set up the remote Docker host computer. See Setting up a remote Docker host computer on page 298 or Setting up a secure remote Docker host computer on page 300.
- Registered the remote Docker host with HCL OneTest[™] Server in your team space. See Registering a remote Docker host on page 303.
- 3. Added the registered Docker host to a project in your team space. See Adding a remote Docker host to the project for running tests on page 306.
- 1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

2. Open the project in your team space from the My Projects page.

The **Overview** page is displayed.

3. Click Infrastructure > Agents and Intercepts in the navigation pane.

The Agents and Intercepts page is displayed.

You can view the agents, intercepts or Dockers that are added to your project.

- 4. You can view the Dockers that you own in any of the following ways:
 - \circ Search for the Docker by entering the name of the Docker host in the Search field.



Note: You can enter either the full name or any text that is in the name. The search is enabled for case sensitive text that you can enter.

- Sort the Type column to sort the items and then identify the Docker by the name displayed.
- Sort the Agents column to sort the items and identify the Docker by the owner.

You can view the following details about the Dockers that are registered with HCL OneTest[™] Server:

- The projects to which the Docker host is added, are displayed in the Projects column.
- \circ The status of the Docker host is displayed in the $\ensuremath{\textit{Status}}$ column.

5. Identify the Docker host that you want to remove from the project, and then click the **Remove docker host** icon

Note: The III icon is displayed in the Actions column in the row of the Docker only if you own the remote Docker host.

A message is displayed that the Docker host is removed from the project successfully.

Results

You have removed the remote Docker host from your project. The remote Docker host is no longer available as a location while configuring a test run in your project.

What to do next

You might have to add a remote Docker host to your project to use the remote Docker host as a location to run tests.

Related information

Unregistering a remote Docker host from HCL OneTest Server on page 311

Editing configurations of a remote Docker host on page 307

Unregistering a remote Docker host from HCL OneTest[™] Server

You can unregister a remote Docker host that is registered with HCL OneTest[™] Server in a team space when you no longer require it.

Before you begin

You must have completed the following tasks:

- 1. Set up the remote Docker host computer. See Setting up a remote Docker host computer on page 298 or Setting up a secure remote Docker host computer on page 300.
- 2. Registered the remote Docker host with HCL OneTest[™] Server in a team space. See Registering a remote Docker host on page 303.
- 1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

2. Click Infrastructure > Agents and Intercepts in the navigation pane.

The Agents and Intercepts page is displayed.

You can view the agents, intercepts, Dockers, or clusters that are registered with HCL OneTest[™] Server in your team space.

3. Identify the Docker host that you want to unregister.

Note: The and in icons are displayed in the Actions column in the row of the Docker only if you own the remote Docker host.

- 4. Unregister the Docker host by completing the following steps:
 - a. Click the Unregister docker host icon III.
 - b. Click Unregister in the Unregister docker host dialog box.

A message is displayed that the Docker host is unregistered successfully.

Results

You have unregistered the remote Docker host in a team space on HCL OneTest[™] Server. You cannot run tests on this remote Docker host if it is added to your project. You might have to register it again with HCL OneTest[™] Server, if you want to use the remote Docker host in your projects.

Related information

Editing configurations of a remote Docker host on page 307 Adding a remote Docker host to the project for running tests on page 306 Removing a remote Docker host from a project on page 310

Management of remote Kubernetes clusters

You can find information about the tasks that you can perform on remote Kubernetes clusters. After you set up a remote Kubernetes cluster, you can register the external cluster with a team space on HCL OneTest[™] Server. You must then add the remote cluster to a project before you run test assets or resources on the remote Kubernetes cluster.

You can find the following information about managing the external Kubernetes cluster:

- Considerations for using a remote Kubernetes cluster on page 313
- Registering a remote Kubernetes cluster on page 315
- Viewing remote Kubernetes clusters on page 318
- Adding a remote Kubernetes cluster to a project on page 320
- Editing configurations of a remote Kubernetes cluster on page 322
- · Removing a remote Kubernetes cluster from a project on page 324
- Unregistering a remote Kubernetes cluster from a team space on page 326

Considerations for using a remote Kubernetes cluster

When you want to use a remote Kubernetes cluster as a location to run the supported tests or test resources, you must read the considerations first.

Before you want to run any of the supported tests or test resources on HCL OneTest[™] Server that are configured to run on a remote Kubernetes cluster, you must have completed the following tasks:

- Verified that the Kubernetes cluster that you want to use is a supported one by referring to the OS, platform, and containers that are specified for HCL OneTest[™] Server in System Requirements on page 13.
- Kept a suitable kubeconfig file with access to the remote Kubernetes cluster in a folder on the computer that you want to use to access an instance of HCL OneTest[™] Server.

You must be familiar with the administration of a Kubernetes cluster. When you as the cluster administrator, set up the remote Kubernetes cluster must consider the following requirements:

- You must have a kubeconfig file with access to the remote Kubernetes cluster in a folder on the computer that you want to use to access an instance of HCL OneTest[™] Server.
 - Note: If the kubeconfig file references certificate files by using filepaths then the certificate data must be embedded in the kubeconfig file to make it usable by HCL OneTest[™] Server. If the kubeconfig file contains multiple contexts, then only the current context is required.

You can use the following kubectl command to create a suitable <code>kubeconfig</code> file called <code>portable-config</code> in the current folder. The <code>portable-config</code> file contains embedded certificate data and the information used by the current context:

```
kubectl config view --flatten --minify > portable-config
```

 You must ensure that the remote Kubernetes cluster is able to access the HCL OneTest[™] Server image registry which is the same registry that you used to install HCL OneTest[™] Server. There is no need to copy the HCL OneTest[™] Server image to the remote Kubernetes cluster but the remote cluster must be able to access the image registry at test runtime.

If the remote cluster that you want to use is a Lightweight Kubernetes (k3s) cluster, it might require a *Secret* to pull the HCL OneTest[™] Server image. You must run the following command on the remote k3s cluster:

```
kubectl create secret docker-registry hclcr.io \
-n {remote-namespace} \
--docker-server=hclcr.io \
--docker-username={okta-email-address} \
--docker-password={harbor-cli-secret} \
--docker-email={example@abc.com}
```



Ż

- You must replace {remote-namespace} with the value of the namespace that you have used for the remote cluster.
 - You must replace {*okta-email-address*} with the user name of the Harbor repository and replace {*harbor-cli-secret*} with the secret key that you copied from the Harbor repository.
 - If the user name contains any special characters, such as \$, you must enclose it within single quotation-marks.
 - You can replace {example@abc.com} with the email address of the administrator, if required.
- You need not configure separate licenses for running on the remote cluster because the licenses are
 consumed from the pool of available licenses that are configured for the team space on HCL OneTest™
 Server. The licenses are returned to the pool when the test run is completed on the remote cluster.
- You must ensure that the HCL OneTest[™] Server domain is accessible from the remote cluster so that the pod in the cluster is able to communicate with HCL OneTest[™] Server.
- You must ensure that the appropriate **PriorityClass** exists on the remote cluster if you want to control the priority given to the remote execution pod by the scheduler. The same **PriorityClass** that is used by the HCL OneTest[™] Server execution pod is used by the remote execution pod. If the named **PriorityClass** does not exist in the remote cluster, then no **PriorityClass** is specified by the remote execution pod.
- You must provide the Ingress details such as Ingress type, Ingress host pattern, and Ingress secret when you register a remote cluster with your team space on HCL OneTest[™] Server. These configurations are required when you want to run virtual services on the remote cluster and run tests from the remote cluster that use static agents.
- You can enter the code snippets for nodeSelectors and tolerations in a yaml format, if you want to use nodeSelectors and tolerations on the remote cluster. You can enter these in the fields provided in the Advanced configuration dialog when you register a remote cluster with your team space on HCL OneTest[™] Server.

For more information about nodeSelector, see nodeSelector and for tolerations, see Tolerations.

Restrictions: The following restrictions apply when you want to run the supported tests on a remote Kubernetes cluster:

- Using the **UserLibs** that are required for running certain API Suites are not supported on the remote cluster.
- Running of Compound Tests that contain performance tests, which require the **NodePort** access to connect to static agents, are not supported on the remote cluster.

When you plan to run any of the test assets or resources on a remote Kubernetes cluster from a project on HCL OneTest[™] Server, you must complete the following tasks:

	Tasks	More information
1	Register a remote Kubernetes cluster with a team space on HCL OneTest™ Server.	Registering a remote Kubernetes cluster on page 315
2	View remote Kubernetes clusters added to a team space.	Viewing remote Kubernetes clusters on page 318
3	Add a remote Kubernetes cluster to a project in a team space.	Adding a remote Kubernetes cluster to a project on page 320
4.1	 Configure a run for your test that you want to run on the remote Kubernetes cluster by performing the following actions: 1. Check for the prerequisite tasks that you must perform before you configure a test run for the test. 2. Select the task for the test that you want to configure for a run, and then follow the steps to run the test. 	 Test run configurations on page 327 Prerequisites to running tests on page 277 Test run configurations on page 327
4.2	 Configure a run of the virtual service resources that you want to run on the remote Kubernetes cluster by performing the following actions: 1. Check for the prerequisite tasks that you must perform before you configure a run of the virtual services. 2. Select the virtual service resources in your project that you want to configure for a run, and then follow the steps to run them. 	 Prerequisites for running virtual services on page 468 Configuring a run of a virtual service on page 478

Related information

Test run configurations on page 327

Management of remote Kubernetes clusters on page 312

Registering a remote Kubernetes cluster

You must register a remote Kubernetes cluster to your team space on HCL OneTest[™] Server before you add the remote cluster to your project.

Before you begin

You must have completed the following tasks:

- Verified that the Kubernetes cluster that you want to use is a supported one by referring to the OS, platform, and containers that are specified for HCL OneTest[™] Server in System Requirements on page 13.
- Kept a suitable kubeconfig file with access to the remote Kubernetes cluster in a folder on the computer that you want to use to access an instance of HCL OneTest[™] Server.
- Ensured that you are assigned a role as a *Member* or *Project Creator* in the team space. See Managing members and their roles in a team space on page 720.
- Ensured that you are assigned a role as a *Project Owner* or *Tester* in the project. See Managing access to server projects on page 734.
- 1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

2. Click Infrastructure > Agents and Intercepts in the navigation pane of the team space.

The Agents and Intercepts page is displayed.

3. Click Add new > Add new cluster.

The **New cluster** dialog is displayed.

- 4. Perform the following steps to add the kubeconfig file:
 - a. Click Browse, and locate the kubeconfig file of the Kubernetes cluster that you want to add.
 - b. Select the kubeconfig file, and then click Open.

The name of the kubeconfig file that you selected is displayed along with the address of the Kubernetes cluster that is specified in the file.

c. Click Next.

The address of the Kubernetes cluster that is configured in the kubeconfig file is displayed in the Address field.



Note: You can change the address of the Kubernetes cluster if it is different from the address in the kubeconfig file.

- 5. Perform the following steps to add a namespace and name for the cluster:
 - a. Enter the namespace of the cluster in the Namespace field.
 - b. Enter a name for the cluster in the Name field.

The name helps you to identify the cluster.

c. Click Next.

- 6. Perform the following steps to add the ingress details of the cluster:
 - a. Select the ingress type of the cluster from the **Ingress type** list.

You can select the ingress type from the following options that are displayed:

Option	Description	Result
None	When selected specifies that no ingress type is configured for the re- mote Kubernetes cluster.	You can run any of the supported tests on the remote cluster but not on the re- mote agents.
NGINX	When selected specifies that NGINX is configured as the ingress type for the remote Kubernetes cluster.	You can run any of the supported tests on the remote cluster or on any of the remote agents.

b. Enter the ingress host pattern of the cluster in the Ingress host pattern field.

The DNS used by a computer that runs a client application (such as a static agent) or the HTTP proxy that routes traffic to the virtual service needs to resolve such host names to the IP address of the ingress domain.

For example, if the IP of the remote cluster is 12.12.12.123, then you must enter the ingress host pattern as *.12.12.12.123.nip.io

The Unique ID of the virtual service is prefixed to the ingress host name when virtual services are routed from the HCL OneTest[™] Server cluster.

c. Enter the name of the secret in the remote namespace, which contains the certificate information.

You must have created the secret and named it following the naming conventions per the Kubernetes guidelines. The certificate that you create is a wildcard certificate which contains the Ingress host pattern of the Kubernetes cluster. This wildcard certificate ensures that the client applications can trust the virtual services.

Note: If a secret name is not provided then the default certificate that is provided by NGINX is used, which might cause issues to authenticate the virtual service by the client applications.

d. Click Next.

- 7. Optionally, perform the following steps to enter the code snippets for *nodeSelectors* and *tolerations*, if applicable for the remote cluster:
 - a. Enter the code snippet for *nodeSelectors* in a yaml format in the **Node selectors** field.
 - b. Enter the code snippet for *tolerations* in a yaml format in the **Tolerations** field.
 - c. Select the Copy pull secret to the cluster checkbox, if it is not already selected.

Note: The remote Kubernetes cluster pulls the secret to access the HCL OneTest[™] Server image registry which is the same registry that you used to install HCL OneTest[™] Server. The remote Kubernetes cluster must be able to access the image registry at test runtime.

d. Click Register.

The remote cluster is added to the team space and is displayed with the icon in the **Type** column on the **Agents and Intercepts** page. You can identify the cluster with its name in the **Agents** column.

Note: The Projects column does not display any projects that are associated with the cluster yet.

Results

You have registered a remote Kubernetes cluster with your team space on HCL OneTest[™] Server.

What to do next

You must add the remote cluster to your project in your team space before you use the remote cluster as a location to run test assets or resources in your project. See Adding a remote Kubernetes cluster to a project on page 320.

Related information

Management of remote Kubernetes clusters on page 312

Viewing remote Kubernetes clusters

You can view the clusters that you have registered with a team space on HCL OneTest[™] Server to view their details or edit their configurations.

Before you begin

You must have completed the following tasks:

- Read and completed the tasks mentioned in Considerations for using a remote Kubernetes cluster on page 313, if you want to use a remote Kubernetes cluster as a location to run the test.
- Registered a remote Kubernetes cluster with your team space on HCL OneTest[™] Server. See Registering a remote Kubernetes cluster on page 315.
- Ensured that you are assigned a role as a *Member* or *Project Creator* in the team space. See Managing members and their roles in a team space on page 720.
- Ensured that you are assigned a role as a *Project Owner* or *Tester* in the project. See Managing access to server projects on page 734.

1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

2. Click Infrastructure > Agents and Intercepts in the navigation pane of the team space.

The Agents and Intercepts page is displayed.

You can view the agents, intercepts, Dockers, or clusters that are registered with the team space on HCL OneTest[™] Server.

- 3. You can view the clusters that you own in any of the following ways:
 - Search for the cluster by entering the name of the cluster in the Search field.

ľ

Note: You can enter either the full name or any text that is in the name. The search is enabled for case-sensitive text that you can enter.

- Sort the Type column to sort the items, and then identify the cluster by the name or owner.
- Sort the Agents column to sort the items, and then identify the cluster by the name or owner.

You can view the following details about the clusters that are in the team space:

- The projects in the team space to which the cluster is added are displayed in the Projects column.
- $\circ\,$ The status of the cluster is displayed in the Status column.



Note: You can add clusters that are in the Ready state to your project, and then use them as locations to run tests.

You can view the details of the cluster by clicking the **Expand** icon \geq .

Туре 🔤	Agents 🛆		
~ 🛞	mycluster Owned by me		
	① Details	Name	Value
		Address	https://10.134.54.52:6443
		Namespace	default
		Nodes	1
		Version	1.21

The following table describes the details about the cluster:

Name	Description
Address	Specifies the address of the remote Kubernetes API.
Namespace	Specifies the <i>namespace</i> of the remote Kubernetes cluster in which the test runs oc- cur.
Nodes	Specifies the number of nodes in the remote Kubernetes cluster.
Version	Specifies the Kubernetes version of the remote Kubernetes cluster.

Results

You have viewed details of the remote clusters that are registered with a team space on HCL OneTest[™] Server.

What to do next

You must add the remote cluster to your project in your team space before you can use the remote cluster as a location to run test assets or resources that are in your project. See Adding a remote Kubernetes cluster to a project on page 320.

Related information

Management of remote Kubernetes clusters on page 312

Adding a remote Kubernetes cluster to a project

You must add a remote Kubernetes cluster to your project after you register the cluster with your team space on HCL OneTest[™] Server.

Before you begin

You must have completed the following tasks:

- Read and completed the tasks mentioned in Considerations for using a remote Kubernetes cluster on page 313, if you want to use a remote Kubernetes cluster as a location to run the test.
- Registered a remote Kubernetes cluster with your team space on HCL OneTest[™] Server. See Registering a remote Kubernetes cluster on page 315.
- Ensured that you are assigned a role as a *Member* or *Project Creator* in the team space. See Managing members and their roles in a team space on page 720.
- Been assigned a role as an Owner in the project.
- · Created a project.
- 1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

2. Open your project.

The **Overview** page is displayed.

3. Click Infrastructure > Agents and Intercepts in the navigation pane of the team space.

The Agents and Intercepts page is displayed.

4. Click Add > Add cluster.

The Add cluster dialog is displayed.


5. Select the cluster that you want to add to the project from the list of clusters that are registered with the team space, and then click **Add**.



Note: You can add the clusters that are registered with the team space. You can add any number of clusters to your project.

The clusters that you added to the project are displayed.

You can view the details of the cluster by clicking the **Expand** icon \geq .



The following table describes the details about the cluster:

Name	Description
Address	Specifies the address of the remote Kubernetes API.
Namespace	Specifies the <i>namespace</i> of the remote Kubernetes cluster in which the test runs oc- cur.
Nodes	Specifies the number of nodes in the remote Kubernetes cluster.
Version	Specifies the Kubernetes version of the remote Kubernetes cluster.

What to do next

You can select any of the remote clusters as an alternate location to run the test assets or resources that are in your project while you configure a run from the **Execution** page.

Related information

Test run configurations on page 327 Management of remote Kubernetes clusters on page 312

Editing configurations of a remote Kubernetes cluster

You can edit the kubeconfig file, address, namespace, name, or ingress details of the remote Kubernetes cluster that you added to a team space on HCL OneTest[™] Server.

Before you begin

You must have completed the following tasks:

- Read and completed the tasks mentioned in Considerations for using a remote Kubernetes cluster on page 313, if you want to use a remote Kubernetes cluster as a location to run the test.
- Registered a remote Kubernetes cluster with your team space on HCL OneTest[™] Server. See Registering a remote Kubernetes cluster on page 315.
- Ensured that you are assigned a role as a *Member* or *Project Creator* in the team space. See Managing members and their roles in a team space on page 720.
- Ensured that you are assigned a role as a *Project Owner* or *Tester* in the project. See Managing access to server projects on page 734.
- 1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

2. Click Infrastructure > Agents and Intercepts in the navigation pane of the team space.

The Agents and Intercepts page is displayed.

You can view the agents, intercepts, Dockers, or clusters that are registered with the team space on HCL OneTest[™] Server.

- 3. You can view the clusters that you own in any of the following ways:
 - Search for the cluster by entering the name of the cluster in the Search field.



Note: You can enter either the full name or any text that is in the name. The search is enabled for case-sensitive text that you can enter.

- Sort the Type column to sort the items, and then identify the cluster by the name or owner.
- Sort the Agents column to sort the items, and then identify the cluster by the name or owner.

You can view the following details about the clusters that are in the team space:

- The projects in the team space to which the cluster is added, are displayed in the Projects column.
- The status of the cluster is displayed in the Status column.



Note: You can add clusters that are in the Ready state to your project, and then use them as locations to run tests.

4. Identify the cluster that you want to modify the configurations, and then click the **Edit** icon \mathscr{O} .

Note: The icon is displayed in the Actions column in the row of the cluster only if you own the cluster.

The Update cluster dialog is displayed.

- 5. Perform the following steps to change the kubeconfig file:
 - a. Click **Browse**, and locate the kubeconfig file of the Kubernetes cluster that you want to use.
 - b. Select the kubeconfig file, and then click Open.

The name of the kubeconfig file that you selected is displayed along with the address of the Kubernetes cluster that is specified in the file.

- c. Click Next.
- 6. Perform the following steps to change the namespace or name of the cluster:
 - a. Edit or change the namespace of the cluster that you want to use, in the Namespace field.
 - b. Edit or change the name of the cluster in the Name field.
 - c. Click Next.
- 7. Perform the following steps to change the ingress details of the cluster:
 - a. Select the ingress type of the cluster from the Ingress type list, if you want to use a different cluster.
 - b. Enter or change the ingress host pattern of the cluster in the **Ingress host pattern** field, if you did not provide it when setting up the remote cluster or change it to match the cluster you want to use.
 - c. Enter the secret if you did not provide it when setting up the remote cluster.

The secret is used to authenticate the remote cluster to use the licenses from the Team space License Server so that the inbound traffic is allowed into the ingress domain.



Note: The secret to use must be available with your HCL OneTest[™] Server server administrator.

d. Click Next.

- 8. Optionally, perform the following steps to edit or change the code snippets for *nodeSelectors* and *tolerations*, if applicable for the remote cluster:
 - a. Enter the code snippet for nodeSelectors in a yaml format in the Node selectors field.
 - b. Enter the code snippet for tolerations in a yaml format in the Tolerations field.

9. Click Update.

The remote cluster is displayed with the updated configurations.



Note: The projects that are associated with the cluster are displayed in the **Projects** column and you need not add the cluster to the same project again.

Results

You have updated an existing remote cluster with the changed configurations.

What to do next

You can select the updated cluster as an alternate location to run the test assets or resources that are in your project while you configure a run from the **Execution** page.

Related information

Management of remote Kubernetes clusters on page 312

Removing a remote Kubernetes cluster from a project

You can remove a remote Kubernetes cluster from a project in a team space on HCL OneTest[™] Server when you no longer need the cluster to run tests.

Before you begin

You must have completed the following tasks:

- Registered a remote Kubernetes cluster with your team space on HCL OneTest[™] Server. See Registering a remote Kubernetes cluster on page 315.
- Added the Kubernetes cluster to a project in your team space. See Adding a remote Kubernetes cluster to a project on page 320.



Note: You can remove remote Kubernetes clusters that only you added to the project.

- 3. Ensured that you are assigned a role as a *Member* or *Project Creator* in the team space. See Managing members and their roles in a team space on page 720.
- 4. Been assigned a role as an Owner in the project.

1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

2. Open the project in your team space.

The **Overview** page is displayed.

3. Click Infrastructure > Agents and Intercepts in the navigation pane of your team space.

The Agents and Intercepts page is displayed.

You can view the agents, intercepts, Dockers, or clusters that are added to your project.

- 4. You can view the clusters that you own in any of the following ways:
 - Search for the cluster by entering the name of the cluster in the Search field.



Note: You can enter either the full name or any text that is in the name. The search is enabled for case-sensitive text that you can enter.

- Sort the Type column to sort the items, and then identify the cluster by the name or owner.
- Sort the Agents column to sort the items, and then identify the cluster by the name or owner.
- 5. Identify the cluster that you want to remove from the project, and then click the **Remove cluster** icon III.

Note: The 🔟 icon is displayed in the Actions column in the row of the cluster only if you own the remote cluster.

A message is displayed that the remote cluster is removed from the project successfully.

Results

You have removed the remote cluster from your project. The remote cluster is no longer available as a location when you configure a run of the test assets or resources that are in your project.

What to do next

You might have to add a remote cluster to your project to use the remote cluster as a location to run test assets or resources.

Related information

Management of remote Kubernetes clusters on page 312 Unregistering a remote Kubernetes cluster from a team space on page 326 Editing configurations of a remote Kubernetes cluster on page 322

Unregistering a remote Kubernetes cluster from a team space

You can unregister a remote Kubernetes cluster from a team space when you no longer require it.

Before you begin

You must have completed the following tasks:

- Registered a remote Kubernetes cluster with your team space on HCL OneTest[™] Server. See Registering a remote Kubernetes cluster on page 315.
- 2. Ensured that you are assigned a role as a *Member* or *Project Creator* in the team space. See Managing members and their roles in a team space on page 720.
- 3. Ensured that you are assigned a role as a *Project Owner* or *Tester* in the project. See Managing access to server projects on page 734.
- 1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

2. Click Infrastructure > Agents and Intercepts in the navigation pane of the team space.

The Agents and Intercepts page is displayed.

You can view the agents, intercepts, Dockers, or clusters that are registered with the team space on HCL OneTest[™] Server.

- 3. You can view the clusters that you own in any of the following ways:
 - Search for the cluster by entering the name of the cluster in the Search field.

Note: You can enter either the full name or any text that is in the name. The search is enabled for case-sensitive text that you can enter.

- Sort the Type column to sort the items, and then identify the cluster by the name or owner.
- Sort the Agents column to sort the items, and then identify the cluster by the name or owner.
- 4. Identify the cluster that you want to remove.

Note: The and in icons are displayed in the Actions column in the row of the cluster only if you own the remote cluster.

- 5. Unregister the cluster by completing the following steps:
 - a. Click the **Unregister cluster** icon **III**.
 - b. Click Unregister in the Unregister cluster dialog box.

A message is displayed that the remote cluster is unregistered successfully.

ľ

Results

You have unregistered the remote cluster from a team space on HCL OneTest[™] Server. You cannot run test assets or resources on this remote cluster if it is added to your project. You might have to add it again to your team space, if you want to use the remote cluster in your projects.

Related information

Management of remote Kubernetes clusters on page 312 Editing configurations of a remote Kubernetes cluster on page 322 Adding a remote Kubernetes cluster to a project on page 320 Removing a remote Kubernetes cluster from a project on page 324

Test run configurations

You can configure and run tests in HCL OneTest[™] Server after you add the test resources to your project in your team space.

Before you configure a test run, you must have completed the following tasks:

- Created a project on HCL OneTest[™] Server or you must have been granted access to a project with the *Tester* role assigned. See Test assets and a server project on page 724.
- Created tests in the desktop clients and committed the test assets and test resources to a remote repository. You must have added the remote repository to the project.
- Read the considerations you must take into account for certain test types. See Prerequisites to running tests on page 277.

You must be a project Owner or a member with the Tester role assigned to configure and run a test.

You can find information about how to configure and run the following types of test assets:

Type of Suite or test	Suite or test	More information
AFT Suite	Suite	Configuring an AFT Suite run on page 333
API Suite	Suite	Configuring an API Suite or an API test run on page 343
Compound Test that contains HTML tests	Suite	Configuring a run of a Compound Test that con- tains HTML tests on page 354
Compound Test that contains Web UI tests	Suite	Configuring a run of a Compound Test that con- tains Web UI tests or a Functional Web UI test on page 363

Type of Suite or test	Suite or test	More information
Compound Test that contains mobile tests	Suite	Configuring a run of a Compound Test that con- tains mobile tests or a Functional Mobile test on page 374
Compound Test that contains performance tests	Suite	Configuring a run of a Compound Test that con- tains performance tests or a Performance test on page 397
JMeter test	Suite	Configuring a run of a JMeter test on page 408
JUnit test	Suite	Configuring a run of a JUnit test on page 414
Postman test	Suite	Configuring a run of a Postman test on page 421
Rate Schedule	Suite	Configuring a run of a Rate Schedule or VU Schedule on page 428
VU Schedule	Suite	Configuring a run of a Rate Schedule or VU Schedule on page 428
API test	Test	Configuring an API Suite or an API test run on page 343
 Functional test Note: The Functional test can contain any or the following tests: Mobile tests Web UI tests Windows tests 	Test	 Configuring a run of a Compound Test that contains mobile tests or a Function- al Mobile test on page 374 Configuring a run of a Compound Test that contains Web UI tests or a Function- al Web UI test on page 363 Configuring a run of a Functional Win- dows test on page 387
Performance test	Test	Configuring a run of a Compound Test that con- tains performance tests or a Performance test on page 397

Configuring a Suite or test for a quick run

You can configure any type of Suite or test to be run on HCL OneTest[™] Server when you want to quickly ensure that the test runs correctly. You might not want to set the different options for the test nor want to schedule the run.

Before you begin

You must have completed the following tasks:

- Read and completed the tasks mentioned in Prerequisites to running tests on page 277 if they apply to the test you want to configure for a run.
- Ensured that you are assigned a role as a *Member* or *Project Creator* in the team space. See Managing members and their roles in a team space on page 720.
- Ensured that you are assigned a role as a *Project Owner* or *Tester* in the project. See Managing access to server projects on page 734.
- 1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

- 2. Open the project that contains the test assets, and then click Execution.
- 3. Select the branch of the repository that contains the test assets.

The test assets that are contained in the selected branch of the repository are displayed in the following tabs on the **Execution** page:

Tab	Description
SUITES	Lists all suites, compound tests, JMeter tests, JUnit tests, Postman tests, Rate Sched- ules, or VU Schedules that are in the selected branch of the repository.
TESTS	Lists all API tests, functional tests, or performance tests that are in the selected branch of the repository.
ADVANCED	Lists all assets that are displayed when custom filters are applied for assets in the se- lected branch of the repository.

4. Select the tab based on the type of test assets that you want to run as indicated in the following table:

If	Then
You want to run AFT Suites, API Suites, Compound Tests, JMeter tests, JUnit tests, Postman tests, Rate Schedules, or VU Schedules,.	Click the SUITES tab.
You want to run API tests, functional tests, or perfor- mance tests.	Click the TESTS tab.
You want to find Suites and tests by using custom fil- ters, and then run Suites and tests.	Click the ADVANCED tab.

The test assets in the selected tab are displayed.

5. Identify the test asset that you want to run by performing any of the following actions:

• Scroll through the list.

i **Tip:** You can hover over the icon in the **Type** column to know the type of the test asset.

Note: You can also identify the type of the asset from the icon that represents the test type as shown in the following table:

lcon	Represents	Listed in the SUITES tab	Listed in the TESTS tab	Listed in the AD- VANCED tab
-63-	API test		0	0
•	Functional test		0	0
٢	Performance test		0	0
	AFT Suite	0		0
•	API Suite	0		0
00 43 (1) (10	Compound Test	0		0
0	HCL AppScan CodeSweep	0		0
/JMeter"	JMeter Test	0		0
Ju	JUnit Test	0		0
0	Postman test	0		0
9	Rate Schedule	0		0
8	VU Schedule	0		0

• Search for the test asset by entering any text contained in the test asset name in the Search field.

• Click the **Filter** icon **T** in the **SUITES** or **TESTS** tab to filter the displayed assets based on the asset type.

For example, select **API Suite** in the **SUITES** tab to display all API Suites or select **Functional Test** in the **TESTS** tab to display all functional tests that are in the selected branch of the repository.

- Click the **Filter** icon **W** in the **ADVANCED** tab, and then create a filter query by using the **New filter** option by performing the following steps:
 - a. Click New filter.
 - b. Enter a name for the filter.
 - c. Select an operator, and add a rule or a group of rules.
 - d. Add or enter the relevant parameters and either select or enter the condition and the criteria for the condition.

You can select a parameter from the following list:

- Type
- Test Asset Name
- Test Asset Path
- Last Result
- Next Run
- Components
- e. Save the filter query to save and apply the filter query to filter the assets based on the query.

The test assets that match the filter criteria are displayed.

 Retrieve and apply a saved filter query, if you have saved filter queries previously by performing the following steps:

Note: The filter query applied previously is selected and the assets based on that filter query are displayed. To apply a different filter query, you must have created and saved the filter query.

a. Click the **Filter** icon \mathbf{M} in the **ADVANCED** tab.

The filter queries that you created and saved are displayed.

b. Click the filter that you want to apply.

The test assets that match the filter criteria are displayed.

You have identified the test asset that you want to run.

Clicking the test name displays the **Details** panel. You can view the details of the test such as the description, the branch in the repository that contains the asset, the Git details, and the details of the commits to the repository. You can also view the history of the test runs for the specific test under the **History** tab of the **Details** panel.

Click the Execute icon in the row of the identified test asset.

The Execute test asset dialog is displayed.



- If you have configured some or all of the settings for the current test run, and you do not want to continue with those settings, you can reset the settings by clicking **Reset**.
- If you want to repeat a test run and do not want to use the saved settings from a previous run, you can reset all the saved settings to their default values by clicking Reset.
- 7. Select the version of the test resources that you want to run, if you want to run a different version other than the latest version.
- 8. No action is required if you want to initiate the test run immediately after you click **Execute**.
- 9. Enter a label for the test run that helps you to identify the test on the **Results** page.

After the test run completes, the label that you entered is displayed for the test under the **Labels** column on the **Results** page.

10. Click Execute.

The test run is initiated.

Results

You have started a test run.

What to do next

You can choose to perform any of the following tasks:

- View all the states of the test asset by clicking the **Show in the Progress page** icon C for the test asset for which you started or scheduled the run. See Viewing the state of test assets on page 453.
- View the progress of the test from the **Progress** page. See Viewing the progress of running test assets on page 457.
- View the results, reports, and logs of the test from the **Results** page after the test completes the run. See Test results on page 513.

Related information

Resetting the configuration settings for a test run on page 461

Viewing the progress of running test assets on page 457

Stopping test runs on page 462

Canceling scheduled test runs on page 465

Configuring an AFT Suite run

After you added the test resources that you created in the desktop client to the project, you can configure an AFT Suite to be run on HCL OneTest[™] Server or a remote Kubernetes cluster.

Before you begin

You must have completed the following tasks:

- Read and completed the tasks mentioned in Prerequisites to running tests on page 277 if they apply to the test that you want to configure for a run.
- Read Test run considerations for AFT Suites or Functional tests on page 277 if you want to configure a run for an AFT Suite that has the agent location configured in the AFT XML file.
- Read and completed the tasks mentioned in Test run considerations for running tests on remote performance agents on page 289, if you want to use a remote agent as the location to run the test.
- Read and completed the tasks mentioned in Considerations for using a remote Kubernetes cluster on page 313, if you want to use a remote Kubernetes cluster as a location to run the test.
- Ensured that you are assigned a role as a *Member* or *Project Creator* in the team space. See Managing members and their roles in a team space on page 720.
- Ensured that you are assigned a role as a *Project Owner* or *Tester* in the project. See Managing access to server projects on page 734.
- 1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

- 2. Open the project that contains the test assets, and then click **Execution**.
- 3. Select the branch of the repository that contains the test assets.

The test assets that are contained in the selected branch of the repository are displayed in the following tabs on the **Execution** page:

Tab	Description
SUITES	Lists all suites, compound tests, JMeter tests, JUnit tests, Postman tests, Rate Sched- ules, or VU Schedules that are in the selected branch of the repository.
TESTS	Lists all API tests, functional tests, or performance tests that are in the selected branch of the repository.
ADVANCED	Lists all assets that are displayed when custom filters are applied for assets in the se- lected branch of the repository.

4. Select the tab based on the type of test assets that you want to run as indicated in the following table:

If	Then
You want to run AFT Suites, API Suites, Compound Tests, JMeter tests, JUnit tests, Postman tests, Rate Schedules, or VU Schedules,.	Click the SUITES tab.
You want to run API tests, functional tests, or perfor- mance tests.	Click the TESTS tab.
You want to find Suites and tests by using custom fil- ters, and then run Suites and tests.	Click the ADVANCED tab.

The test assets in the selected tab are displayed.

- 5. Identify the test asset that you want to run by performing any of the following actions:
 - Scroll through the list.

i Tip: You can hover over the icon in the **Type** column to know the type of the test asset.

Note: You can also identify the type of the asset from the icon that represents the test type as shown in the following table:

lcon	Represents	Listed in the SUITES tab	Listed in the TESTS tab	Listed in the AD- VANCED tab
-6.9-	API test		0	0
•	Functional test		0	0
٢	Performance test		0	0
	AFT Suite	0		0
4.2	API Suite	0		0
<u>ම් 🔂</u> රා ම	Compound Test	0		0
0	HCL AppScan CodeSweep	0		0

lcon	Represents	Listed in the SUITES tab	Listed in the TESTS tab	Listed in the AD- VANCED tab
/JMeter*	JMeter Test	0		0
Ju	JUnit Test	0		0
0	Postman test	0		0
9	Rate Schedule	0		0
8	VU Schedule	0		0

- Search for the test asset by entering any text contained in the test asset name in the Search field.
- Click the **Filter** icon **M** in the **SUITES** or **TESTS** tab to filter the displayed assets based on the asset type.

For example, select **API Suite** in the **SUITES** tab to display all API Suites or select **Functional Test** in the **TESTS** tab to display all functional tests that are in the selected branch of the repository.

- Click the **Filter** icon **W** in the **ADVANCED** tab, and then create a filter query by using the **New filter** option by performing the following steps:
 - a. Click New filter.
 - b. Enter a name for the filter.
 - c. Select an operator, and add a rule or a group of rules.
 - d. Add or enter the relevant parameters and either select or enter the condition and the criteria for the condition.

You can select a parameter from the following list:

- Type
- Test Asset Name
- Test Asset Path
- Last Result
- Next Run
- Components
- e. Save the filter query to save and apply the filter query to filter the assets based on the query.

The test assets that match the filter criteria are displayed.

- Retrieve and apply a saved filter query, if you have saved filter queries previously by performing the following steps:
 - Note: The filter query applied previously is selected and the assets based on that filter query are displayed. To apply a different filter query, you must have created and saved the filter query.
 - a. Click the **Filter** icon \mathbf{M} in the **ADVANCED** tab.

The filter queries that you created and saved are displayed.

b. Click the filter that you want to apply.

The test assets that match the filter criteria are displayed.

You have identified the test asset that you want to run.

Clicking the test name displays the **Details** panel. You can view the details of the test such as the description, the branch in the repository that contains the asset, the Git details, and the details of the commits to the repository. You can also view the history of the test runs for the specific test under the **History** tab of the **Details** panel.

6. Click the **Execute** icon 🕑 in the row of the identified test asset.

The Execute test asset dialog is displayed.

Notes:

- If you have configured some or all of the settings for the current test run, and you do not want to continue with those settings, you can reset the settings by clicking **Reset**.
- If you want to repeat a test run and do not want to use the saved settings from a previous run, you can reset all the saved settings to their default values by clicking Reset.
- 7. Select the version of the test resources that you want to run by completing any of the following actions:

Note: The test resources in the version can contain the test assets, datasets, AFT XML files, API environment tags, and other resources specific to projects created from any of the desktop clients.

• Expand the list in the Version field, find the version of the test resources, and then select the version.

Use the following details about the version of the test resources that are displayed to identify the version that you want:

- Commit message.
- Tags labeled by the user for the version committed.

- The user who committed the version to the repository.
- Relative time of the commit. For example, 2 hours ago or 3 days ago.

The list displays the versions of the test resources committed by all users to the branch in the repository. The versions are arranged with the latest version that is committed, and then followed by the versions committed previously.

• Expand the list in the **Version** field, and then search for the version that you want to select by entering a partial or the complete commit message of that version.

The version that matches the search criteria is displayed and it is selected for the test run.

The default value for the version selected for the run is the latest version in the selected branch of the repository. If you do not select any version, then the latest version is selected for the test run.

Notes:

- If you selected a version but you do not want to use that version in the test run, you can remove the selected version by clicking the x icon. As a result, the default version is selected for the test run.
- If you repeated a test or ran the test again from the **Results** page, then the version of the test resources that you chose for the earlier run is shown as selected. You can either retain this version or select any other version from the list. You can also remove the previous version by clicking the x icon.
- 8. Select the time for scheduling the test run from the following options:
 - No action is required if you want to initiate the test run immediately after you click Execute.



Important: Click Execute only after you have configured the other settings in this dialog.



Note: The default time for scheduling a run is Now.

- Select Later and configure the date and time to schedule a test run.
- Select Recurring and perform the following steps to configure recurring test runs:
 - a. Click the **Calendar** icon 📛 under **Start**, and then select the date and time at which the test run must start.
 - b. Set the frequency at which the test runs must run by entering the number in the **Repeat every** field, and then select the period from the list.

For example, if you want the test run to be run every 2 hours, enter 120, and then select the **Minute(s)** option.

c. Set the option to end the recurring test runs from the following options:

- Select the Never option, if you do not want the recurring test runs to end.
- Select the **On** option, and then click the **Calendar** icon **C**. You can select the date and time after which the scheduled test runs do not run.
- 9. Enter a label for the test run that helps you to identify the test on the **Results** page.

After the test run completes, the label that you entered is displayed for the test under the **Labels** column on the **Results** page. After you have created a label, any member of the project can use that label.

The default value for the Label field is null or an empty field.

Important: The configuration that you set for the test run in the Execute test asset dialog is preserved when you run the same test again. Those changes are not visible when another user logs in to HCL OneTest[™] Server. For example, if you created new variables on the server, those variables are available only for you when the same test is run again.

If you want to run the test immediately or at the scheduled time, click Execute, or continue with the next step.

If you are running an AFT Suite and the following conditions are true, then you must perform the next step:

- \circ You do not want to run the test on the agent configured in the <code>AFT XML</code> file.
- $\,\circ\,$ You have not selected the agent from the **Override** column in the **Location** tab.

10. Click Advanced to make the following advanced configurations:

a. Add the following setting in the Program Arguments field:

-swaplocation <configured_agent_location>:<overriding_agent_location>

For example, if the configured agent location is *91.2.352.24* and the remote agent where you want to run the test is *100.35.117.164*, then the entry in the **Program Arguments** field is as follows:

-swaplocation 91.2.352.24:100.35.117.164

If the test that you want to configure supports the presentation of the test results data in different formats, then do the required tasks in the following scenarios:

If	Then
You want the test results data in different supported formats.	Enter -history cisterna in the Program Argu- ments field.
You want to obtain the test results as a Jaeger trace.	Enter -history jaeger in the Program Arguments field.
You want the report as a test log and as a Jaeger trace.	Enter -history jaeger, testlog in the Program Ar- guments field.

lf	Then
Jaeger is already set as a program argument and you want to remove the Jaeger trace for your test.	Delete the -history jaeger entry in the Program Arguments field.



Note: The default report format is the test log format for the test reports.

Note: You must separate the arguments or variables with a white space when you enter them in the same line or start each argument or variable on a new line.

The default value for each of the fields for the advanced settings is null or an empty field.

If you want to run the test immediately or at the scheduled time, click **Execute**, or continue with the next step.

11. Follow the instructions if you are running a test asset that contains datasets:

- a. Click the DATA SOURCES tab, if it is not already open.
- b. Consider the following information about datasets before you select a dataset:

The default value for the datasets in the **DATA SOURCES** tab is null if the test asset did not have an associated dataset. If the asset had an associated dataset, the default value is the associated dataset.

You can utilize the dataset stored as an Excel or CSV file to override the original dataset associated with the Suite, test, or schedule. For example, when you have associated a dataset in .xlsx, .xls, or .csv format with the test or schedule in desktop clients and if you have another set of data stored in an Excel or CSV file, then you can select that dataset from the **Override** list.

Remember: You must have uploaded the dataset as an Excel or CSV file into the Git repository, and ensured that both the original dataset (from the test asset) and new datasets (added to the project) have the same column names.

- c. Select the dataset that you want to use in the test run from any of the following options:
 - Select the dataset that is displayed as the default dataset when the test asset contains a single dataset.

Note: If there is only one dataset in the test asset, then that dataset is displayed as the default dataset.

- Select the dataset from the list.

- Note: If there are multiple datasets in the test asset, the datasets are listed in their increasing alphabetical order.
- Select the dataset from the **Override** list to override the dataset that was associated with the test in the desktop client.
 - Important: If the test contains an encrypted dataset, the Project Owner must classify it in the DATA SECURITY tab on the Project page before you can select it. You must have added datasets to your project from the Dataset page for the datasets to be displayed in the Override list.

If you want to run the test immediately or at the scheduled time, click **Execute**, or continue with the next step.

- 12. Follow the instructions if the test requires a variable that must be passed to the test at the test run time.
 - a. Click the VARIABLES tab, if it is not already open.
 - b. Choose one of the following methods to add the variables:
 - To add new variables manually, click the **Add Variable** icon (+), enter the name, and value of the variable.
 - To add new variables from your local computer or from the Git repository that is associated

with your server project, click the **Upload** icon and select the **Upload from local system** or **Browse from server** to select the variable file.



Note: You must have created a file with the variables before you can select the file.

The default value for the variables is null or an empty field.

If you want to run the test immediately or at the scheduled time, click Execute, or continue with the next step.

- 13. Select any of the following steps that depends on the location to run the test:
 - If you want to run the tests on the remote agents, go to Step 14 on page 340.
 - \circ If you want to run the tests on a Kubernetes cluster, go to Step 15 on page 342.
- 14. Follow the instructions if you want to run a test on the remote performance agent that is connected either to the default Kubernetes cluster or the remote Kubernetes cluster:
 - a. Click the LOCATION tab, if it is not already open.

The performance agents that are configured in the test asset are listed under the **Host** column. The information about the availability of the performance agent is displayed.

Note: You must have added performance agents to your project from the Agents and Intercepts page for the performance agents to be displayed under the **Override** column.

The default value for the performance agents is null or an empty field if no performance agents were configured in the test asset. If the test asset contains performance agents that are configured, then the default performance agent is the first item to be displayed on the list of performance agents listed in the increasing alphabetical order.

b. Select the performance agent where you want to run the test asset in the following scenarios:

lf	Then	Action
The agent that is specified in the test assets is available and no other agents are added to the project.	The agent that is specified in the test assets is displayed in the Override column.	Select the agent in the Host that is also displayed in the Override column as the location to run the test.
The agent that is specified in the test assets is not available and no other agents are added to the project.	There is no agent displayed for override in the Override column.	You cannot run the test on the agent. You must wait until the agent is available to run the test on the agent.
The agent that is specified in the test assets is available and there are other agents that are added to the project.	Agents that have capabilities that match with the agent capa- bilities specified in the test as- sets are listed in the Override column as follows: • Agents with capabilities that best match the ca- pabilities in the agent in the asset are at the top of the list. • Agents with capabilities that do not match with the capabilities in the agent in the asset are listed subsequently. You can find details of both agents for the matching capa- bilities when you hover over the agent in the Override column.	 Perform any of the following actions: Select the agent in the Host that is also displayed in the Override column as the location to run the test. Select an agent in the Override column as the location to run the test.

c. Click Execute.

The test run is initiated.

- 15. Follow the instructions if you want to change the location of a Kubernetes cluster for running the test:
 - a. Click the **LOCATION** tab, if it is not already open.

The **Default Cluster** is the default location where the test runs, and it is listed under the **Host** column. The information about the availability of the default location is displayed.

Important: You must have added the following remote hosts to your project that are then displayed under the **Override** column:

- Docker hosts that are registered with HCL OneTest[™] Server.
- Kubernetes clusters that are registered with a team space.

Notes:

- If the remote Docker hosts or clusters are not added to your project, the option No
 override options is displayed as the default value and the test runs in the Kubernetes
 cluster of HCL OneTest[™] Server.
- If remote Docker hosts or clusters are added to your project, the added Docker hosts or clusters are displayed along with their availability status and ownership information.

b. Select the location where you want to run the test asset from the following options:

- Select the **Default Cluster** when no remote Docker hosts or clusters are available in your project.
- Select the remote Docker host or cluster from the list when a remote Docker host or cluster is available in your project.
- Select **No override options**, if you selected any remote Docker host or cluster and want to revert to the **Default Cluster** to run the test asset.
- c. Click Execute.

The test run is initiated.

Results

You have configured and either started or scheduled a test run of an AFT Suite.

What to do next

You can choose to perform any of the following tasks after you have initiated or scheduled a run:

- Stop the test run at any point after the test run is initiated from the **Execution** page. See Stopping test runs on page 462.
- Cancel a scheduled test run from the Execution page. See Canceling scheduled test runs on page 465.
- View all the states of the test asset by clicking the **Show in the Progress page** icon **C** for the test asset for which you started or scheduled the run. See Viewing the state of test assets on page 453.
- View the progress of the test from the **Progress** page. See Viewing the progress of running test assets on page 457.
- View the results, reports, and logs of the test from the **Results** page after the test completes the run. See Test results on page 513.

Related information

Resetting the configuration settings for a test run on page 461

Test run configurations on page 327

Configuring an API Suite or an API test run

After you added the test resources that you created in the desktop client to the project, you can configure an API Suite or an API test to be run on HCL OneTest[™] Server or a remote Kubernetes cluster.

Before you begin

You must have completed the following tasks:

- Read and completed the tasks mentioned in Prerequisites to running tests on page 277 if they apply to the test you want to configure for a run.
- Read and completed the tasks mentioned in Considerations for using a remote Kubernetes cluster on page 313, if you want to use a remote Kubernetes cluster as a location to run the test.
- Completed the following tasks if you are running API Suites or tests that use a transport and the transport requires third-party application Jar files for a successful run:
 - Read Test run considerations for API Suites or API tests on page 279.
 - Copied the third-party application Jar files to the third-party application folder on the computer where HCL OneTest[™] Server is installed, if you are running the API Suite in Kubernetes. See Copying thirdparty application Jars to Kubernetes on page 100.
 - Copied the third-party application Jar files to the third-party application folder on the computer where the remote Docker host is installed, if you are running the API Suite on a remote Docker host. See Copying third-party application Jars to a remote Docker host on page 301.
- Ensured that you are assigned a role as a *Member* or *Project Creator* in the team space. See Managing members and their roles in a team space on page 720.
- Ensured that you are assigned a role as a *Project Owner* or *Tester* in the project. See Managing access to server projects on page 734.

1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

- 2. Open the project that contains the test assets, and then click **Execution**.
- 3. Select the branch of the repository that contains the test assets.

The test assets that are contained in the selected branch of the repository are displayed in the following tabs on the **Execution** page:

Tab	Description			
SUITES	Lists all suites, compound tests, JMeter tests, JUnit tests, Postman tests, Rate Sched- ules, or VU Schedules that are in the selected branch of the repository.			
TESTS	Lists all API tests, functional tests, or performance tests that are in the selected branch of the repository.			
ADVANCED	Lists all assets that are displayed when custom filters are applied for assets in the se- lected branch of the repository.			

4. Select the tab based on the type of test assets that you want to run as indicated in the following table:

If	Then
You want to run AFT Suites, API Suites, Compound Tests, JMeter tests, JUnit tests, Postman tests, Rate Schedules, or VU Schedules,.	Click the SUITES tab.
You want to run API tests, functional tests, or perfor- mance tests.	Click the TESTS tab.
You want to find Suites and tests by using custom fil- ters, and then run Suites and tests.	Click the ADVANCED tab.

The test assets in the selected tab are displayed.

- 5. Identify the test asset that you want to run by performing any of the following actions:
 - Scroll through the list.

i **Tip:** You can hover over the icon in the **Type** column to know the type of the test asset.

Note: You can also identify the type of the asset from the icon that represents the test type as shown in the following table:

~	lcon	Represents	Listed in the SUITES tab	Listed in the TESTS tab	Listed in the AD- VANCED tab
	49	API test		0	0
		Functional test		0	0
	B	Performance test		0	0
		AFT Suite	0		0
	¢	API Suite	0		0
	0 00 0 00	Compound Test	0		0
	0	HCL AppScan CodeSweep	0		0
	/JMeter"	JMeter Test	0		0
	Ju	JUnit Test	0		0
	۲	Postman test	0		0
	0	Rate Schedule	0		0
	9	VU Schedule	0		0

- Search for the test asset by entering any text contained in the test asset name in the Search field.
- Click the **Filter** icon **Y** in the **SUITES** or **TESTS** tab to filter the displayed assets based on the asset type.

For example, select **API Suite** in the **SUITES** tab to display all API Suites or select **Functional Test** in the **TESTS** tab to display all functional tests that are in the selected branch of the repository.

- Click the **Filter** icon **W** in the **ADVANCED** tab, and then create a filter query by using the **New filter** option by performing the following steps:
 - a. Click New filter.
 - b. Enter a name for the filter.

- c. Select an operator, and add a rule or a group of rules.
- d. Add or enter the relevant parameters and either select or enter the condition and the criteria for the condition.

You can select a parameter from the following list:

- Type
- Test Asset Name
- Test Asset Path
- Last Result
- Next Run
- Components
- e. Save the filter query to save and apply the filter query to filter the assets based on the query.

The test assets that match the filter criteria are displayed.

• Retrieve and apply a saved filter query, if you have saved filter queries previously by performing the following steps:

Note: The filter query applied previously is selected and the assets based on that filter query are displayed. To apply a different filter query, you must have created and saved the filter query.

a. Click the **Filter** icon \mathbf{Y} in the **ADVANCED** tab.

The filter queries that you created and saved are displayed.

b. Click the filter that you want to apply.

The test assets that match the filter criteria are displayed.

You have identified the test asset that you want to run.

Clicking the test name displays the **Details** panel. You can view the details of the test such as the description, the branch in the repository that contains the asset, the Git details, and the details of the commits to the repository. You can also view the history of the test runs for the specific test under the **History** tab of the **Details** panel.

6. Click the **Execute** icon 🕑 in the row of the identified test asset.

The Execute test asset dialog is displayed.



- If you have configured some or all of the settings for the current test run, and you do not want to continue with those settings, you can reset the settings by clicking **Reset**.
 - If you want to repeat a test run and do not want to use the saved settings from a previous run, you can reset all the saved settings to their default values by clicking **Reset**.
- 7. Select the version of the test resources that you want to run by completing any of the following actions:
 - **Note:** The test resources in the version can contain the test assets, datasets, AFT XML files, API environment tags, and other resources specific to projects created from any of the desktop clients.
 - Expand the list in the Version field, find the version of the test resources, and then select the version.

Use the following details about the version of the test resources that are displayed to identify the version that you want:

- Commit message.
- Tags labeled by the user for the version committed.
- The user who committed the version to the repository.
- Relative time of the commit. For example, 2 hours ago or 3 days ago.

The list displays the versions of the test resources committed by all users to the branch in the repository. The versions are arranged with the latest version that is committed, and then followed by the versions committed previously.

• Expand the list in the **Version** field, and then search for the version that you want to select by entering a partial or the complete commit message of that version.

The version that matches the search criteria is displayed and it is selected for the test run.

The default value for the version selected for the run is the latest version in the selected branch of the repository. If you do not select any version, then the latest version is selected for the test run.

Notes:

1

- If you selected a version but you do not want to use that version in the test run, you can remove the selected version by clicking the x icon. As a result, the default version is selected for the test run.
- If you repeated a test or ran the test again from the **Results** page, then the version of the test resources that you chose for the earlier run is shown as selected. You can either retain this version or select any other version from the list. You can also remove the previous version by clicking the x icon.
- 8. Select the time for scheduling the test run from the following options:

• No action is required if you want to initiate the test run immediately after you click Execute.

Important: Click **Execute** only after you have configured the other settings in this dialog.



Note: The default time for scheduling a run is Now.

- Select Later and configure the date and time to schedule a test run.
- Select Recurring and perform the following steps to configure recurring test runs:
 - a. Click the **Calendar** icon to under **Start**, and then select the date and time at which the test run must start.
 - b. Set the frequency at which the test runs must run by entering the number in the **Repeat every** field, and then select the period from the list.

For example, if you want the test run to be run every 2 hours, enter 120, and then select the **Minute(s)** option.

- c. Set the option to end the recurring test runs from the following options:
 - Select the Never option, if you do not want the recurring test runs to end.
 - Select the **On** option, and then click the **Calendar** icon .
 You can select the date and time after which the scheduled test runs do not run.
- 9. Enter a label for the test run that helps you to identify the test on the **Results** page.

After the test run completes, the label that you entered is displayed for the test under the **Labels** column on the **Results** page. After you have created a label, any member of the project can use that label.

The default value for the Label field is null or an empty field.

Important: The configuration that you set for the test run in the Execute test asset dialog is preserved when you run the same test again. Those changes are not visible when another user logs in to HCL OneTest[™] Server. For example, if you created new variables on the server, those variables are available only for you when the same test is run again.

If you want to run the test immediately or at the scheduled time, click Execute, or continue with the next step.

- 10. Click Advanced to make the following advanced configurations:
 - a. Enter any JVM arguments that must be passed to the test run at run time in the **JVM Arguments** field, if applicable for the test.

For example, you can set a maximum Java heap size.

b. Enter program arguments that must be passed to the test run at run time in the **Program Arguments**, if applicable for the test.

Perform the following actions, if applicable for your test:

Configuring Jaeger tracing.

If the test that you want to configure supports the presentation of the test results data in different formats, then do the required tasks in the following scenarios:

lf	Then
You want the test results data in different supported formats.	Enter -history cisterna in the Program Arguments field.
You want to obtain the test results as a Jaeger trace.	Enter -history jaeger in the Program Argu- ments field.
You want the report as a test log and as a Jaeger trace.	Enter -history jaeger, testlog in the Program Arguments field.
Jaeger is already set as a program argument and you want to remove the Jaeger trace for your test.	Delete the -history jaeger entry in the Pro- gram Arguments field.

Note: The default report format is the *test log* format for the test reports.

• Overriding results database that is configured in the API Suite project.



Note: You can use any of the databases that are specified in the system requirements as supported databases in HCL OneTest[™] API.

Enter the following arguments in the **Program Arguments** field, if you want to override the **Results Database**:

Program Arguments	Description
-resultDatabaseURL <database_url></database_url>	Specifies the URL of the results database that overrides the results database that is configured for the project in HCL OneTest™ API.
-resultDatabaseDriver <driver_name></driver_name>	Specifies the driver of the results database that overrides the results database that is configured for the project in HCL OneTest [™] API. For example, the driver for a MySQL database is <i>com.mysql.cj.jdbc.Driver</i> .

Program Arguments	Description	
-resultDatabaseUser- name < <i>user_name></i>	Specifies the user name that is authorized to access the results data- base that overrides the results database that is configured for the project in HCL OneTest [™] API.	
-resultDatabasePa- ssword <encrypted password></encrypted 	Specifies the password that is to be used to authenticate the user to access the results database that overrides the results database that is configured for the project in HCL OneTest [™] API.	
	Note: You can encrypt the password by using the Encrypt- Password application that is available in the installation di- rectory of HCL OneTest [™] API.	

For example, if you want to override the results database that is configured in the HCL OneTest[™] API project with a different results database that has the following details:

- MySQL database as the results database with the URL as jdbc:mysql://localhost:3306/ myresultsdb
- com.mysql.cj.jdbc.Driver as the driver for the MySQL database
- tester as the user name to access the MySQL database
- #com.ghc.1!9a8521137E0A12994ACF4434E315A2B9 as the encrypted password to authenticate the user name tester

The entry in the Program Arguments field must be as follows:

-resultDatabaseDriver com.mysql.cj.jdbc.Driver

-resultDatabaseUsername tester

```
-resultDatabasePassword #com.ghc.1!9a8521137E0A12994ACF4434E315A2B9
```



Note: You must separate entries in the field with white spaces or with a new-line character.

- 11. Follow the instructions if the API Suite has an environment or secrets configured:
 - a. Click the ENVIRONMENT tab, if it is not already open.
 - Select the API test environment from the list if there are multiple environments configured in the test asset.
 - c. Select the secrets collection that contains the secrets to be used for the test run.



Ż

- The test asset that was created in the desktop client and added to the Git repository must have the environments defined as part of the API test project.
- If the test asset contained secrets, then you must create those secrets in secrets collections in the project.

The default value for the environment is the environment configured in the test asset. The default value for secrets is null or an empty field.

If you want to run the test immediately or at the scheduled time, click Execute, or continue with the next step.

- 12. Follow the instructions if you are running a test asset that contains datasets:
 - a. Click the DATA SOURCES tab, if it is not already open.
 - b. Consider the following information about datasets before you select a dataset:

The default value for the datasets in the **DATA SOURCES** tab is null if the test asset did not have an associated dataset. If the asset had an associated dataset, the default value is the associated dataset.

You can utilize the dataset stored as an Excel or CSV file to override the original dataset associated with the Suite, test, or schedule. For example, when you have associated a dataset in .xlsx, .xls, or .csv format with the test or schedule in desktop clients and if you have another set of data stored in an Excel or CSV file, then you can select that dataset from the **Override** list.

Remember: You must have uploaded the dataset as an Excel or CSV file into the Git repository, and ensured that both the original dataset (from the test asset) and new datasets (added to the project) have the same column names.

- c. Select the dataset that you want to use in the test run from any of the following options:
 - Select the dataset that is displayed as the default dataset when the test asset contains a single dataset.



Note: If there is only one dataset in the test asset, then that dataset is displayed as the default dataset.

- Select the dataset from the list.

Note: If there are multiple datasets in the test asset, the datasets are listed in their increasing alphabetical order.

• Select the dataset from the **Override** list to override the dataset that was associated with the test in the desktop client.

Important: If the test contains an encrypted dataset, the Project Owner must classify it in the DATA SECURITY tab on the Project page before you can select it. You must have added datasets to your project from the Dataset page for the datasets to be displayed in the Override list.

If you want to run the test immediately or at the scheduled time, click Execute, or continue with the next step.

- 13. Follow the instructions if the test requires a variable that must be passed to the test at the test run time.
 - a. Click the VARIABLES tab, if it is not already open.
 - b. Choose one of the following methods to add the variables:
 - To add new variables manually, click the **Add Variable** icon (\oplus), enter the name, and value of the variable.
 - To add new variables from your local computer or from the Git repository that is associated

with your server project, click the **Upload** icon and select the **Upload from local system** or **Browse from server** to select the variable file.

Note: You must have created a file with the variables before you can select the file.

The default value for the variables is null or an empty field.

If you want to run the test immediately or at the scheduled time, click Execute, or continue with the next step.

- 14. Follow the instructions if you want to change the location of a Kubernetes cluster for running the test:
 - a. Click the LOCATION tab, if it is not already open.

The **Default Cluster** is the default location where the test runs, and it is listed under the **Host** column. The information about the availability of the default location is displayed.



Important: You must have added the following remote hosts to your project that are then displayed under the **Override** column:

- Docker hosts that are registered with HCL OneTest[™] Server.
- Kubernetes clusters that are registered with a team space.

Notes:

- If the remote Docker hosts or clusters are not added to your project, the option No
 override options is displayed as the default value and the test runs in the Kubernetes
 cluster of HCL OneTest[™] Server.
 - If remote Docker hosts or clusters are added to your project, the added Docker hosts or clusters are displayed along with their availability status and ownership information.
- b. Select the location where you want to run the test asset from the following options:
 - Select the **Default Cluster** when no remote Docker hosts or clusters are available in your project.
 - Select the remote Docker host or cluster from the list when a remote Docker host or cluster is available in your project.
 - Select No override options, if you selected any remote Docker host or cluster and want to revert to the Default Cluster to run the test asset.
- c. Click Execute.

The test run is initiated.

Results

You have configured and either started or scheduled a test run of an API Suite.

What to do next

You can choose to perform any of the following tasks after you have initiated or scheduled a run:

- Stop the test run at any point after the test run is initiated from the **Execution** page. See Stopping test runs on page 462.
- Cancel a scheduled test run from the Execution page. See Canceling scheduled test runs on page 465.
- View all the states of the test asset by clicking the **Show in the Progress page** icon **C** for the test asset for which you started or scheduled the run. See Viewing the state of test assets on page 453.
- View the progress of the test from the **Progress** page. See Viewing the progress of running test assets on page 457.
- View the results, reports, and logs of the test from the **Results** page after the test completes the run. See Test results on page 513.

Related information

Resetting the configuration settings for a test run on page 461 Test run configurations on page 327

Configuring a run of a Compound Test that contains HTML tests

After you added the test resources that you created in the desktop client to the project, you can configure a Compound Test that contains HTML tests to be run on HCL OneTest[™] Server or a remote Kubernetes cluster.

Before you begin

You must have completed the following tasks:

- When you want to run a Compound Test, you must have authored a Compound Test in HCL OneTest[™] UI and must have completed the following tasks when you created the Compound test:
 - \circ Created a Compound Test under a Web UI project in your workspace.
 - Added a Functional HTML Test under the Compound Test.
 - Used the **startBrowser(Firefox,<URL>)** attribute with the browser value set to *Firefox* in the Functional test script.

Restriction: Functional test scripts that contain the **startApp()** or **callScript()** attributes are treated as non-HTML scripts and are not supported to be used in test scripts in the HTML tests.

- ∘ Ran the Compound Test that contains the HTML tests on HCL OneTest[™] UI.
- Committed the projects that include the Web UI project (with the Compound Test) and the Functional test (with the HTML tests) to the remote repository.
- Read and completed the tasks mentioned in Considerations for using a remote Kubernetes cluster on page 313, if you want to use a remote Kubernetes cluster as a location to run the test.
- Ensured that you are assigned a role as a *Member* or *Project Creator* in the team space. See Managing members and their roles in a team space on page 720.
- Ensured that you are assigned a role as a *Project Owner* or *Tester* in the project. See Managing access to server projects on page 734.
- 1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

- 2. Open the project that contains the test assets, and then click Execution.
- 3. Select the branch of the repository that contains the test assets.

The test assets that are contained in the selected branch of the repository are displayed in the following tabs on the **Execution** page:

Tab	Description
SUITES	Lists all suites, compound tests, JMeter tests, JUnit tests, Postman tests, Rate Sched- ules, or VU Schedules that are in the selected branch of the repository.

Tab	Description	
TESTS	Lists all API tests, functional tests, or performance tests that are in the selected branch of the repository.	
ADVANCED	Lists all assets that are displayed when custom filters are applied for assets in the se lected branch of the repository.	

4. Select the tab based on the type of test assets that you want to run as indicated in the following table:

If	Then
You want to run AFT Suites, API Suites, Compound Tests, JMeter tests, JUnit tests, Postman tests, Rate Schedules, or VU Schedules,.	Click the SUITES tab.
You want to run API tests, functional tests, or perfor- mance tests.	Click the TESTS tab.
You want to find Suites and tests by using custom fil- ters, and then run Suites and tests.	Click the ADVANCED tab.

The test assets in the selected tab are displayed.

- 5. Identify the test asset that you want to run by performing any of the following actions:
 - Scroll through the list.

i

1

Tip: You can hover over the icon in the Type column to know the type of the test asset.

Note: You can also identify the type of the asset from the icon that represents the test type as shown in the following table:

lcon	Represents	Listed in the SUITES tab	Listed in the TESTS tab	Listed in the AD- VANCED tab
43	API test		0	0
•	Functional test		0	0
٢	Performance test		Ø	0

lcon	Represents	Listed in the SUITES tab	Listed in the TESTS tab	Listed in the AD- VANCED tab
-	AFT Suite	0		0
ŧ	API Suite	0		0
0 () ()	Compound Test	0		0
0	HCL AppScan CodeSweep	0		0
/jMeter"	JMeter Test	0		0
Ju	JUnit Test	0		0
۲	Postman test	0		0
0	Rate Schedule	0		0
8	VU Schedule	0		0

• Search for the test asset by entering any text contained in the test asset name in the Search field.

• Click the **Filter** icon **W** in the **SUITES** or **TESTS** tab to filter the displayed assets based on the asset type.

For example, select **API Suite** in the **SUITES** tab to display all API Suites or select **Functional Test** in the **TESTS** tab to display all functional tests that are in the selected branch of the repository.

- Click the **Filter** icon **T** in the **ADVANCED** tab, and then create a filter query by using the **New filter** option by performing the following steps:
 - a. Click New filter.
 - b. Enter a name for the filter.
 - c. Select an operator, and add a rule or a group of rules.
 - d. Add or enter the relevant parameters and either select or enter the condition and the criteria for the condition.

You can select a parameter from the following list:

- Type
- Test Asset Name

- Test Asset Path
- Last Result
- Next Run
- Components
- e. Save the filter query to save and apply the filter query to filter the assets based on the query.

The test assets that match the filter criteria are displayed.

• Retrieve and apply a saved filter query, if you have saved filter queries previously by performing the following steps:

Note: The filter query applied previously is selected and the assets based on that filter query are displayed. To apply a different filter query, you must have created and saved the filter query.

a. Click the **Filter** icon \mathbf{M} in the **ADVANCED** tab.

The filter queries that you created and saved are displayed.

b. Click the filter that you want to apply.

The test assets that match the filter criteria are displayed.

You have identified the test asset that you want to run.

Clicking the test name displays the **Details** panel. You can view the details of the test such as the description, the branch in the repository that contains the asset, the Git details, and the details of the commits to the repository. You can also view the history of the test runs for the specific test under the **History** tab of the **Details** panel.

6. Click the **Execute** icon 🕑 in the row of the identified test asset.

The Execute test asset dialog is displayed.

Notes:

- If you have configured some or all of the settings for the current test run, and you do not want to continue with those settings, you can reset the settings by clicking **Reset**.
- If you want to repeat a test run and do not want to use the saved settings from a previous run, you can reset all the saved settings to their default values by clicking **Reset**.

7. Select the version of the test resources that you want to run by completing any of the following actions:

- **Note:** The test resources in the version can contain the test assets, datasets, AFT XML files, API environment tags, and other resources specific to projects created from any of the desktop clients.
 - Expand the list in the Version field, find the version of the test resources, and then select the version.

Use the following details about the version of the test resources that are displayed to identify the version that you want:

- Commit message.
- Tags labeled by the user for the version committed.
- The user who committed the version to the repository.
- Relative time of the commit. For example, 2 hours ago or 3 days ago.

The list displays the versions of the test resources committed by all users to the branch in the repository. The versions are arranged with the latest version that is committed, and then followed by the versions committed previously.

• Expand the list in the **Version** field, and then search for the version that you want to select by entering a partial or the complete commit message of that version.

The version that matches the search criteria is displayed and it is selected for the test run.

The default value for the version selected for the run is the latest version in the selected branch of the repository. If you do not select any version, then the latest version is selected for the test run.

Notes:

- If you selected a version but you do not want to use that version in the test run, you can remove the selected version by clicking the x icon. As a result, the default version is selected for the test run.
- If you repeated a test or ran the test again from the **Results** page, then the version of the test resources that you chose for the earlier run is shown as selected. You can either retain this version or select any other version from the list. You can also remove the previous version by clicking the x icon.
- 8. Select the time for scheduling the test run from the following options:
 - No action is required if you want to initiate the test run immediately after you click Execute.

Important: Click Execute only after you have configured the other settings in this dialog.



Note: The default time for scheduling a run is Now.

- Select Later and configure the date and time to schedule a test run.
- Select Recurring and perform the following steps to configure recurring test runs:

- a. Click the **Calendar** icon to under **Start**, and then select the date and time at which the test run must start.
- b. Set the frequency at which the test runs must run by entering the number in the **Repeat every** field, and then select the period from the list.

For example, if you want the test run to be run every 2 hours, enter 120, and then select the **Minute(s)** option.

- c. Set the option to end the recurring test runs from the following options:
 - Select the Never option, if you do not want the recurring test runs to end.
 - Select the **On** option, and then click the **Calendar** icon ^(C). You can select the date and time after which the scheduled test runs do not run.
- 9. Enter a label for the test run that helps you to identify the test on the Results page.

After the test run completes, the label that you entered is displayed for the test under the **Labels** column on the **Results** page. After you have created a label, any member of the project can use that label.

The default value for the Label field is null or an empty field.

Important: The configuration that you set for the test run in the Execute test asset dialog is preserved when you run the same test again. Those changes are not visible when another user logs in to HCL OneTest[™] Server. For example, if you created new variables on the server, those variables are available only for you when the same test is run again.

If you want to run the test immediately or at the scheduled time, click Execute, or continue with the next step.

10. Click Advanced to make the following advanced configurations:

a. Enter any JVM arguments that must be passed to the test run at run time in the **JVM Arguments** field, if applicable for the test.

For example, you can set a maximum Java heap size.

b. Enter program arguments that must be passed to the test run at run time in the **Program Arguments**, if applicable for the test.

If the test that you want to configure supports the presentation of the test results data in different formats, then do the required tasks in the following scenarios:

If	Then
You want the test results data in different supported formats.	Enter -history cisterna in the Program Argu- ments field.

lf	Then
You want to obtain the test results as a Jaeger trace.	Enter -history jaeger in the Program Arguments field.
You want the report as a test log and as a Jaeger trace.	Enter -history jaeger, testlog in the Program Ar- guments field.
Jaeger is already set as a program argument and you want to remove the Jaeger trace for your test.	Delete the -history jaeger entry in the Program Arguments field.



Note: The default report format is the test log format for the test reports.

c. Enter the environment variables that must be passed to the test run at run time in the **Environment Variables** field, if applicable for the test.

For example, enter the environment variables when the third-party libraries that are used in the test run refer to the environment variables for configuration.

Note: You must separate the arguments or variables with a white space when you enter them in the same line or start each argument or variable on a new line.

The default value for each of the fields for the advanced settings is null or an empty field.

If you want to run the test immediately or at the scheduled time, click Execute, or continue with the next step.

- 11. Follow the instructions if you are running a test asset that contains datasets:
 - a. Click the DATA SOURCES tab, if it is not already open.
 - b. Consider the following information about datasets before you select a dataset:

The default value for the datasets in the **DATA SOURCES** tab is null if the test asset did not have an associated dataset. If the asset had an associated dataset, the default value is the associated dataset.

You can utilize the dataset stored as an Excel or CSV file to override the original dataset associated with the Suite, test, or schedule. For example, when you have associated a dataset in .xlsx, .xls, or .csv format with the test or schedule in desktop clients and if you have another set of data stored in an Excel or CSV file, then you can select that dataset from the **Override** list.

- **Remember:** You must have uploaded the dataset as an Excel or CSV file into the Git repository, and ensured that both the original dataset (from the test asset) and new datasets (added to the project) have the same column names.
- c. Select the dataset that you want to use in the test run from any of the following options:
 - Select the dataset that is displayed as the default dataset when the test asset contains a single dataset.

Note: If there is only one dataset in the test asset, then that dataset is displayed as the default dataset.

Select the dataset from the list.

Note: If there are multiple datasets in the test asset, the datasets are listed in their increasing alphabetical order.

• Select the dataset from the **Override** list to override the dataset that was associated with the test in the desktop client.

Important: If the test contains an encrypted dataset, the Project Owner must classify it in the DATA SECURITY tab on the Project page before you can select it. You must have added datasets to your project from the Dataset page for the datasets to be displayed in the Override list.

If you want to run the test immediately or at the scheduled time, click Execute, or continue with the next step.

12. Follow the instructions in this step if the test requires a variable that must be passed to the test at the test run time.

You must configure the supported browser by using a variable if the test has a browser configured, which is different from the one that is supported by HCL OneTest™ Server.

- a. Click the VARIABLES tab, if it is not already open.
- b. Choose one of the following methods to add the variables:
 - To add new variables manually, click the **Add Variable** icon (①), enter the name, and value of the variable.
 - i. Enter RTW_WebUI_Browser_Selection as the name.
 - ii. Enter Firefox as the value, if you want to use Firefox as the browser and override the browser that is specified in the HTML test.

• To add new variables from your local computer or from the Git repository that is associated

with your server project, click the **Upload** icon and select the **Upload from local system** or **Browse from server** to select the variable file.



Note: You must have created a file with the variables before you can select the file.

The default value for the variables is null or an empty field.

If you want to run the test immediately or at the scheduled time, click **Execute**, or continue with the next step.

- 13. Follow the instructions if you want to change the location of a Kubernetes cluster for running the test:
 - a. Click the LOCATION tab, if it is not already open.

The **Default Cluster** is the default location where the test runs, and it is listed under the **Host** column. The information about the availability of the default location is displayed.

Important: You must have added the following remote hosts to your project that are then displayed under the **Override** column:

- Docker hosts that are registered with HCL OneTest[™] Server.
- Kubernetes clusters that are registered with a team space.

Notes:

- If the remote Docker hosts or clusters are not added to your project, the option No
 override options is displayed as the default value and the test runs in the Kubernetes
 cluster of HCL OneTest[™] Server.
- If remote Docker hosts or clusters are added to your project, the added Docker hosts or clusters are displayed along with their availability status and ownership information.
- b. Select the location where you want to run the test asset from the following options:
 - Select the **Default Cluster** when no remote Docker hosts or clusters are available in your project.
 - Select the remote Docker host or cluster from the list when a remote Docker host or cluster is available in your project.
 - Select No override options, if you selected any remote Docker host or cluster and want to revert to the Default Cluster to run the test asset.
- c. Click Execute.

The test run is initiated.

Results

You have configured and either started or scheduled a test run of a Compound Test that contains Functional HTML tests.

What to do next

You can choose to perform any of the following tasks after you have initiated or scheduled a run:

- Stop the test run at any point after the test run is initiated from the **Execution** page. See Stopping test runs on page 462.
- Cancel a scheduled test run from the Execution page. See Canceling scheduled test runs on page 465.
- View all the states of the test asset by clicking the **Show in the Progress page** icon C for the test asset for which you started or scheduled the run. See Viewing the state of test assets on page 453.
- View the progress of the test from the **Progress** page. See Viewing the progress of running test assets on page 457.
- View the results, reports, and logs of the test from the **Results** page after the test completes the run. See Test results on page 513.

Related information

Resetting the configuration settings for a test run on page 461

Test run configurations on page 327

Configuring a run of a Compound Test that contains Web UI tests or a Functional Web UI test

After you added the test resources that you created in the desktop client to the project, you can configure a Compound Test that contains Web UI tests or a Functional Web UI test to be run on HCL OneTest[™] Server or a remote Kubernetes cluster.

Before you begin

You must have completed the following tasks:

- Read and completed the tasks mentioned in Prerequisites to running tests on page 277, if they apply to the test that you want to configure for a run.
- Read and completed the tasks mentioned in Test run considerations for running tests on remote performance agents on page 289, if you want to use a remote agent as the location to run the test.
- Read and completed the tasks mentioned in Considerations for using a remote Kubernetes cluster on page 313, if you want to use a remote Kubernetes cluster as a location to run the test.
- Created a Compound test that contains Web UI tests or a Functional Web UI test in HCL OneTest[™] UI and added the test asset to the project repository on HCL OneTest[™] Server.

- Ensured that you are assigned a role as a *Member* or *Project Creator* in the team space. See Managing members and their roles in a team space on page 720.
- Ensured that you are assigned a role as a *Project Owner* or *Tester* in the project. See Managing access to server projects on page 734.
- 1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

- 2. Open the project that contains the test assets, and then click **Execution**.
- 3. Select the branch of the repository that contains the test assets.

The test assets that are contained in the selected branch of the repository are displayed in the following tabs on the **Execution** page:

Tab	Description
SUITES	Lists all suites, compound tests, JMeter tests, JUnit tests, Postman tests, Rate Sched- ules, or VU Schedules that are in the selected branch of the repository.
TESTS	Lists all API tests, functional tests, or performance tests that are in the selected branch of the repository.
ADVANCED	Lists all assets that are displayed when custom filters are applied for assets in the se- lected branch of the repository.

4. Select the tab based on the type of test assets that you want to run as indicated in the following table:

If	Then
You want to run AFT Suites, API Suites, Compound Tests, JMeter tests, JUnit tests, Postman tests, Rate Schedules, or VU Schedules,.	Click the SUITES tab.
You want to run API tests, functional tests, or perfor- mance tests.	Click the TESTS tab.
You want to find Suites and tests by using custom fil- ters, and then run Suites and tests.	Click the ADVANCED tab.

The test assets in the selected tab are displayed.

5. Identify the test asset that you want to run by performing any of the following actions:

• Scroll through the list.

i ·

Tip: You can hover over the icon in the Type column to know the type of the test asset.

Note: You can also identify the type of the asset from the icon that represents the test type as shown in the following table:

lcon	Represents	Listed in the SUITES tab	Listed in the TESTS tab	Listed in the AD- VANCED tab
-6.3-	API test		0	0
۲	Functional test		0	0
٨	Performance test		0	0
	AFT Suite	0		0
•	API Suite	0		0
0 4	Compound Test	0		0
0	HCL AppScan CodeSweep	0		0
/jMeter"	JMeter Test	0		0
Ju	JUnit Test	0		0
0	Postman test	0		0
9	Rate Schedule	0		0
9	VU Schedule	0		0

• Search for the test asset by entering any text contained in the test asset name in the Search field.

• Click the **Filter** icon **T** in the **SUITES** or **TESTS** tab to filter the displayed assets based on the asset type.

For example, select **API Suite** in the **SUITES** tab to display all API Suites or select **Functional Test** in the **TESTS** tab to display all functional tests that are in the selected branch of the repository.

- Click the **Filter** icon **W** in the **ADVANCED** tab, and then create a filter query by using the **New filter** option by performing the following steps:
 - a. Click New filter.
 - b. Enter a name for the filter.
 - c. Select an operator, and add a rule or a group of rules.
 - d. Add or enter the relevant parameters and either select or enter the condition and the criteria for the condition.

You can select a parameter from the following list:

- Type
- Test Asset Name
- Test Asset Path
- Last Result
- Next Run
- Components
- e. Save the filter query to save and apply the filter query to filter the assets based on the query.

The test assets that match the filter criteria are displayed.

 Retrieve and apply a saved filter query, if you have saved filter queries previously by performing the following steps:

Note: The filter query applied previously is selected and the assets based on that filter query are displayed. To apply a different filter query, you must have created and saved the filter query.

a. Click the **Filter** icon \mathbf{M} in the **ADVANCED** tab.

The filter queries that you created and saved are displayed.

b. Click the filter that you want to apply.

The test assets that match the filter criteria are displayed.

You have identified the test asset that you want to run.

Clicking the test name displays the **Details** panel. You can view the details of the test such as the description, the branch in the repository that contains the asset, the Git details, and the details of the commits to the repository. You can also view the history of the test runs for the specific test under the **History** tab of the **Details** panel.

Click the Execute icon in the row of the identified test asset.

The Execute test asset dialog is displayed.



- If you have configured some or all of the settings for the current test run, and you do not want to continue with those settings, you can reset the settings by clicking **Reset**.
- If you want to repeat a test run and do not want to use the saved settings from a previous run, you can reset all the saved settings to their default values by clicking Reset.
- 7. Select the version of the test resources that you want to run by completing any of the following actions:

Note: The test resources in the version can contain the test assets, datasets, AFT XML files, API environment tags, and other resources specific to projects created from any of the desktop clients.

• Expand the list in the Version field, find the version of the test resources, and then select the version.

Use the following details about the version of the test resources that are displayed to identify the version that you want:

- Commit message.
- Tags labeled by the user for the version committed.
- The user who committed the version to the repository.
- Relative time of the commit. For example, 2 hours ago or 3 days ago.

The list displays the versions of the test resources committed by all users to the branch in the repository. The versions are arranged with the latest version that is committed, and then followed by the versions committed previously.

• Expand the list in the **Version** field, and then search for the version that you want to select by entering a partial or the complete commit message of that version.

The version that matches the search criteria is displayed and it is selected for the test run.

The default value for the version selected for the run is the latest version in the selected branch of the repository. If you do not select any version, then the latest version is selected for the test run.



367

Ż

- If you selected a version but you do not want to use that version in the test run, you can remove the selected version by clicking the x icon. As a result, the default version is selected for the test run.
- If you repeated a test or ran the test again from the **Results** page, then the version of the test resources that you chose for the earlier run is shown as selected. You can either retain this version or select any other version from the list. You can also remove the previous version by clicking the **x** icon.
- 8. Select the time for scheduling the test run from the following options:
 - No action is required if you want to initiate the test run immediately after you click Execute.



Important: Click Execute only after you have configured the other settings in this dialog.



Note: The default time for scheduling a run is Now.

- Select Later and configure the date and time to schedule a test run.
- Select Recurring and perform the following steps to configure recurring test runs:
 - a. Click the **Calendar** icon 📛 under **Start**, and then select the date and time at which the test run must start.
 - b. Set the frequency at which the test runs must run by entering the number in the **Repeat every** field, and then select the period from the list.

For example, if you want the test run to be run every 2 hours, enter 120, and then select the **Minute(s)** option.

- c. Set the option to end the recurring test runs from the following options:
 - Select the Never option, if you do not want the recurring test runs to end.
 - Select the **On** option, and then click the **Calendar** icon \square . You can select the date and time after which the scheduled test runs do not run.
- 9. Enter a label for the test run that helps you to identify the test on the **Results** page.

After the test run completes, the label that you entered is displayed for the test under the **Labels** column on the **Results** page. After you have created a label, any member of the project can use that label.

The default value for the Label field is null or an empty field.

Important: The configuration that you set for the test run in the Execute test asset dialog is preserved when you run the same test again. Those changes are not visible when another user logs in to HCL OneTest[™] Server. For example, if you created new variables on the server, those variables are available only for you when the same test is run again.

If you want to run the test immediately or at the scheduled time, click **Execute**, or continue with the next step.

- 10. Click Advanced to make the following advanced configurations:
 - a. Enter any JVM arguments that must be passed to the test run at run time in the **JVM Arguments** field, if applicable for the test.

For example, you can set a maximum Java heap size.

b. Enter program arguments that must be passed to the test run at run time in the **Program Arguments**, if applicable for the test.

If the test that you want to configure supports the presentation of the test results data in different formats, then do the required tasks in the following scenarios:

If	Then
You want the test results data in different supported formats.	Enter -history cisterna in the Program Argu- ments field.
You want to obtain the test results as a Jaeger trace.	Enter -history jaeger in the Program Arguments field.
You want the report as a test log and as a Jaeger trace.	Enter -history jaeger, testlog in the Program Ar- guments field.
Jaeger is already set as a program argument and you want to remove the Jaeger trace for your test.	Delete the -history jaeger entry in the Program Arguments field.

Note: The default report format is the test log format for the test reports.

c. Enter the environment variables that must be passed to the test run at run time in the **Environment Variables** field, if applicable for the test.

For example, enter the environment variables when the third-party libraries that are used in the test run refer to the environment variables for configuration.

Note: You must separate the arguments or variables with a white space when you enter them in the same line or start each argument or variable on a new line.

The default value for each of the fields for the advanced settings is null or an empty field.

If you want to run the test immediately or at the scheduled time, click **Execute**, or continue with the next step.

- 11. Follow the instructions if you are running a test asset that contains datasets:
 - a. Click the DATA SOURCES tab, if it is not already open.
 - b. Consider the following information about datasets before you select a dataset:

The default value for the datasets in the **DATA SOURCES** tab is null if the test asset did not have an associated dataset. If the asset had an associated dataset, the default value is the associated dataset.

You can utilize the dataset stored as an Excel or CSV file to override the original dataset associated with the Suite, test, or schedule. For example, when you have associated a dataset in .xlsx, .xls, or .csv format with the test or schedule in desktop clients and if you have another set of data stored in an Excel or CSV file, then you can select that dataset from the **Override** list.

Remember: You must have uploaded the dataset as an Excel or CSV file into the Git repository, and ensured that both the original dataset (from the test asset) and new datasets (added to the project) have the same column names.

- c. Select the dataset that you want to use in the test run from any of the following options:
 - Select the dataset that is displayed as the default dataset when the test asset contains a single dataset.

Note: If there is only one dataset in the test asset, then that dataset is displayed as the default dataset.

- · Select the dataset from the list.
 - **Note:** If there are multiple datasets in the test asset, the datasets are listed in their increasing alphabetical order.
- Select the dataset from the **Override** list to override the dataset that was associated with the test in the desktop client.

Important: If the test contains an encrypted dataset, the Project Owner must classify it in the DATA SECURITY tab on the Project page before you can select it. You must have added datasets to your project from the Dataset page for the datasets to be displayed in the Override list.

If you want to run the test immediately or at the scheduled time, click **Execute**, or continue with the next step.

12. Follow the instructions in this step if the test requires a variable that must be passed to the test at the test run time.

You must configure the supported browser by using a variable if the test has a browser configured, which is different from the one that is supported by HCL OneTest[™] Server.

- a. Click the VARIABLES tab, if it is not already open.
- b. Choose one of the following methods to add the variables:
 - To add new variables manually, click the **Add Variable** icon (+), enter the name, and value of the variable.
 - i. Enter RTW_WebUI_Browser_Selection as the name.
 - ii. Enter Firefox as the value, if you want to use Firefox as the browser and override the browser that is specified in the Web UI test.
 - To add new variables from your local computer or from the Git repository that is associated

with your server project, click the **Upload** icon and select the **Upload from local system** or **Browse from server** to select the variable file.

Note: You must have created a file with the variables before you can select the file.

The default value for the variables is null or an empty field.

If you want to run the test immediately or at the scheduled time, click **Execute**, or continue with the next step.

- 13. Select any of the following steps that depends on the location to run the test:
 - If you want to run the tests on the remote agents, go to Step 14 on page 371.
 - If you want to run the tests on a Kubernetes cluster, go to Step 15 on page 372.
- 14. Follow the instructions if you want to run a compound test on the remote agent that is connected either to the default Kubernetes cluster or the remote Kubernetes cluster:
 - a. Click the LOCATION tab, if it is not already open.

The static agents that are configured in the test asset are listed under the **Host** column. The information about the availability and capabilities of the agent are displayed.



Note: You must have added agents to your project from the **Infrastructure** page for the agents to be displayed under the **Override** column.

The default value for the agents is null or an empty field if no agents were configured in the test asset. If the test asset contains agents that are configured, then the default agent is the first item to be displayed on the list of agents listed in the increasing alphabetical order.

b. Select the agent where you want to run the test asset in the following scenarios:

lf	Then	Action
The agent that is specified in the test assets is available and no other agents are added to the project.	The agent that is specified in the test assets is displayed in the Override column.	Select the agent in the Host that is also displayed in the Override column as the location to run the test.
The agent that is specified in the test assets is not available and no other agents are added to the project.	There is no agent displayed for override in the Override column.	You cannot run the test on the agent. You must wait until the agent is available to run the test on the agent.
The agent that is specified in the test assets is available and there are other agents that are added to the project.	Agents that have capabilities that match with the agent capa- bilities specified in the test as- sets are listed in the Override column as follows: • Agents with capabilities that best match the ca- pabilities in the agent in the asset are at the top of the list. • Agents with capabilities that do not match with the capabilities in the agent in the asset are listed subsequently. You can find details of both agents for the matching capa- bilities when you hover over the agent in the Override column.	 Perform any of the following actions: Select the agent in the Host that is also displayed in the Override column as the location to run the test. Select an agent in the Override column as the location to run the test.

c. Click Execute.

15. Follow the instructions if you want to change the location of a Kubernetes cluster for running the test:

a. Click the **LOCATION** tab, if it is not already open.

The **Default Cluster** is the default location where the test runs, and it is listed under the **Host** column. The information about the availability of the default location is displayed. Important: You must have added the following remote hosts to your project that are then displayed under the **Override** column:

- Docker hosts that are registered with HCL OneTest[™] Server.
- Kubernetes clusters that are registered with a team space.

Notes:

- If the remote Docker hosts or clusters are not added to your project, the option No
 override options is displayed as the default value and the test runs in the Kubernetes
 cluster of HCL OneTest[™] Server.
- If remote Docker hosts or clusters are added to your project, the added Docker hosts or clusters are displayed along with their availability status and ownership information.

b. Select the location where you want to run the test asset from the following options:

- Select the **Default Cluster** when no remote Docker hosts or clusters are available in your project.
- Select the remote Docker host or cluster from the list when a remote Docker host or cluster is available in your project.
- Select No override options, if you selected any remote Docker host or cluster and want to revert to the Default Cluster to run the test asset.

c. Click Execute.

The test run is initiated.

Results

You have configured and either started or scheduled a test run of a Compound Test that contains Web UI tests or a Functional Web UI test.

What to do next

You can choose to perform any of the following tasks after you have initiated or scheduled a run:

- Stop the test run at any point after the test run is initiated from the **Execution** page. See Stopping test runs on page 462.
- Cancel a scheduled test run from the **Execution** page. See Canceling scheduled test runs on page 465.
- View all the states of the test asset by clicking the **Show in the Progress page** icon C for the test asset for which you started or scheduled the run. See Viewing the state of test assets on page 453.
- View the progress of the test from the **Progress** page. See Viewing the progress of running test assets on page 457.
- View the results, reports, and logs of the test from the **Results** page after the test completes the run. See Test results on page 513.

Related information

Resetting the configuration settings for a test run on page 461

Test run configurations on page 327

Configuring a run of a Compound Test that contains mobile tests or a Functional Mobile test

After you added the test resources that you created in the desktop client to the project, you can configure a Compound Test that contains mobile tests or a Functional mobile test to be run on HCL OneTest[™] Server or a remote Kubernetes cluster.

Before you begin

You must have completed the following tasks:

- Created a Compound Test or a Functional test that contains the mobile tests in HCL OneTest[™] UI and added the test asset to the project repository on HCL OneTest[™] Server.
- Created a variable file if you want to import the variables file. The file must contain the details of the UI Test agent or the device cloud to which the mobile device is connected.
- Read Considerations for using Jaeger traces in reports on page 283, if you want to configure a run and you want Jaeger to report the test results for the test.
- Read and completed the tasks mentioned in Test run considerations for running tests on remote performance agents on page 289, if you want to use a remote agent as the location to run the test.
- Read and completed the tasks mentioned in Considerations for using a remote Kubernetes cluster on page 313, if you want to use a remote Kubernetes cluster as a location to run the test.
- Ensured that you are assigned a role as a *Member* or *Project Creator* in the team space. See Managing members and their roles in a team space on page 720.
- Ensured that you are assigned a role as a *Project Owner* or *Tester* in the project. See Managing access to server projects on page 734.

About this task

You can run the mobile tests that are contained in a Compound Test or a Functional test after you create the tests in HCL OneTest[™] UI, and then add them to your project on HCL OneTest[™] Server. You can then run the mobile tests on the mobile devices that are connected to any of the following agents or clouds:

- Remote UI Test agents. Requires the variables at test run time as specified in Table 6: Variables for the UI Test agent on page 375.
- The BitBar cloud. Requires the variables at test run time as specified in Table 7: Variables for the BitBar cloud on page 375.

- The Perfecto mobile cloud. Requires the variables at test run time as specified in Table 8: Variables for the Perfecto mobile cloud on page 376.
- The pCloudy mobile cloud. Requires the variables at test run time as specified in Table 9: Variables for the pCloudy mobile cloud on page 376.

You must provide the details of the UI Test agent or the mobile cloud to which the mobile devices are connected as variables in Step 12 on page 383. You can either enter the variables or use the file in which you entered the variables. You must refer to the following tables for the variables that are required for a successful run:

Table 6. Variables for the UI Test agent

Name of the Variable	Action for the Value field	
Mobile_Device_Selection	Specify the name of the mobile device that is connected to the UI Test agent.	
appium.server.host	Specify the host name or IP address of the UI Test agent.	
appium.server.port	Specify the port on the UI Test agent that is configured to communicate with HCL OneTest™ Server.	

Table 7	Variables	for the	BitBar	cloud
Table 7.	variables	ior uie	Ditbai	ciouu

Name of the Variable	Value	
Mobile_Device_Selection	Specify the name of the mobile device that is connected to the BitBar cloud.	
bitbar.apikey	Specify the user token generated for your BitBar account to authenticate your connection with the BitBar cloud.	
bitbar.host	Specify the host name of the BitBar cloud instance.	
bitbar.project	Specify the name of the project that contains the recorded test.	
bitbar.testrun	Specify a name for the test run that must be displayed in the BitBar dashboard for the test run.	

Table 8. Variables for the Perfecto mobile cloud

Name of the Variable	Value
Mobile_Device_Selection	Specify the name of the mobile device that is connected to the Perfecto mobile cloud.
perfecto.securitytoken	Specify the user token generated for your Perfecto ac- count to authenticate your connection with the Perfecto mobile cloud.
perfecto.host	Specify the host name of the Perfecto mobile cloud in- stance.

Table 9. Variables for the pCloudy mobile cloud

Name of the Variable	Value	
Mobile_Device_Selection	Specify the name of the mobile device that is connected to the pCloudy mobile cloud.	
pcloudy.apikey	Specify the API key that is generated for your pCloudy account to authenticate your connection with the pCloudy mobile cloud.	
pcloudy.username	Specify your user name with which you can access the pCloudy mobile cloud instance.	
pcloudy.host	Specify the host name of the pCloudy mobile cloud in- stance.	

1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

- 2. Open the project that contains the test assets, and then click Execution.
- 3. Select the branch of the repository that contains the test assets.

The test assets that are contained in the selected branch of the repository are displayed in the following tabs on the **Execution** page:

Tab	Description
SUITES	Lists all suites, compound tests, JMeter tests, JUnit tests, Postman tests, Rate Sched- ules, or VU Schedules that are in the selected branch of the repository.
TESTS	Lists all API tests, functional tests, or performance tests that are in the selected branch of the repository.
ADVANCED	Lists all assets that are displayed when custom filters are applied for assets in the se- lected branch of the repository.

4. Select the tab based on the type of test assets that you want to run as indicated in the following table:

If	Then
You want to run AFT Suites, API Suites, Compound Tests, JMeter tests, JUnit tests, Postman tests, Rate Schedules, or VU Schedules,.	Click the SUITES tab.
You want to run API tests, functional tests, or perfor- mance tests.	Click the TESTS tab.
You want to find Suites and tests by using custom fil- ters, and then run Suites and tests.	Click the ADVANCED tab.

The test assets in the selected tab are displayed.

- 5. Identify the test asset that you want to run by performing any of the following actions:
 - Scroll through the list.

Tip: You can hover over the icon in the **Type** column to know the type of the test asset.



i

Note: You can also identify the type of the asset from the icon that represents the test type as shown in the following table:

lcon	Represents	Listed in the SUITES tab	Listed in the TESTS tab	Listed in the AD- VANCED tab
-63-	API test		0	0
۲	Functional test		0	0

1

lcon	Represents	Listed in the SUITES tab	Listed in the TESTS tab	Listed in the AD- VANCED tab
٢	Performance test		0	0
	AFT Suite	0		0
43	API Suite	0		0
6 1	Compound Test	0		0
0	HCL AppScan CodeSweep	0		0
/ JMeter	JMeter Test	0		0
Ju	JUnit Test	0		0
0	Postman test	0		0
9	Rate Schedule	0		0
8	VU Schedule	0		0

- Search for the test asset by entering any text contained in the test asset name in the Search field.
- Click the **Filter** icon **Y** in the **SUITES** or **TESTS** tab to filter the displayed assets based on the asset type.

For example, select **API Suite** in the **SUITES** tab to display all API Suites or select **Functional Test** in the **TESTS** tab to display all functional tests that are in the selected branch of the repository.

- Click the **Filter** icon **W** in the **ADVANCED** tab, and then create a filter query by using the **New filter** option by performing the following steps:
 - a. Click New filter.
 - b. Enter a name for the filter.
 - c. Select an operator, and add a rule or a group of rules.
 - d. Add or enter the relevant parameters and either select or enter the condition and the criteria for the condition.

You can select a parameter from the following list:

- Type
- Test Asset Name
- Test Asset Path
- Last Result
- Next Run
- Components
- e. Save the filter query to save and apply the filter query to filter the assets based on the query.

The test assets that match the filter criteria are displayed.

 Retrieve and apply a saved filter query, if you have saved filter queries previously by performing the following steps:

Note: The filter query applied previously is selected and the assets based on that filter query are displayed. To apply a different filter query, you must have created and saved the filter query.

a. Click the **Filter** icon \mathbf{M} in the **ADVANCED** tab.

The filter queries that you created and saved are displayed.

b. Click the filter that you want to apply.

The test assets that match the filter criteria are displayed.

You have identified the test asset that you want to run.

Clicking the test name displays the **Details** panel. You can view the details of the test such as the description, the branch in the repository that contains the asset, the Git details, and the details of the commits to the repository. You can also view the history of the test runs for the specific test under the **History** tab of the **Details** panel.

6. Click the **Execute** icon 🕑 in the row of the identified test asset.

The Execute test asset dialog is displayed.

Notes:

- If you have configured some or all of the settings for the current test run, and you do not want to continue with those settings, you can reset the settings by clicking **Reset**.
- If you want to repeat a test run and do not want to use the saved settings from a previous run, you can reset all the saved settings to their default values by clicking **Reset**.

7. Select the version of the test resources that you want to run by completing any of the following actions:

- **Note:** The test resources in the version can contain the test assets, datasets, AFT XML files, API environment tags, and other resources specific to projects created from any of the desktop clients.
 - Expand the list in the Version field, find the version of the test resources, and then select the version.

Use the following details about the version of the test resources that are displayed to identify the version that you want:

- Commit message.
- Tags labeled by the user for the version committed.
- The user who committed the version to the repository.
- Relative time of the commit. For example, 2 hours ago or 3 days ago.

The list displays the versions of the test resources committed by all users to the branch in the repository. The versions are arranged with the latest version that is committed, and then followed by the versions committed previously.

• Expand the list in the **Version** field, and then search for the version that you want to select by entering a partial or the complete commit message of that version.

The version that matches the search criteria is displayed and it is selected for the test run.

The default value for the version selected for the run is the latest version in the selected branch of the repository. If you do not select any version, then the latest version is selected for the test run.

Notes:

- If you selected a version but you do not want to use that version in the test run, you can remove the selected version by clicking the x icon. As a result, the default version is selected for the test run.
- If you repeated a test or ran the test again from the **Results** page, then the version of the test resources that you chose for the earlier run is shown as selected. You can either retain this version or select any other version from the list. You can also remove the previous version by clicking the x icon.
- 8. Select the time for scheduling the test run from the following options:
 - No action is required if you want to initiate the test run immediately after you click Execute.

Important: Click Execute only after you have configured the other settings in this dialog.



Note: The default time for scheduling a run is Now.

- Select Later and configure the date and time to schedule a test run.
- Select Recurring and perform the following steps to configure recurring test runs:

- a. Click the **Calendar** icon to under **Start**, and then select the date and time at which the test run must start.
- b. Set the frequency at which the test runs must run by entering the number in the **Repeat every** field, and then select the period from the list.

For example, if you want the test run to be run every 2 hours, enter 120, and then select the **Minute(s)** option.

- c. Set the option to end the recurring test runs from the following options:
 - Select the Never option, if you do not want the recurring test runs to end.
 - Select the **On** option, and then click the **Calendar** icon ^(C). You can select the date and time after which the scheduled test runs do not run.
- 9. Enter a label for the test run that helps you to identify the test on the **Results** page.

After the test run completes, the label that you entered is displayed for the test under the **Labels** column on the **Results** page. After you have created a label, any member of the project can use that label.

The default value for the Label field is null or an empty field.

Important: The configuration that you set for the test run in the Execute test asset dialog is preserved when you run the same test again. Those changes are not visible when another user logs in to HCL OneTest[™] Server. For example, if you created new variables on the server, those variables are available only for you when the same test is run again.

If you want to run the test immediately or at the scheduled time, click **Execute**, or continue with the next step.

10. Click Advanced to make the following advanced configurations:

a. Enter any JVM arguments that must be passed to the test run at run time in the **JVM Arguments** field, if applicable for the test.

For example, you can set a maximum Java heap size.

b. Enter program arguments that must be passed to the test run at run time in the **Program Arguments**, if applicable for the test.

If the test that you want to configure supports the presentation of the test results data in different formats, then do the required tasks in the following scenarios:

If	Then
You want the test results data in different supported formats.	Enter -history cisterna in the Program Argu- ments field.

lf	Then
You want to obtain the test results as a Jaeger trace.	Enter -history jaeger in the Program Arguments field.
You want the report as a test log and as a Jaeger trace.	Enter -history jaeger, testlog in the Program Ar- guments field.
Jaeger is already set as a program argument and you want to remove the Jaeger trace for your test.	Delete the -history jaeger entry in the Program Arguments field.



Note: The default report format is the test log format for the test reports.

c. Enter the environment variables that must be passed to the test run at run time in the **Environment Variables** field, if applicable for the test.

For example, enter the environment variables when the third-party libraries that are used in the test run refer to the environment variables for configuration.

Note: You must separate the arguments or variables with a white space when you enter them in the same line or start each argument or variable on a new line.

The default value for each of the fields for the advanced settings is null or an empty field.

If you want to run the test immediately or at the scheduled time, click Execute, or continue with the next step.

- 11. Follow the instructions if you are running a test asset that contains datasets:
 - a. Click the DATA SOURCES tab, if it is not already open.
 - b. Consider the following information about datasets before you select a dataset:

The default value for the datasets in the **DATA SOURCES** tab is null if the test asset did not have an associated dataset. If the asset had an associated dataset, the default value is the associated dataset.

You can utilize the dataset stored as an Excel or CSV file to override the original dataset associated with the Suite, test, or schedule. For example, when you have associated a dataset in .xlsx, .xls, or .csv format with the test or schedule in desktop clients and if you have another set of data stored in an Excel or CSV file, then you can select that dataset from the **Override** list.

- **Remember:** You must have uploaded the dataset as an Excel or CSV file into the Git repository, and ensured that both the original dataset (from the test asset) and new datasets (added to the project) have the same column names.
- c. Select the dataset that you want to use in the test run from any of the following options:
 - Select the dataset that is displayed as the default dataset when the test asset contains a single dataset.

Note: If there is only one dataset in the test asset, then that dataset is displayed as the default dataset.

Select the dataset from the list.

Note: If there are multiple datasets in the test asset, the datasets are listed in their increasing alphabetical order.

• Select the dataset from the **Override** list to override the dataset that was associated with the test in the desktop client.

Important: If the test contains an encrypted dataset, the Project Owner must classify it in the DATA SECURITY tab on the Project page before you can select it. You must have added datasets to your project from the Dataset page for the datasets to be displayed in the Override list.

If you want to run the test immediately or at the scheduled time, click **Execute**, or continue with the next step.

- 12. Perform the following steps to provide the variables that specify the UI Test agent or cloud to which the mobile device is attached. You can either enter the variables that must be passed to the test at the test run time or import the file that contains the variables.
 - a. Click the VARIABLES tab, if it is not already open.
 - b. Choose one of the following methods to add the variables:

- To add new variables manually, click the **Add Variable** icon , enter the name, and value of the variable.
- To add new variables from your local computer or from the Git repository that is associated

with your server project, click the **Upload** icon and select the **Upload from local system** or **Browse from server** to select the variable file.



Note: You must have created a file with the variables before you can select the file.

- 13. Select any of the following steps that depends on the location to run the test:
 - If you want to run the tests on the remote agents, go to Step 14 on page 384.
 - If you want to run the tests on a Kubernetes cluster, go to Step 15 on page 385.
- 14. Follow the instructions if you want to run a test on the remote performance agent that is connected either to the default Kubernetes cluster or the remote Kubernetes cluster:
 - a. Click the LOCATION tab, if it is not already open.

The performance agents that are configured in the test asset are listed under the **Host** column. The information about the availability of the performance agent is displayed.

Note: You must have added performance agents to your project from the Agents and Intercepts page for the performance agents to be displayed under the **Override** column.

The default value for the performance agents is null or an empty field if no performance agents were configured in the test asset. If the test asset contains performance agents that are configured, then the default performance agent is the first item to be displayed on the list of performance agents listed in the increasing alphabetical order.

b. Select the performance agent where you want to run the test asset in the following scenarios:

lf	Then	Action
The agent that is specified in the test assets is available and no other agents are added to the project.	The agent that is specified in the test assets is displayed in the Override column.	Select the agent in the Host that is also displayed in the Override column as the location to run the test.
The agent that is specified in the test assets is not available and no other agents are added to the project.	There is no agent displayed for override in the Override column.	You cannot run the test on the agent. You must wait until the agent is available to run the test on the agent.

If	Then	Action
If The agent that is specified in the test assets is available and there are other agents that are added to the project.	Then Agents that have capabilities that match with the agent capa- bilities specified in the test as- sets are listed in the Override column as follows: • Agents with capabilities that best match the ca- pabilities in the agent in the asset are at the top	Action Perform any of the following ac- tions: • Select the agent in the Host that is also dis- played in the Override column as the location to run the test. • Select an agent in the Override column as the
	of the list. • Agents with capabilities that do not match with the capabilities in the agent in the asset are listed subsequently. You can find details of both agents for the matching capa- bilities when you hover over the agent in the Override column.	location to run the test.

c. Click Execute.

The test run is initiated.

- 15. Follow the instructions if you want to change the location of a Kubernetes cluster for running the test:
 - a. Click the **LOCATION** tab, if it is not already open.

The **Default Cluster** is the default location where the test runs, and it is listed under the **Host** column. The information about the availability of the default location is displayed.



Important: You must have added the following remote hosts to your project that are then displayed under the **Override** column:

- Docker hosts that are registered with HCL OneTest[™] Server.
- Kubernetes clusters that are registered with a team space.



- If the remote Docker hosts or clusters are not added to your project, the option No
 override options is displayed as the default value and the test runs in the Kubernetes
 cluster of HCL OneTest[™] Server.
 - If remote Docker hosts or clusters are added to your project, the added Docker hosts or clusters are displayed along with their availability status and ownership information.
- b. Select the location where you want to run the test asset from the following options:
 - Select the **Default Cluster** when no remote Docker hosts or clusters are available in your project.
 - Select the remote Docker host or cluster from the list when a remote Docker host or cluster is available in your project.
 - Select No override options, if you selected any remote Docker host or cluster and want to revert to the Default Cluster to run the test asset.
- c. Click Execute.

The test run is initiated.

Results

You have configured and either started or scheduled a test run of a Compound Test that contains mobile tests or a Functional mobile test.

What to do next

You can choose to perform any of the following tasks after you have initiated or scheduled a run:

- Stop the test run at any point after the test run is initiated from the **Execution** page. See Stopping test runs on page 462.
- Cancel a scheduled test run from the Execution page. See Canceling scheduled test runs on page 465.
- View all the states of the test asset by clicking the **Show in the Progress page** icon **C** for the test asset for which you started or scheduled the run. See Viewing the state of test assets on page 453.
- View the progress of the test from the **Progress** page. See Viewing the progress of running test assets on page 457.
- View the results, reports, and logs of the test from the **Results** page after the test completes the run. See Test results on page 513.

Related information

Resetting the configuration settings for a test run on page 461

Test run configurations on page 327

Configuring a run of a Functional Windows test

After you added the test resources that you created in the desktop client to the project, you can configure a Functional Windows test to be run on HCL OneTest[™] Server or a remote Kubernetes cluster.

Before you begin

You must have completed the following tasks:

- Created a Functional Windows test in HCL OneTest[™] UI and added the test asset to the project repository on HCL OneTest[™] Server.
- Read Considerations for using Jaeger traces in reports on page 283, if you want to configure a run and you want Jaeger to report the test results for the test.
- Read and completed the tasks mentioned in Test run considerations for running tests on remote performance agents on page 289, if you want to use a remote agent as the location to run the test.
- Read and completed the tasks mentioned in Considerations for using a remote Kubernetes cluster on page 313, if you want to use a remote Kubernetes cluster as a location to run the test.
- Ensured that you are assigned a role as a *Member* or *Project Creator* in the team space. See Managing members and their roles in a team space on page 720.
- Ensured that you are assigned a role as a *Project Owner* or *Tester* in the project. See Managing access to server projects on page 734.

About this task

You can run the Functional Windows tests after you create the tests in HCL OneTest[™] UI, and then add them to your project on HCL OneTest[™] Server.

1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

- 2. Open the project that contains the test assets, and then click Execution.
- 3. Select the branch of the repository that contains the test assets.

The test assets that are contained in the selected branch of the repository are displayed in the following tabs on the **Execution** page:

Tab	Description
SUITES	Lists all suites, compound tests, JMeter tests, JUnit tests, Postman tests, Rate Sched- ules, or VU Schedules that are in the selected branch of the repository.
TESTS	Lists all API tests, functional tests, or performance tests that are in the selected branch of the repository.
ADVANCED	Lists all assets that are displayed when custom filters are applied for assets in the se- lected branch of the repository.

4. Select the tab based on the type of test assets that you want to run as indicated in the following table:

If	Then
You want to run AFT Suites, API Suites, Compound Tests, JMeter tests, JUnit tests, Postman tests, Rate Schedules, or VU Schedules,.	Click the SUITES tab.
You want to run API tests, functional tests, or perfor- mance tests.	Click the TESTS tab.
You want to find Suites and tests by using custom fil- ters, and then run Suites and tests.	Click the ADVANCED tab.

The test assets in the selected tab are displayed.

- 5. Identify the test asset that you want to run by performing any of the following actions:
 - Scroll through the list.

(i)

Tip: You can hover over the icon in the **Type** column to know the type of the test asset.

Note: You can also identify the type of the asset from the icon that represents the test type as shown in the following table:

lcon	Represents	Listed in the SUITES tab	Listed in the TESTS tab	Listed in the AD- VANCED tab
-63-	API test		0	0
•	Functional test		0	0
٢	Performance test		0	0
۲	AFT Suite	0		0
43	API Suite	0		0
<u>商</u> 49 (小 @	Compound Test	0		0

lcon	Represents	Listed in the SUITES tab	Listed in the TESTS tab	Listed in the AD- VANCED tab
0	HCL AppScan CodeSweep	0		0
/JMeter*	JMeter Test	0		0
Ju	JUnit Test	0		0
0	Postman test	0		0
9	Rate Schedule	0		0
9	VU Schedule	0		0

• Search for the test asset by entering any text contained in the test asset name in the Search field.

• Click the **Filter** icon **M** in the **SUITES** or **TESTS** tab to filter the displayed assets based on the asset type.

For example, select **API Suite** in the **SUITES** tab to display all API Suites or select **Functional Test** in the **TESTS** tab to display all functional tests that are in the selected branch of the repository.

- Click the **Filter** icon **W** in the **ADVANCED** tab, and then create a filter query by using the **New filter** option by performing the following steps:
 - a. Click New filter.
 - b. Enter a name for the filter.
 - c. Select an operator, and add a rule or a group of rules.
 - d. Add or enter the relevant parameters and either select or enter the condition and the criteria for the condition.

You can select a parameter from the following list:

- Type
- Test Asset Name
- Test Asset Path
- Last Result
- Next Run
- Components
- e. Save the filter query to save and apply the filter query to filter the assets based on the query.

The test assets that match the filter criteria are displayed.

- Retrieve and apply a saved filter query, if you have saved filter queries previously by performing the following steps:
 - Note: The filter query applied previously is selected and the assets based on that filter query are displayed. To apply a different filter query, you must have created and saved the filter query.
 - a. Click the **Filter** icon \mathbf{M} in the **ADVANCED** tab.

The filter queries that you created and saved are displayed.

b. Click the filter that you want to apply.

The test assets that match the filter criteria are displayed.

You have identified the test asset that you want to run.

Clicking the test name displays the **Details** panel. You can view the details of the test such as the description, the branch in the repository that contains the asset, the Git details, and the details of the commits to the repository. You can also view the history of the test runs for the specific test under the **History** tab of the **Details** panel.

6. Click the **Execute** icon 🕑 in the row of the identified test asset.

The Execute test asset dialog is displayed.

Notes:

- If you have configured some or all of the settings for the current test run, and you do not want to continue with those settings, you can reset the settings by clicking **Reset**.
- If you want to repeat a test run and do not want to use the saved settings from a previous run, you can reset all the saved settings to their default values by clicking Reset.
- 7. Select the version of the test resources that you want to run by completing any of the following actions:

Note: The test resources in the version can contain the test assets, datasets, AFT XML files, API environment tags, and other resources specific to projects created from any of the desktop clients.

• Expand the list in the Version field, find the version of the test resources, and then select the version.

Use the following details about the version of the test resources that are displayed to identify the version that you want:

- Commit message.
- Tags labeled by the user for the version committed.

- The user who committed the version to the repository.
- Relative time of the commit. For example, 2 hours ago or 3 days ago.

The list displays the versions of the test resources committed by all users to the branch in the repository. The versions are arranged with the latest version that is committed, and then followed by the versions committed previously.

• Expand the list in the **Version** field, and then search for the version that you want to select by entering a partial or the complete commit message of that version.

The version that matches the search criteria is displayed and it is selected for the test run.

The default value for the version selected for the run is the latest version in the selected branch of the repository. If you do not select any version, then the latest version is selected for the test run.

Notes:

- If you selected a version but you do not want to use that version in the test run, you can remove the selected version by clicking the x icon. As a result, the default version is selected for the test run.
- If you repeated a test or ran the test again from the **Results** page, then the version of the test resources that you chose for the earlier run is shown as selected. You can either retain this version or select any other version from the list. You can also remove the previous version by clicking the x icon.
- 8. Select the time for scheduling the test run from the following options:
 - No action is required if you want to initiate the test run immediately after you click Execute.



Important: Click Execute only after you have configured the other settings in this dialog.



Note: The default time for scheduling a run is Now.

- Select Later and configure the date and time to schedule a test run.
- Select Recurring and perform the following steps to configure recurring test runs:
 - a. Click the **Calendar** icon 📛 under **Start**, and then select the date and time at which the test run must start.
 - b. Set the frequency at which the test runs must run by entering the number in the **Repeat every** field, and then select the period from the list.

For example, if you want the test run to be run every 2 hours, enter 120, and then select the **Minute(s)** option.

c. Set the option to end the recurring test runs from the following options:

- Select the Never option, if you do not want the recurring test runs to end.
- Select the **On** option, and then click the **Calendar** icon 🗮. You can select the date and time after which the scheduled test runs do not run.
- 9. Enter a label for the test run that helps you to identify the test on the **Results** page.

After the test run completes, the label that you entered is displayed for the test under the **Labels** column on the **Results** page. After you have created a label, any member of the project can use that label.

The default value for the Label field is null or an empty field.

Important: The configuration that you set for the test run in the Execute test asset dialog is preserved when you run the same test again. Those changes are not visible when another user logs in to HCL OneTest[™] Server. For example, if you created new variables on the server, those variables are available only for you when the same test is run again.

If you want to run the test immediately or at the scheduled time, click **Execute**, or continue with the next step. 10. Click **Advanced** to make the following advanced configurations:

a. Enter any JVM arguments that must be passed to the test run at run time in the **JVM Arguments** field, if applicable for the test.

For example, you can set a maximum Java heap size.

b. Enter program arguments that must be passed to the test run at run time in the **Program Arguments**, if applicable for the test.

If the test that you want to configure supports the presentation of the test results data in different formats, then do the required tasks in the following scenarios:

If	Then
You want the test results data in different supported formats.	Enter -history cisterna in the Program Argu- ments field.
You want to obtain the test results as a Jaeger trace.	Enter -history jaeger in the Program Arguments field.
You want the report as a test log and as a Jaeger trace.	Enter -history jaeger, testlog in the Program Ar- guments field.

If	Then
Jaeger is already set as a program argument and you want to remove the Jaeger trace for your test.	Delete the -history jaeger entry in the Program Arguments field.



Note: The default report format is the test log format for the test reports.

c. Enter the environment variables that must be passed to the test run at run time in the **Environment Variables** field, if applicable for the test.

For example, enter the environment variables when the third-party libraries that are used in the test run refer to the environment variables for configuration.



Note: You must separate the arguments or variables with a white space when you enter them in the same line or start each argument or variable on a new line.

The default value for each of the fields for the advanced settings is null or an empty field.

If you want to run the test immediately or at the scheduled time, click Execute, or continue with the next step.

- 11. Follow the instructions if you are running a test asset that contains datasets:
 - a. Click the DATA SOURCES tab, if it is not already open.
 - b. Consider the following information about datasets before you select a dataset:

The default value for the datasets in the **DATA SOURCES** tab is null if the test asset did not have an associated dataset. If the asset had an associated dataset, the default value is the associated dataset.

You can utilize the dataset stored as an Excel or CSV file to override the original dataset associated with the Suite, test, or schedule. For example, when you have associated a dataset in .xlsx, .xls, or .csv format with the test or schedule in desktop clients and if you have another set of data stored in an Excel or CSV file, then you can select that dataset from the **Override** list.

Remember: You must have uploaded the dataset as an Excel or CSV file into the Git repository, and ensured that both the original dataset (from the test asset) and new datasets (added to the project) have the same column names.

c. Select the dataset that you want to use in the test run from any of the following options:

- Select the dataset that is displayed as the default dataset when the test asset contains a single dataset.
 - **Note:** If there is only one dataset in the test asset, then that dataset is displayed as the default dataset.
- Select the dataset from the list.
 - **N**

Note: If there are multiple datasets in the test asset, the datasets are listed in their increasing alphabetical order.

• Select the dataset from the **Override** list to override the dataset that was associated with the test in the desktop client.

Important: If the test contains an encrypted dataset, the Project Owner must classify it in the DATA SECURITY tab on the Project page before you can select it. You must have added datasets to your project from the Dataset page for the datasets to be displayed in the Override list.

If you want to run the test immediately or at the scheduled time, click Execute, or continue with the next step.

- 12. Perform the following steps to provide the variables that must be passed to the test at the test run time. You can either enter the variables or import the file that contains the variables.
 - a. Click the VARIABLES tab, if it is not already open.
 - b. Choose one of the following methods to add the variables:
 - To add new variables manually, click the **Add Variable** icon (+), enter the name, and value of the variable.
 - i. Enter ${\tt Windows_Device_Selection}$ as the name.
 - ii. Enter <IP_address> as the value, which is the IP address of the computer that contains the UI Test agent.
 - To add new variables from your local computer or from the Git repository that is associated

with your server project, click the **Upload** icon and select the **Upload from local system** or **Browse from server** to select the variable file.



Note: You must have created a file with the variables before you can select the file.

13. Select any of the following steps that depends on the location to run the test:

- If you want to run the tests on the remote agents, go to Step 14 on page 395.
- \circ If you want to run the tests on a Kubernetes cluster, go to Step 15 on page 396.
- 14. Follow the instructions if you want to run a test on the remote performance agent that is connected either to the default Kubernetes cluster or the remote Kubernetes cluster:
 - a. Click the **LOCATION** tab, if it is not already open.

The performance agents that are configured in the test asset are listed under the **Host** column. The information about the availability of the performance agent is displayed.

Note: You must have added performance agents to your project from the Agents and Intercepts page for the performance agents to be displayed under the Override column.

The default value for the performance agents is null or an empty field if no performance agents were configured in the test asset. If the test asset contains performance agents that are configured, then the default performance agent is the first item to be displayed on the list of performance agents listed in the increasing alphabetical order.

b. Select the performance agent where you want to run the test asset in the following scenarios:

lf	Then	Action
The agent that is specified in the test assets is available and no other agents are added to the project.	The agent that is specified in the test assets is displayed in the Override column.	Select the agent in the Host that is also displayed in the Override column as the location to run the test.
The agent that is specified in the test assets is not available and no other agents are added to the project.	There is no agent displayed for override in the Override column.	You cannot run the test on the agent. You must wait until the agent is available to run the test on the agent.
The agent that is specified in the test assets is available and there are other agents that are added to the project.	Agents that have capabilities that match with the agent capa- bilities specified in the test as- sets are listed in the Override column as follows: • Agents with capabilities that best match the ca- pabilities in the agent in the asset are at the top of the list.	 Perform any of the following actions: Select the agent in the Host that is also displayed in the Override column as the location to run the test. Select an agent in the Override column as the location to run the test.

If	Then	Action
	 Agents with capabilities 	
	that do not match with	
	the capabilities in the	
	agent in the asset are	
	listed subsequently.	
	You can find details of both	
	agents for the matching capa-	
	bilities when you hover over the	
	agent in the Override column.	

c. Click Execute.

The test run is initiated.

- 15. Follow the instructions if you want to change the location of a Kubernetes cluster for running the test:
 - a. Click the **LOCATION** tab, if it is not already open.

The **Default Cluster** is the default location where the test runs, and it is listed under the **Host** column. The information about the availability of the default location is displayed.

Important: You must have added the following remote hosts to your project that are then displayed under the **Override** column:

- Docker hosts that are registered with HCL OneTest[™] Server.
- Kubernetes clusters that are registered with a team space.

Notes:

- If the remote Docker hosts or clusters are not added to your project, the option No
 override options is displayed as the default value and the test runs in the Kubernetes
 cluster of HCL OneTest[™] Server.
- If remote Docker hosts or clusters are added to your project, the added Docker hosts or clusters are displayed along with their availability status and ownership information.
- b. Select the location where you want to run the test asset from the following options:
 - Select the **Default Cluster** when no remote Docker hosts or clusters are available in your project.
 - Select the remote Docker host or cluster from the list when a remote Docker host or cluster is available in your project.
 - Select **No override options**, if you selected any remote Docker host or cluster and want to revert to the **Default Cluster** to run the test asset.

c. Click Execute.

The test run is initiated.

Results

You have configured and either started or scheduled a test run of a Functional Windows test.

What to do next

You can choose to perform any of the following tasks after you have initiated or scheduled a run:

- Stop the test run at any point after the test run is initiated from the **Execution** page. See Stopping test runs on page 462.
- Cancel a scheduled test run from the Execution page. See Canceling scheduled test runs on page 465.
- View all the states of the test asset by clicking the **Show in the Progress page** icon **C** for the test asset for which you started or scheduled the run. See Viewing the state of test assets on page 453.
- View the progress of the test from the **Progress** page. See Viewing the progress of running test assets on page 457.
- View the results, reports, and logs of the test from the **Results** page after the test completes the run. See Test results on page 513.

Related information

Resetting the configuration settings for a test run on page 461

Test run configurations on page 327

Configuring a run of a Compound Test that contains performance tests or a Performance test

After you added the test resources that you created in the desktop client to the project, you can configure a Compound Test that contains performance tests or a Performance test to be run on HCL OneTest[™] Server or a remote Kubernetes cluster.

Before you begin

You must have completed the following tasks:

- Created performance tests under a Compound Test or a Performance test in HCL OneTest™ Performance.
- Read and completed the tasks mentioned in Test run considerations for running tests on remote performance agents on page 289, if you want to use a remote agent as the location to run the test.
- Read and completed the tasks mentioned in Considerations for using a remote Kubernetes cluster on page 313, if you want to use a remote Kubernetes cluster as a location to run the test.

- Ensured that you are assigned a role as a *Member* or *Project Creator* in the team space. See Managing members and their roles in a team space on page 720.
- Ensured that you are assigned a role as a *Project Owner* or *Tester* in the project. See Managing access to server projects on page 734.
- 1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

- 2. Open the project that contains the test assets, and then click **Execution**.
- 3. Select the branch of the repository that contains the test assets.

The test assets that are contained in the selected branch of the repository are displayed in the following tabs on the **Execution** page:

Tab	Description
SUITES	Lists all suites, compound tests, JMeter tests, JUnit tests, Postman tests, Rate Sched- ules, or VU Schedules that are in the selected branch of the repository.
TESTS	Lists all API tests, functional tests, or performance tests that are in the selected branch of the repository.
ADVANCED	Lists all assets that are displayed when custom filters are applied for assets in the se- lected branch of the repository.

4. Select the tab based on the type of test assets that you want to run as indicated in the following table:

If	Then
You want to run AFT Suites, API Suites, Compound Tests, JMeter tests, JUnit tests, Postman tests, Rate Schedules, or VU Schedules,.	Click the SUITES tab.
You want to run API tests, functional tests, or perfor- mance tests.	Click the TESTS tab.
You want to find Suites and tests by using custom fil- ters, and then run Suites and tests.	Click the ADVANCED tab.

The test assets in the selected tab are displayed.

5. Identify the test asset that you want to run by performing any of the following actions:

• Scroll through the list.

i ·

Tip: You can hover over the icon in the Type column to know the type of the test asset.

Note: You can also identify the type of the asset from the icon that represents the test type as shown in the following table:

lcon	Represents	Listed in the SUITES tab	Listed in the TESTS tab	Listed in the AD- VANCED tab
-6.3-	API test		0	0
۲	Functional test		0	0
٨	Performance test		0	0
	AFT Suite	0		0
•	API Suite	0		0
0 00 0 00	Compound Test	0		0
0	HCL AppScan CodeSweep	0		0
/jMeter"	JMeter Test	0		0
Ju	JUnit Test	0		0
0	Postman test	0		0
9	Rate Schedule	0		0
9	VU Schedule	0		0

• Search for the test asset by entering any text contained in the test asset name in the Search field.

• Click the **Filter** icon **T** in the **SUITES** or **TESTS** tab to filter the displayed assets based on the asset type.

For example, select **API Suite** in the **SUITES** tab to display all API Suites or select **Functional Test** in the **TESTS** tab to display all functional tests that are in the selected branch of the repository.

- Click the **Filter** icon **W** in the **ADVANCED** tab, and then create a filter query by using the **New filter** option by performing the following steps:
 - a. Click New filter.
 - b. Enter a name for the filter.
 - c. Select an operator, and add a rule or a group of rules.
 - d. Add or enter the relevant parameters and either select or enter the condition and the criteria for the condition.

You can select a parameter from the following list:

- Type
- Test Asset Name
- Test Asset Path
- Last Result
- Next Run
- Components
- e. Save the filter query to save and apply the filter query to filter the assets based on the query.

The test assets that match the filter criteria are displayed.

 Retrieve and apply a saved filter query, if you have saved filter queries previously by performing the following steps:

Note: The filter query applied previously is selected and the assets based on that filter query are displayed. To apply a different filter query, you must have created and saved the filter query.

a. Click the **Filter** icon \mathbf{M} in the **ADVANCED** tab.

The filter queries that you created and saved are displayed.

b. Click the filter that you want to apply.

The test assets that match the filter criteria are displayed.

You have identified the test asset that you want to run.

Clicking the test name displays the **Details** panel. You can view the details of the test such as the description, the branch in the repository that contains the asset, the Git details, and the details of the commits to the repository. You can also view the history of the test runs for the specific test under the **History** tab of the **Details** panel.

Click the Execute icon in the row of the identified test asset.

The Execute test asset dialog is displayed.



- If you have configured some or all of the settings for the current test run, and you do not want to continue with those settings, you can reset the settings by clicking **Reset**.
- If you want to repeat a test run and do not want to use the saved settings from a previous run, you can reset all the saved settings to their default values by clicking Reset.
- 7. Select the version of the test resources that you want to run by completing any of the following actions:

Note: The test resources in the version can contain the test assets, datasets, AFT XML files, API environment tags, and other resources specific to projects created from any of the desktop clients.

• Expand the list in the Version field, find the version of the test resources, and then select the version.

Use the following details about the version of the test resources that are displayed to identify the version that you want:

- Commit message.
- Tags labeled by the user for the version committed.
- The user who committed the version to the repository.
- Relative time of the commit. For example, 2 hours ago or 3 days ago.

The list displays the versions of the test resources committed by all users to the branch in the repository. The versions are arranged with the latest version that is committed, and then followed by the versions committed previously.

• Expand the list in the **Version** field, and then search for the version that you want to select by entering a partial or the complete commit message of that version.

The version that matches the search criteria is displayed and it is selected for the test run.

The default value for the version selected for the run is the latest version in the selected branch of the repository. If you do not select any version, then the latest version is selected for the test run.



401

Ż

- If you selected a version but you do not want to use that version in the test run, you can remove the selected version by clicking the x icon. As a result, the default version is selected for the test run.
- If you repeated a test or ran the test again from the **Results** page, then the version of the test resources that you chose for the earlier run is shown as selected. You can either retain this version or select any other version from the list. You can also remove the previous version by clicking the **x** icon.
- 8. Select the time for scheduling the test run from the following options:
 - No action is required if you want to initiate the test run immediately after you click Execute.



Important: Click Execute only after you have configured the other settings in this dialog.



Note: The default time for scheduling a run is Now.

- Select Later and configure the date and time to schedule a test run.
- Select Recurring and perform the following steps to configure recurring test runs:
 - a. Click the **Calendar** icon 📛 under **Start**, and then select the date and time at which the test run must start.
 - b. Set the frequency at which the test runs must run by entering the number in the **Repeat every** field, and then select the period from the list.

For example, if you want the test run to be run every 2 hours, enter 120, and then select the **Minute(s)** option.

- c. Set the option to end the recurring test runs from the following options:
 - Select the Never option, if you do not want the recurring test runs to end.
 - Select the **On** option, and then click the **Calendar** icon \square . You can select the date and time after which the scheduled test runs do not run.
- 9. Enter a label for the test run that helps you to identify the test on the **Results** page.

After the test run completes, the label that you entered is displayed for the test under the **Labels** column on the **Results** page. After you have created a label, any member of the project can use that label.

The default value for the Label field is null or an empty field.

Important: The configuration that you set for the test run in the Execute test asset dialog is preserved when you run the same test again. Those changes are not visible when another user logs in to HCL OneTest[™] Server. For example, if you created new variables on the server, those variables are available only for you when the same test is run again.

If you want to run the test immediately or at the scheduled time, click **Execute**, or continue with the next step.

- 10. Click Advanced to make the following advanced configurations:
 - a. Enter any JVM arguments that must be passed to the test run at run time in the **JVM Arguments** field, if applicable for the test.

For example, you can set a maximum Java heap size.

b. Enter program arguments that must be passed to the test run at run time in the **Program Arguments**, if applicable for the test.

If the test that you want to configure supports the presentation of the test results data in different formats, then do the required tasks in the following scenarios:

If	Then
You want the test results data in different supported formats.	Enter -history cisterna in the Program Argu- ments field.
You want to obtain the test results as a Jaeger trace.	Enter -history jaeger in the Program Arguments field.
You want the report as a test log and as a Jaeger trace.	Enter -history jaeger, testlog in the Program Ar- guments field.
Jaeger is already set as a program argument and you want to remove the Jaeger trace for your test.	Delete the -history jaeger entry in the Program Arguments field.

Note: The default report format is the test log format for the test reports.

c. Enter the environment variables that must be passed to the test run at run time in the **Environment Variables** field, if applicable for the test.

For example, enter the environment variables when the third-party libraries that are used in the test run refer to the environment variables for configuration.

Note: You must separate the arguments or variables with a white space when you enter them in the same line or start each argument or variable on a new line.

The default value for each of the fields for the advanced settings is null or an empty field.

If you want to run the test immediately or at the scheduled time, click **Execute**, or continue with the next step.

- 11. Follow the instructions if you are running a test asset that contains datasets:
 - a. Click the DATA SOURCES tab, if it is not already open.
 - b. Consider the following information about datasets before you select a dataset:

The default value for the datasets in the **DATA SOURCES** tab is null if the test asset did not have an associated dataset. If the asset had an associated dataset, the default value is the associated dataset.

You can utilize the dataset stored as an Excel or CSV file to override the original dataset associated with the Suite, test, or schedule. For example, when you have associated a dataset in .xlsx, .xls, or .csv format with the test or schedule in desktop clients and if you have another set of data stored in an Excel or CSV file, then you can select that dataset from the **Override** list.

Remember: You must have uploaded the dataset as an Excel or CSV file into the Git repository, and ensured that both the original dataset (from the test asset) and new datasets (added to the project) have the same column names.

- c. Select the dataset that you want to use in the test run from any of the following options:
 - Select the dataset that is displayed as the default dataset when the test asset contains a single dataset.

Note: If there is only one dataset in the test asset, then that dataset is displayed as the default dataset.

- · Select the dataset from the list.
 - Note: If there are multiple datasets in the test asset, the datasets are listed in their increasing alphabetical order.
- Select the dataset from the **Override** list to override the dataset that was associated with the test in the desktop client.


Important: If the test contains an encrypted dataset, the Project Owner must classify it in the DATA SECURITY tab on the Project page before you can select it. You must have added datasets to your project from the Dataset page for the datasets to be displayed in the Override list.

If you want to run the test immediately or at the scheduled time, click **Execute**, or continue with the next step.

12. Follow the instructions if the test requires a variable that must be passed to the test at the test run time.

- a. Click the VARIABLES tab, if it is not already open.
- b. Choose one of the following methods to add the variables:
 - To add new variables manually, click the **Add Variable** icon (+), enter the name, and value of the variable.
 - To add new variables from your local computer or from the Git repository that is associated

with your server project, click the **Upload** icon and select the **Upload from local system** or **Browse from server** to select the variable file.



The default value for the variables is null or an empty field.

If you want to run the test immediately or at the scheduled time, click **Execute**, or continue with the next step.

- 13. Select any of the following steps that depends on the location to run the test:
 - If you want to run the tests on the remote agents, go to Step 14 on page 405.
 - \circ If you want to run the tests on a Kubernetes cluster, go to Step 15 on page 406.
- 14. Follow the instructions if you want to run a test on the remote performance agent that is connected either to the default Kubernetes cluster or the remote Kubernetes cluster:
 - a. Click the LOCATION tab, if it is not already open.

The performance agents that are configured in the test asset are listed under the **Host** column. The information about the availability of the performance agent is displayed.

Note: You must have added performance agents to your project from the Agents and Intercepts page for the performance agents to be displayed under the Override column.

The default value for the performance agents is null or an empty field if no performance agents were configured in the test asset. If the test asset contains performance agents that are configured, then the default performance agent is the first item to be displayed on the list of performance agents listed in the increasing alphabetical order.

b. Select the performance agent where you want to run the test asset in the following scenarios:

lf	Then	Action
The agent that is specified in	The agent that is specified in	Select the agent in the Host that
the test assets is available and	the test assets is displayed in	is also displayed in the Override
no other agents are added to	the Override column.	column as the location to run
the project.		the test.

lf	Then	Action
The agent that is specified in the test assets is not available and no other agents are added to the project.	There is no agent displayed for override in the Override column.	You cannot run the test on the agent. You must wait until the agent is available to run the test on the agent.
The agent that is specified in the test assets is available and there are other agents that are added to the project.	Agents that have capabilities that match with the agent capa- bilities specified in the test as- sets are listed in the Override column as follows: • Agents with capabilities that best match the ca- pabilities in the agent in the asset are at the top of the list. • Agents with capabilities that do not match with the capabilities in the agent in the asset are listed subsequently. You can find details of both agents for the matching capa- bilities when you hover over the agent in the Override column.	 Perform any of the following actions: Select the agent in the Host that is also displayed in the Override column as the location to run the test. Select an agent in the Override column as the location to run the test.

c. Click Execute.

The test run is initiated.

15. Follow the instructions if you want to change the location of a Kubernetes cluster for running the test:

a. Click the **LOCATION** tab, if it is not already open.

The **Default Cluster** is the default location where the test runs, and it is listed under the **Host** column. The information about the availability of the default location is displayed.

Important: You must have added the following remote hosts to your project that are then displayed under the **Override** column:

- Docker hosts that are registered with HCL OneTest[™] Server.
 - Kubernetes clusters that are registered with a team space.

Notes:

I

- If the remote Docker hosts or clusters are not added to your project, the option No
 override options is displayed as the default value and the test runs in the Kubernetes
 cluster of HCL OneTest[™] Server.
- If remote Docker hosts or clusters are added to your project, the added Docker hosts or clusters are displayed along with their availability status and ownership information.

b. Select the location where you want to run the test asset from the following options:

- Select the **Default Cluster** when no remote Docker hosts or clusters are available in your project.
- Select the remote Docker host or cluster from the list when a remote Docker host or cluster is available in your project.
- Select No override options, if you selected any remote Docker host or cluster and want to revert to the Default Cluster to run the test asset.
- c. Click Execute.

The test run is initiated.

Results

You have configured and either started or scheduled a test run of a Compound Test that contains performance tests or a Performance test.

What to do next

You can choose to perform any of the following tasks after you have initiated or scheduled a run:

- Stop the test run at any point after the test run is initiated from the **Execution** page. See Stopping test runs on page 462.
- Cancel a scheduled test run from the Execution page. See Canceling scheduled test runs on page 465.
- View all the states of the test asset by clicking the **Show in the Progress page** icon C for the test asset for which you started or scheduled the run. See Viewing the state of test assets on page 453.
- View the progress of the test from the **Progress** page. See Viewing the progress of running test assets on page 457.
- View the results, reports, and logs of the test from the **Results** page after the test completes the run. See Test results on page 513.

Related information

Resetting the configuration settings for a test run on page 461

Test run configurations on page 327

Configuring a run of a JMeter test

After you added the test resources that you created in JMeter to the server project, you can configure a JMeter test run on HCL OneTest[™] Server or a remote Kubernetes cluster.

Before you begin

You must have completed the following tasks:

- Read and completed the tasks mentioned in Test run considerations for JMeter tests on page 284.
- Read and completed the tasks mentioned in Considerations for using a remote Kubernetes cluster on page 313, if you want to use a remote Kubernetes cluster as a location to run the test.
- Ensured that the JMeter extension on HCL OneTest™ Server is enabled before you configure a test run.
- Ensured that you are assigned a role as a *Member* or *Project Creator* in the team space. See Managing members and their roles in a team space on page 720.
- Ensured that you are assigned a role as a *Project Owner* or *Tester* in the project. See Managing access to server projects on page 734.

About this task

- Important: You can run the JMeter tests only on the default cluster of HCL OneTest[™] Server or a remote Kubernetes cluster. You cannot run the JMeter tests on remote agents or remote Docker hosts that are registered with HCL OneTest[™] Server.
- 1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

- 2. Open the project that contains the test assets, and then click Execution.
- 3. Select the branch of the repository that contains the test assets.

The test assets that are contained in the selected branch of the repository are displayed in the following tabs on the **Execution** page:

Tab	Description
SUITES	Lists all suites, compound tests, JMeter tests, JUnit tests, Postman tests, Rate Sched- ules, or VU Schedules that are in the selected branch of the repository.

Tab	Description	
TESTS	Lists all API tests, functional tests, or performance tests that are in the selected branch of the repository.	
ADVANCED	Lists all assets that are displayed when custom filters are applied for assets in the se- lected branch of the repository.	

4. Select the tab based on the type of test assets that you want to run as indicated in the following table:

If	Then
You want to run AFT Suites, API Suites, Compound Tests, JMeter tests, JUnit tests, Postman tests, Rate Schedules, or VU Schedules,.	Click the SUITES tab.
You want to run API tests, functional tests, or perfor- mance tests.	Click the TESTS tab.
You want to find Suites and tests by using custom fil- ters, and then run Suites and tests.	Click the ADVANCED tab.

The test assets in the selected tab are displayed.

- 5. Identify the test asset that you want to run by performing any of the following actions:
 - Scroll through the list.

i

1

Tip: You can hover over the icon in the Type column to know the type of the test asset.

Note: You can also identify the type of the asset from the icon that represents the test type as shown in the following table:

lcon	Represents	Listed in the SUITES tab	Listed in the TESTS tab	Listed in the AD- VANCED tab
43	API test		0	0
•	Functional test		0	0
٢	Performance test		Ø	0

lcon	Represents	Listed in the SUITES tab	Listed in the TESTS tab	Listed in the AD- VANCED tab
	AFT Suite	0		0
•	API Suite	0		0
00 49 (1) 00	Compound Test	0		0
0	HCL AppScan CodeSweep	0		0
/jMeter"	JMeter Test	0		0
Ju	JUnit Test	0		0
0	Postman test	0		0
9	Rate Schedule	0		0
0	VU Schedule	0		0

• Search for the test asset by entering any text contained in the test asset name in the Search field.

• Click the **Filter** icon **W** in the **SUITES** or **TESTS** tab to filter the displayed assets based on the asset type.

For example, select **API Suite** in the **SUITES** tab to display all API Suites or select **Functional Test** in the **TESTS** tab to display all functional tests that are in the selected branch of the repository.

- Click the **Filter** icon **T** in the **ADVANCED** tab, and then create a filter query by using the **New filter** option by performing the following steps:
 - a. Click New filter.
 - b. Enter a name for the filter.
 - c. Select an operator, and add a rule or a group of rules.
 - d. Add or enter the relevant parameters and either select or enter the condition and the criteria for the condition.

You can select a parameter from the following list:

- Type
- Test Asset Name

- Test Asset Path
- Last Result
- Next Run
- Components
- e. Save the filter query to save and apply the filter query to filter the assets based on the query.

The test assets that match the filter criteria are displayed.

• Retrieve and apply a saved filter query, if you have saved filter queries previously by performing the following steps:

Note: The filter query applied previously is selected and the assets based on that filter query are displayed. To apply a different filter query, you must have created and saved the filter query.

a. Click the **Filter** icon \mathbf{M} in the **ADVANCED** tab.

The filter queries that you created and saved are displayed.

b. Click the filter that you want to apply.

The test assets that match the filter criteria are displayed.

You have identified the test asset that you want to run.

Clicking the test name displays the **Details** panel. You can view the details of the test such as the description, the branch in the repository that contains the asset, the Git details, and the details of the commits to the repository. You can also view the history of the test runs for the specific test under the **History** tab of the **Details** panel.

6. Click the **Execute** icon 🕑 in the row of the identified test asset.

The Execute test asset dialog is displayed.

Notes:

- If you have configured some or all of the settings for the current test run, and you do not want to continue with those settings, you can reset the settings by clicking **Reset**.
- If you want to repeat a test run and do not want to use the saved settings from a previous run, you can reset all the saved settings to their default values by clicking **Reset**.

7. Select the version of the test resources that you want to run by completing any of the following actions:

• Expand the list in the Version field, find the version of the test resources, and then select the version.

Use the following details about the version of the test resources that are displayed to identify the version that you want:

- · Commit message.
- Tags labeled by the user for the version committed.
- The user who committed the version to the repository.
- Relative time of the commit. For example, 2 hours ago or 3 days ago.

The list displays the versions of the test resources committed by all users to the branch in the repository. The versions are arranged with the latest version that is committed, and then followed by the versions committed previously.

• Expand the list in the **Version** field, and then search for the version that you want to select by entering a partial or the complete commit message of that version.

The version that matches the search criteria is displayed and it is selected for the test run.

- 8. Select the time for scheduling the test run from the following options:
 - No action is required if you want to initiate the test run immediately after you click Execute.

Important: Click Execute only after you have configured the other settings in this dialog.



Note: The default time for scheduling a run is Now.

- Select Later and configure the date and time to schedule a test run.
- Select Recurring and perform the following steps to configure recurring test runs:
 - a. Click the **Calendar** icon 📛 under **Start**, and then select the date and time at which the test run must start.
 - b. Set the frequency at which the test runs must run by entering the number in the **Repeat every** field, and then select the period from the list.

For example, if you want the test run to be run every 2 hours, enter 120, and then select the **Minute(s)** option.

- c. Set the option to end the recurring test runs from the following options:
 - Select the Never option, if you do not want the recurring test runs to end.
 - Select the On option, and then click the Calendar icon . You can select the date and time after which the scheduled test runs do not run.
- 9. Enter a label for the test run that helps you to identify the test on the Results page.

After the test run completes, the label that you entered is displayed for the test under the **Labels** column on the **Results** page. After you have created a label, any member of the project can use that label.

The default value for the Label field is null or an empty field.

Important: The configuration that you set for the test run in the Execute test asset dialog is preserved when you run the same test again. Those changes are not visible when another user logs in to HCL OneTest[™] Server. For example, if you created new variables on the server, those variables are available only for you when the same test is run again.

If you want to run the test immediately or at the scheduled time, click **Execute**, or continue with the next step.

- 10. Click Advanced to make the following advanced configurations:
 - a. Enter any JVM arguments that must be passed to the test run at run time in the **JVM Arguments** field, if applicable for the test.

For example, you can set a maximum Java heap size.

b. Enter program arguments that must be passed to the test run at run time in the **Program Arguments**, if applicable for the test.

For example, enter -J to override any JMeter property that is defined in the properties file.

Note: You must separate the arguments or variables with a white space when you enter them in the same line or start each argument or variable on a new line.

The default value for each of the fields for the advanced settings is null or an empty field.

If you want to run the test immediately or at the scheduled time, click Execute, or continue with the next step.

- 11. Follow the instructions if you want to change the location of a Kubernetes cluster for running the test:
 - a. Click the LOCATION tab, if it is not already open.

The **Default Cluster** is the default location where the test runs, and it is listed under the **Host** column. The information about the availability of the default location is displayed.



Important: You must have added the registered remote Kubernetes clusters to your project that are then displayed under the **Override** column:



- If the remote clusters are not added to your project, the option No override options is displayed as the default value and the test runs in the Kubernetes cluster of HCL OneTest[™] Server.
 - If remote clusters are added to your project, the added clusters are displayed along with their availability status and ownership information.
- b. Select the location where you want to run the test asset from the following options:
 - Select the Default Cluster when no remote clusters are available in your project.
 - Select the remote cluster from the list when a remote cluster is available in your project.
 - Select No override options, if you selected any remote cluster and want to revert to the Default Cluster to run the test asset.
- c. Click Execute.

The test run is initiated.

Results

You have configured and either started or scheduled a test run of a JMeter test.

What to do next

You can choose to perform any of the following tasks after you have initiated or scheduled a run:

- Stop the test run at any point after the test run is initiated from the **Execution** page. See Stopping test runs on page 462.
- Cancel a scheduled test run from the Execution page. See Canceling scheduled test runs on page 465.
- View all the states of the test asset by clicking the **Show in the Progress page** icon **C** for the test asset for which you started or scheduled the run. See Viewing the state of test assets on page 453.
- View the progress of the test from the **Progress** page. See Viewing the progress of running test assets on page 457.
- View the results, reports, and logs of the test from the **Results** page after the test completes the run. See Test results on page 513.

Related information

Resetting the configuration settings for a test run on page 461

Test run configurations on page 327

Configuring a run of a JUnit test

After you added the test resources that contain the Maven project with the JUnit tests to the server project, you can configure a JUnit test run on HCL OneTest[™] Server or a remote Kubernetes cluster.

Before you begin

You must have completed the following tasks:

- Read and completed the tasks mentioned in Test run considerations for JUnit tests on page 286 before you configure a JUnit test run.
- Read and completed the tasks mentioned in Considerations for using a remote Kubernetes cluster on page 313, if you want to use a remote Kubernetes cluster as a location to run the test.
- Ensured that the JUnit extension on HCL OneTest[™] Server is enabled before you configure a test run.
- Ensured that you are assigned a role as a *Member* or *Project Creator* in the team space. See Managing members and their roles in a team space on page 720.
- Ensured that you are assigned a role as a *Project Owner* or *Tester* in the project. See Managing access to server projects on page 734.

About this task

Important: You can run the JUnit tests only on the default cluster of HCL OneTest[™] Server or a remote Kubernetes cluster. You cannot run the JUnit tests on remote agents or remote Docker hosts that are registered with HCL OneTest[™] Server.

After the test runs, you can view the results of the JUnit test in the following formats:

- Surefire
- Jaeger trace
- JUnit XML Report
- 1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

- 2. Open the project that contains the test assets, and then click Execution.
- 3. Select the branch of the repository that contains the test assets.

The test assets that are contained in the selected branch of the repository are displayed in the following tabs on the **Execution** page:

Tab	Description
SUITES	Lists all suites, compound tests, JMeter tests, JUnit tests, Postman tests, Rate Sched- ules, or VU Schedules that are in the selected branch of the repository.
TESTS	Lists all API tests, functional tests, or performance tests that are in the selected branch of the repository.
ADVANCED	Lists all assets that are displayed when custom filters are applied for assets in the se- lected branch of the repository.

4. Select the tab based on the type of test assets that you want to run as indicated in the following table:

If	Then
You want to run AFT Suites, API Suites, Compound Tests, JMeter tests, JUnit tests, Postman tests, Rate Schedules, or VU Schedules,.	Click the SUITES tab.
You want to run API tests, functional tests, or perfor- mance tests.	Click the TESTS tab.
You want to find Suites and tests by using custom fil- ters, and then run Suites and tests.	Click the ADVANCED tab.

The test assets in the selected tab are displayed.

- 5. Identify the test asset that you want to run by performing any of the following actions:
 - Scroll through the list.

(i)

Tip: You can hover over the icon in the **Type** column to know the type of the test asset.

Note: You can also identify the type of the asset from the icon that represents the test type as shown in the following table:

lcon	Represents	Listed in the SUITES tab	Listed in the TESTS tab	Listed in the AD- VANCED tab
-63-	API test		0	0
۲	Functional test		0	0
٢	Performance test		0	0
	AFT Suite	0		0
43	API Suite	0		0
<u>த்</u> ம	Compound Test	0		0

lcon	Represents	Listed in the SUITES tab	Listed in the TESTS tab	Listed in the AD- VANCED tab
Ø	HCL AppScan CodeSweep	0		0
/JMeter	JMeter Test	0		0
Ju	JUnit Test	0		0
0	Postman test	0		0
9	Rate Schedule	0		0
9	VU Schedule	0		0

• Search for the test asset by entering any text contained in the test asset name in the Search field.

• Click the **Filter** icon **M** in the **SUITES** or **TESTS** tab to filter the displayed assets based on the asset type.

For example, select **API Suite** in the **SUITES** tab to display all API Suites or select **Functional Test** in the **TESTS** tab to display all functional tests that are in the selected branch of the repository.

- Click the **Filter** icon **W** in the **ADVANCED** tab, and then create a filter query by using the **New filter** option by performing the following steps:
 - a. Click New filter.
 - b. Enter a name for the filter.
 - c. Select an operator, and add a rule or a group of rules.
 - d. Add or enter the relevant parameters and either select or enter the condition and the criteria for the condition.

You can select a parameter from the following list:

- Type
- Test Asset Name
- Test Asset Path
- Last Result
- Next Run
- Components
- e. Save the filter query to save and apply the filter query to filter the assets based on the query.

The test assets that match the filter criteria are displayed.

- Retrieve and apply a saved filter query, if you have saved filter queries previously by performing the following steps:
 - Note: The filter query applied previously is selected and the assets based on that filter query are displayed. To apply a different filter query, you must have created and saved the filter query.
 - a. Click the **Filter** icon \mathbf{M} in the **ADVANCED** tab.

The filter queries that you created and saved are displayed.

b. Click the filter that you want to apply.

The test assets that match the filter criteria are displayed.

You have identified the test asset that you want to run.

Clicking the test name displays the **Details** panel. You can view the details of the test such as the description, the branch in the repository that contains the asset, the Git details, and the details of the commits to the repository. You can also view the history of the test runs for the specific test under the **History** tab of the **Details** panel.

6. Click the **Execute** icon 🕑 in the row of the identified test asset.

The Execute test asset dialog is displayed.

Notes:

- If you have configured some or all of the settings for the current test run, and you do not want to continue with those settings, you can reset the settings by clicking **Reset**.
- If you want to repeat a test run and do not want to use the saved settings from a previous run, you can reset all the saved settings to their default values by clicking Reset.
- 7. Select the version of the test resources that you want to run by completing any of the following actions:
 - Expand the list in the Version field, find the version of the test resources, and then select the version.

Use the following details about the version of the test resources that are displayed to identify the version that you want:

- Commit message.
- Tags labeled by the user for the version committed.
- The user who committed the version to the repository.
- Relative time of the commit. For example, 2 hours ago or 3 days ago.

The list displays the versions of the test resources committed by all users to the branch in the repository. The versions are arranged with the latest version that is committed, and then followed by the versions committed previously.

• Expand the list in the **Version** field, and then search for the version that you want to select by entering a partial or the complete commit message of that version.

The version that matches the search criteria is displayed and it is selected for the test run.

- 8. Select the time for scheduling the test run from the following options:
 - No action is required if you want to initiate the test run immediately after you click Execute.

Important: Click Execute only after you have configured the other settings in this dialog.



Note: The default time for scheduling a run is Now.

- Select Later and configure the date and time to schedule a test run.
- \circ Select $\mbox{Recurring}$ and perform the following steps to configure recurring test runs:
 - a. Click the **Calendar** icon to under **Start**, and then select the date and time at which the test run must start.
 - b. Set the frequency at which the test runs must run by entering the number in the **Repeat every** field, and then select the period from the list.

For example, if you want the test run to be run every 2 hours, enter 120, and then select the **Minute(s)** option.

- c. Set the option to end the recurring test runs from the following options:
 - Select the Never option, if you do not want the recurring test runs to end.
 - Select the **On** option, and then click the **Calendar** icon ^{III}. You can select the date and time after which the scheduled test runs do not run.
- 9. Enter a label for the test run that helps you to identify the test on the **Results** page.

After the test run completes, the label that you entered is displayed for the test under the **Labels** column on the **Results** page. After you have created a label, any member of the project can use that label.

The default value for the Label field is null or an empty field.

Important: The configuration that you set for the test run in the Execute test asset dialog is preserved when you run the same test again. Those changes are not visible when another user logs in to HCL OneTest[™] Server. For example, if you created new variables on the server, those variables are available only for you when the same test is run again.

If you want to run the test immediately or at the scheduled time, click **Execute**, or continue with the next step.

- 10. Click Advanced to make the following advanced configurations:
 - a. Enter any JVM arguments that must be passed to the test run at run time in the **JVM Arguments** field, if applicable for the test.

You can enter a variable that points to the MAVEN_OPTS property.

b. Enter the environment variables that must be passed to the test run at run time in the **Environment Variables** field, if applicable for the test.

For example, if you have created the JUnit tests by using JDK V12, then you must enter the variable as **JDKOTHER** and the value as **jdkv12**, so that the test run uses the JDK in the path /data/junit-ext/jdks/jdkv12.

Note: You must separate the arguments or variables with a white space when you enter them in the same line or start each argument or variable on a new line.

The default value for each of the fields for the advanced settings is null or an empty field.

If you want to run the test immediately or at the scheduled time, click **Execute**, or continue with the next step.

- 11. Follow the instructions if you want to change the location of a Kubernetes cluster for running the test:
 - a. Click the LOCATION tab, if it is not already open.

The **Default Cluster** is the default location where the test runs, and it is listed under the **Host** column. The information about the availability of the default location is displayed.

Important: You must have added the registered remote Kubernetes clusters to your project that are then displayed under the Override column:

Notes:

- If the remote clusters are not added to your project, the option No override options is displayed as the default value and the test runs in the Kubernetes cluster of HCL OneTest[™] Server.
- If remote clusters are added to your project, the added clusters are displayed along with their availability status and ownership information.

b. Select the location where you want to run the test asset from the following options:

- Select the Default Cluster when no remote clusters are available in your project.
- Select the remote cluster from the list when a remote cluster is available in your project.
- Select No override options, if you selected any remote cluster and want to revert to the Default Cluster to run the test asset.

c. Click Execute.

The test run is initiated.

Results

You have configured and either started or scheduled a test run of a JUnit test.

What to do next

You can choose to perform any of the following tasks after you have initiated or scheduled a run:

- Stop the test run at any point after the test run is initiated from the **Execution** page. See Stopping test runs on page 462.
- Cancel a scheduled test run from the Execution page. See Canceling scheduled test runs on page 465.
- View all the states of the test asset by clicking the **Show in the Progress page** icon G for the test asset for which you started or scheduled the run. See Viewing the state of test assets on page 453.
- View the progress of the test from the **Progress** page. See Viewing the progress of running test assets on page 457.
- View the results, reports, and logs of the test from the **Results** page after the test completes the run. See Test results on page 513.

Related information

Resetting the configuration settings for a test run on page 461

Test run configurations on page 327

Configuring a run of a Postman test

After you added the test resources that you created and exported from Postman to the server project, you can configure a run of the Postman tests on HCL OneTest[™] Server or a remote Kubernetes cluster.

Before you begin

You must have completed the following tasks:

- Read and completed the tasks mentioned in Test run considerations for Postman tests on page 286 before you configure a test run for the Postman collections.
- Read and completed the tasks mentioned in Considerations for using a remote Kubernetes cluster on page 313, if you want to use a remote Kubernetes cluster as a location to run the test.
- Ensured that the Postman extension on HCL OneTest[™] Server is enabled before you configure a test run.
- Ensured that you are assigned a role as a *Member* or *Project Creator* in the team space. See Managing members and their roles in a team space on page 720.
- Ensured that you are assigned a role as a *Project Owner* or *Tester* in the project. See Managing access to server projects on page 734.

About this task

Important: You can run the Postman tests only on the default cluster of HCL OneTest[™] Server or a remote Kubernetes cluster. You cannot run the Postman tests on remote agents or remote Docker hosts that are registered with HCL OneTest[™] Server.

1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

- 2. Open the project that contains the test assets, and then click Execution.
- 3. Select the branch of the repository that contains the test assets.

The test assets that are contained in the selected branch of the repository are displayed in the following tabs on the **Execution** page:

Tab	Description
SUITES	Lists all suites, compound tests, JMeter tests, JUnit tests, Postman tests, Rate Sched- ules, or VU Schedules that are in the selected branch of the repository.
TESTS	Lists all API tests, functional tests, or performance tests that are in the selected branch of the repository.
ADVANCED	Lists all assets that are displayed when custom filters are applied for assets in the se- lected branch of the repository.

4. Select the tab based on the type of test assets that you want to run as indicated in the following table:

If	Then
You want to run AFT Suites, API Suites, Compound Tests, JMeter tests, JUnit tests, Postman tests, Rate Schedules, or VU Schedules,.	Click the SUITES tab.
You want to run API tests, functional tests, or perfor- mance tests.	Click the TESTS tab.
You want to find Suites and tests by using custom fil- ters, and then run Suites and tests.	Click the ADVANCED tab.

The test assets in the selected tab are displayed.

5. Identify the test asset that you want to run by performing any of the following actions:

• Scroll through the list.

i ·

Tip: You can hover over the icon in the Type column to know the type of the test asset.

Note: You can also identify the type of the asset from the icon that represents the test type as shown in the following table:

lcon	Represents	Listed in the SUITES tab	Listed in the TESTS tab	Listed in the AD- VANCED tab
-6.3-	API test		0	0
۲	Functional test		0	0
٨	Performance test		0	0
	AFT Suite	0		0
•	API Suite	0		0
0 4	Compound Test	0		0
0	HCL AppScan CodeSweep	0		0
/jMeter"	JMeter Test	0		0
Ju	JUnit Test	0		0
0	Postman test	0		0
9	Rate Schedule	0		0
9	VU Schedule	0		0

• Search for the test asset by entering any text contained in the test asset name in the Search field.

• Click the **Filter** icon **T** in the **SUITES** or **TESTS** tab to filter the displayed assets based on the asset type.

For example, select **API Suite** in the **SUITES** tab to display all API Suites or select **Functional Test** in the **TESTS** tab to display all functional tests that are in the selected branch of the repository.

- Click the **Filter** icon **W** in the **ADVANCED** tab, and then create a filter query by using the **New filter** option by performing the following steps:
 - a. Click New filter.
 - b. Enter a name for the filter.
 - c. Select an operator, and add a rule or a group of rules.
 - d. Add or enter the relevant parameters and either select or enter the condition and the criteria for the condition.

You can select a parameter from the following list:

- Type
- Test Asset Name
- Test Asset Path
- Last Result
- Next Run
- Components
- e. Save the filter query to save and apply the filter query to filter the assets based on the query.

The test assets that match the filter criteria are displayed.

 Retrieve and apply a saved filter query, if you have saved filter queries previously by performing the following steps:

Note: The filter query applied previously is selected and the assets based on that filter query are displayed. To apply a different filter query, you must have created and saved the filter query.

a. Click the **Filter** icon \mathbf{M} in the **ADVANCED** tab.

The filter queries that you created and saved are displayed.

b. Click the filter that you want to apply.

The test assets that match the filter criteria are displayed.

You have identified the test asset that you want to run.

Clicking the test name displays the **Details** panel. You can view the details of the test such as the description, the branch in the repository that contains the asset, the Git details, and the details of the commits to the repository. You can also view the history of the test runs for the specific test under the **History** tab of the **Details** panel.

Click the Execute icon in the row of the identified test asset.

The Execute test asset dialog is displayed.



- If you have configured some or all of the settings for the current test run, and you do not want to continue with those settings, you can reset the settings by clicking **Reset**.
- If you want to repeat a test run and do not want to use the saved settings from a previous run, you can reset all the saved settings to their default values by clicking Reset.
- 7. Select the version of the test resources that you want to run by completing any of the following actions:

Note: The test resources in the version can contain the test assets, datasets, AFT XML files, API environment tags, and other resources specific to projects created from any of the desktop clients.

Expand the list in the Version field, find the version of the test resources, and then select the version.

Use the following details about the version of the test resources that are displayed to identify the version that you want:

- Commit message.
- Tags labeled by the user for the version committed.
- The user who committed the version to the repository.
- Relative time of the commit. For example, 2 hours ago or 3 days ago.

The list displays the versions of the test resources committed by all users to the branch in the repository. The versions are arranged with the latest version that is committed, and then followed by the versions committed previously.

• Expand the list in the **Version** field, and then search for the version that you want to select by entering a partial or the complete commit message of that version.

The version that matches the search criteria is displayed and it is selected for the test run.

The default value for the version selected for the run is the latest version in the selected branch of the repository. If you do not select any version, then the latest version is selected for the test run.



425

Ż

- If you selected a version but you do not want to use that version in the test run, you can remove the selected version by clicking the x icon. As a result, the default version is selected for the test run.
- If you repeated a test or ran the test again from the **Results** page, then the version of the test resources that you chose for the earlier run is shown as selected. You can either retain this version or select any other version from the list. You can also remove the previous version by clicking the **x** icon.
- 8. Select the time for scheduling the test run from the following options:
 - No action is required if you want to initiate the test run immediately after you click Execute.



Important: Click Execute only after you have configured the other settings in this dialog.



Note: The default time for scheduling a run is Now.

- Select Later and configure the date and time to schedule a test run.
- Select Recurring and perform the following steps to configure recurring test runs:
 - a. Click the **Calendar** icon 📛 under **Start**, and then select the date and time at which the test run must start.
 - b. Set the frequency at which the test runs must run by entering the number in the **Repeat every** field, and then select the period from the list.

For example, if you want the test run to be run every 2 hours, enter 120, and then select the **Minute(s)** option.

- c. Set the option to end the recurring test runs from the following options:
 - Select the Never option, if you do not want the recurring test runs to end.
 - Select the **On** option, and then click the **Calendar** icon 📛. You can select the date and time after which the scheduled test runs do not run.
- 9. Enter a label for the test run that helps you to identify the test on the **Results** page.

After the test run completes, the label that you entered is displayed for the test under the **Labels** column on the **Results** page. After you have created a label, any member of the project can use that label.

The default value for the Label field is null or an empty field.

Important: The configuration that you set for the test run in the Execute test asset dialog is preserved when you run the same test again. Those changes are not visible when another user logs in to HCL OneTest[™] Server. For example, if you created new variables on the server, those variables are available only for you when the same test is run again.

If you want to run the test immediately or at the scheduled time, click **Execute**, or continue with the next step.

10. Click **Advanced**, and then enter program arguments that must be passed to the test run at run time in the **Program Arguments**, if applicable for the test.

You can enter the command options that you use when you run Postman tests by using Newman, as the program arguments.

For example, enter --verbose, if you want the details of the test run and each request sent.



Note: You must separate the arguments or variables with a white space when you enter them in the same line or start each argument or variable on a new line.

The default value for each of the fields for the advanced settings is null or an empty field.

If you want to run the test immediately or at the scheduled time, click **Execute**, or continue with the next step.

- 11. Follow the instructions if you want to change the location of a Kubernetes cluster for running the test:
 - a. Click the LOCATION tab, if it is not already open.

The **Default Cluster** is the default location where the test runs, and it is listed under the **Host** column. The information about the availability of the default location is displayed.

Important: You must have added the registered remote Kubernetes clusters to your project that are then displayed under the **Override** column:

Notes:

- If the remote clusters are not added to your project, the option No override options is displayed as the default value and the test runs in the Kubernetes cluster of HCL OneTest[™] Server.
- If remote clusters are added to your project, the added clusters are displayed along with their availability status and ownership information.
- b. Select the location where you want to run the test asset from the following options:
 - Select the Default Cluster when no remote clusters are available in your project.
 - Select the remote cluster from the list when a remote cluster is available in your project.
 - Select No override options, if you selected any remote cluster and want to revert to the Default Cluster to run the test asset.
- c. Click Execute.

The test run is initiated.

Results

You have configured and either started or scheduled a test run of a Postman test.

What to do next

You can choose to perform any of the following tasks after you have initiated or scheduled a run:

- Stop the test run at any point after the test run is initiated from the **Execution** page. See Stopping test runs on page 462.
- Cancel a scheduled test run from the Execution page. See Canceling scheduled test runs on page 465.
- View all the states of the test asset by clicking the **Show in the Progress page** icon C for the test asset for which you started or scheduled the run. See Viewing the state of test assets on page 453.
- View the progress of the test from the **Progress** page. See Viewing the progress of running test assets on page 457.
- View the results, reports, and logs of the test from the **Results** page after the test completes the run. See Test results on page 513.

Related information

Resetting the configuration settings for a test run on page 461

Test run configurations on page 327

Test run considerations for running tests on remote Docker hosts on page 296

Configuring a run of a Rate Schedule or VU Schedule

After you added the test resources that you created in the desktop client to the project, you can configure a Rate Schedule or VU Schedule to be run on HCL OneTest[™] Server or a remote Kubernetes cluster.

Before you begin

You must have completed the following tasks:

- Created Schedules in HCL OneTest[™] Performance and added the test asset to the project repository on HCL OneTest[™] Server.
- Read and completed the tasks mentioned in Prerequisites to running tests on page 277, if they apply to the test that you want to configure for a run.
- Read Considerations for using Jaeger traces in reports on page 283, if you want to configure a run and you want Jaeger to report the test results for the test.
- Read Test run considerations for schedules on page 282, if you want to configure a run for Rate Schedules or VU Schedules that have Resource Monitoring sources configured.
- Read and completed the tasks mentioned in Test run considerations for running tests on remote performance agents on page 289, if you want to use a remote agent as the location to run the test.
- Read and completed the tasks mentioned in Considerations for using a remote Kubernetes cluster on page 313, if you want to use a remote Kubernetes cluster as a location to run the test.

- Ensured that you are assigned a role as a *Member* or *Project Creator* in the team space. See Managing members and their roles in a team space on page 720.
- Ensured that you are assigned a role as a *Project Owner* or *Tester* in the project. See Managing access to server projects on page 734.
- 1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

- 2. Open the project that contains the test assets, and then click Execution.
- 3. Select the branch of the repository that contains the test assets.

The test assets that are contained in the selected branch of the repository are displayed in the following tabs on the **Execution** page:

Tab	Description					
SUITES	sts all suites, compound tests, JMeter tests, JUnit tests, Postman tests, Rate Sched- es, or VU Schedules that are in the selected branch of the repository.					
TESTS	Lists all API tests, functional tests, or performance tests that are in the selected branch of the repository.					
ADVANCED	Lists all assets that are displayed when custom filters are applied for assets in the se- lected branch of the repository.					

- 4. Identify the test asset that you want to run by performing any of the following actions:
 - Scroll through the list.

i

Tip: You can hover over the icon in the Type column to know the type of the test asset.

Note: You can also identify the type of the asset from the icon that represents the test type as shown in the following table:

lcon	Represents	Listed in the SUITES tab	Listed in the TESTS tab	Listed in the AD- VANCED tab
-63-	API test		0	0
۲	Functional test		0	0
٥	Performance test		0	0

lcon	Represents	Listed in the SUITES tab	Listed in the TESTS tab	Listed in the AD- VANCED tab
	AFT Suite	0		0
•	API Suite	0		0
00 49 (1) 00	Compound Test	0		0
0	HCL AppScan CodeSweep	0		0
/jMeter"	JMeter Test	0		0
Ju	JUnit Test	0		0
0	Postman test	0		0
9	Rate Schedule	0		0
0	VU Schedule	0		0

• Search for the test asset by entering any text contained in the test asset name in the Search field.

• Click the **Filter** icon **W** in the **SUITES** or **TESTS** tab to filter the displayed assets based on the asset type.

For example, select **API Suite** in the **SUITES** tab to display all API Suites or select **Functional Test** in the **TESTS** tab to display all functional tests that are in the selected branch of the repository.

- Click the **Filter** icon **T** in the **ADVANCED** tab, and then create a filter query by using the **New filter** option by performing the following steps:
 - a. Click New filter.
 - b. Enter a name for the filter.
 - c. Select an operator, and add a rule or a group of rules.
 - d. Add or enter the relevant parameters and either select or enter the condition and the criteria for the condition.

You can select a parameter from the following list:

- Type
- Test Asset Name

- Test Asset Path
- Last Result
- Next Run
- Components
- e. Save the filter query to save and apply the filter query to filter the assets based on the query.

The test assets that match the filter criteria are displayed.

• Retrieve and apply a saved filter query, if you have saved filter queries previously by performing the following steps:

Note: The filter query applied previously is selected and the assets based on that filter query are displayed. To apply a different filter query, you must have created and saved the filter query.

a. Click the **Filter** icon \mathbf{M} in the **ADVANCED** tab.

The filter queries that you created and saved are displayed.

b. Click the filter that you want to apply.

The test assets that match the filter criteria are displayed.

You have identified the test asset that you want to run.

Clicking the test name displays the **Details** panel. You can view the details of the test such as the description, the branch in the repository that contains the asset, the Git details, and the details of the commits to the repository. You can also view the history of the test runs for the specific test under the **History** tab of the **Details** panel.

5. Click the **Execute** icon 🕑 in the row of the identified test asset.

The Execute test asset dialog is displayed.

Notes:

- If you have configured some or all of the settings for the current test run, and you do not want to continue with those settings, you can reset the settings by clicking **Reset**.
- If you want to repeat a test run and do not want to use the saved settings from a previous run, you can reset all the saved settings to their default values by clicking **Reset**.

6. Select the version of the test resources that you want to run by completing any of the following actions:

- **Note:** The test resources in the version can contain the test assets, datasets, AFT XML files, API environment tags, and other resources specific to projects created from any of the desktop clients.
 - Expand the list in the Version field, find the version of the test resources, and then select the version.

Use the following details about the version of the test resources that are displayed to identify the version that you want:

- Commit message.
- Tags labeled by the user for the version committed.
- The user who committed the version to the repository.
- Relative time of the commit. For example, 2 hours ago or 3 days ago.

The list displays the versions of the test resources committed by all users to the branch in the repository. The versions are arranged with the latest version that is committed, and then followed by the versions committed previously.

• Expand the list in the **Version** field, and then search for the version that you want to select by entering a partial or the complete commit message of that version.

The version that matches the search criteria is displayed and it is selected for the test run.

The default value for the version selected for the run is the latest version in the selected branch of the repository. If you do not select any version, then the latest version is selected for the test run.

Notes:

- If you selected a version but you do not want to use that version in the test run, you can remove the selected version by clicking the x icon. As a result, the default version is selected for the test run.
- If you repeated a test or ran the test again from the **Results** page, then the version of the test resources that you chose for the earlier run is shown as selected. You can either retain this version or select any other version from the list. You can also remove the previous version by clicking the x icon.
- 7. Select the time for scheduling the test run from the following options:
 - No action is required if you want to initiate the test run immediately after you click Execute.

Important: Click Execute only after you have configured the other settings in this dialog.



Note: The default time for scheduling a run is Now.

- Select Later and configure the date and time to schedule a test run.
- Select Recurring and perform the following steps to configure recurring test runs:

- a. Click the **Calendar** icon to under **Start**, and then select the date and time at which the test run must start.
- b. Set the frequency at which the test runs must run by entering the number in the **Repeat every** field, and then select the period from the list.

For example, if you want the test run to be run every 2 hours, enter 120, and then select the **Minute(s)** option.

- c. Set the option to end the recurring test runs from the following options:
 - Select the Never option, if you do not want the recurring test runs to end.
 - Select the **On** option, and then click the **Calendar** icon ^(C). You can select the date and time after which the scheduled test runs do not run.
- 8. Enter a label for the test run that helps you to identify the test on the **Results** page.

After the test run completes, the label that you entered is displayed for the test under the **Labels** column on the **Results** page. After you have created a label, any member of the project can use that label.

The default value for the Label field is null or an empty field.

Important: The configuration that you set for the test run in the Execute test asset dialog is preserved when you run the same test again. Those changes are not visible when another user logs in to HCL OneTest[™] Server. For example, if you created new variables on the server, those variables are available only for you when the same test is run again.

If you want to run the test immediately or at the scheduled time, click **Execute**, or continue with the next step.

- 9. Click Advanced to make the following advanced configurations:
 - a. Enter any JVM arguments that must be passed to the test run at run time in the **JVM Arguments** field, if applicable for the test.

For example, you can set a maximum Java heap size.

b. Enter program arguments that must be passed to the test run at run time in the **Program Arguments**, if applicable for the test.

If the test that you want to configure supports the presentation of the test results data in different formats, then do the required tasks in the following scenarios:

lf	Then
You want the test results data in different supported formats.	Enter -history cisterna in the Program Argu- ments field.

lf	Then
You want to obtain the test results as a Jaeger trace.	Enter -history jaeger in the Program Arguments field.
You want the report as a test log and as a Jaeger trace.	Enter -history jaeger, testlog in the Program Ar- guments field.
Jaeger is already set as a program argument and you want to remove the Jaeger trace for your test.	Delete the -history jaeger entry in the Program Arguments field.



Note: The default report format is the test log format for the test reports.

c. Enter the environment variables that must be passed to the test run at run time in the **Environment Variables** field, if applicable for the test.

For example, enter the environment variables when the third-party libraries that are used in the test run refer to the environment variables for configuration.

Note: You must separate the arguments or variables with a white space when you enter them in the same line or start each argument or variable on a new line.

The default value for each of the fields for the advanced settings is null or an empty field.

If you want to run the test immediately or at the scheduled time, click Execute, or continue with the next step.

10. Follow the instructions if you are running a test asset that contains datasets:

- a. Click the DATA SOURCES tab, if it is not already open.
- b. Consider the following information about datasets before you select a dataset:


The default value for the datasets in the **DATA SOURCES** tab is null if the test asset did not have an associated dataset. If the asset had an associated dataset, the default value is the associated dataset.

You can utilize the dataset stored as an Excel or CSV file to override the original dataset associated with the Suite, test, or schedule. For example, when you have associated a dataset in .xlsx, .xls, or .csv format with the test or schedule in desktop clients and if you have another set of data stored in an Excel or CSV file, then you can select that dataset from the **Override** list.

- **Remember:** You must have uploaded the dataset as an Excel or CSV file into the Git repository, and ensured that both the original dataset (from the test asset) and new datasets (added to the project) have the same column names.
- c. Select the dataset that you want to use in the test run from any of the following options:
 - Select the dataset that is displayed as the default dataset when the test asset contains a single dataset.

Note: If there is only one dataset in the test asset, then that dataset is displayed as the default dataset.

Select the dataset from the list.



• Select the dataset from the **Override** list to override the dataset that was associated with the test in the desktop client.

Important: If the test contains an encrypted dataset, the Project Owner must classify it in the DATA SECURITY tab on the Project page before you can select it. You must have added datasets to your project from the Dataset page for the datasets to be displayed in the Override list.

If you want to run the test immediately or at the scheduled time, click Execute, or continue with the next step.

- 11. Follow the instructions if the test requires a variable that must be passed to the test at the test run time.
 - a. Click the VARIABLES tab, if it is not already open.
 - b. Choose one of the following methods to add the variables:
 - To add new variables manually, click the **Add Variable** icon (+), enter the name, and value of the variable.
 - To add new variables from your local computer or from the Git repository that is associated

with your server project, click the **Upload** icon and select the **Upload from local system** or **Browse from server** to select the variable file.



Note: You must have created a file with the variables before you can select the file.

The default value for the variables is null or an empty field.

If you want to run the test immediately or at the scheduled time, click Execute, or continue with the next step.

- 12. Follow the instructions if you want to override the Resource Monitoring labels in the test asset with the Resource Monitoring labels that you created in HCL OneTest[™] Server:
 - a. Click the Resource Monitoring tab.



The **Resource Monitoring** tab displays only if you enabled the **Resource Monitoring from Service** option in HCL OneTest[™] Performance when you created the test asset.

b. Click the ctrl + space bar keys, or enter the initial letter of a label to select a label in the list.



You can select or add labels only if you added the labels in the **Resource Monitoring Sources** page in HCL OneTest[™] Server.

- 13. Select any of the following steps that depends on the location to run the test:
 - If you want to run the tests on the remote agents, go to Step 14 on page 436.
 - If you want to run the tests on a Kubernetes cluster, go to Step 15 on page 437.
- 14. Follow the instructions if you want to run a test on the remote performance agent that is connected either to the default Kubernetes cluster or the remote Kubernetes cluster:
 - a. Click the LOCATION tab, if it is not already open.

The performance agents that are configured in the test asset are listed under the **Host** column. The information about the availability of the performance agent is displayed.

Note: You must have added performance agents to your project from the **Agents and Intercepts** page for the performance agents to be displayed under the **Override** column.

The default value for the performance agents is null or an empty field if no performance agents were configured in the test asset. If the test asset contains performance agents that are configured, then the default performance agent is the first item to be displayed on the list of performance agents listed in the increasing alphabetical order.

b. Select the performance agent where you want to run the test asset in the following scenarios:

lf	Then	Action
The agent that is specified in the test assets is available and no other agents are added to the project.	The agent that is specified in the test assets is displayed in the Override column.	Select the agent in the Host that is also displayed in the Override column as the location to run the test.
The agent that is specified in the test assets is not available and no other agents are added to the project.	There is no agent displayed for override in the Override column.	You cannot run the test on the agent. You must wait until the agent is available to run the test on the agent.
The agent that is specified in the test assets is available and there are other agents that are added to the project.	Agents that have capabilities that match with the agent capa- bilities specified in the test as- sets are listed in the Override column as follows: • Agents with capabilities that best match the ca- pabilities in the agent in the asset are at the top of the list. • Agents with capabilities that do not match with the capabilities in the agent in the asset are listed subsequently. You can find details of both agents for the matching capa- bilities when you hover over the agent in the Override column.	 Perform any of the following actions: Select the agent in the Host that is also displayed in the Override column as the location to run the test. Select an agent in the Override column as the location to run the test.

c. Click Execute.

The test run is initiated.

15. Follow the instructions if you want to change the location of a Kubernetes cluster for running the test:

a. Click the LOCATION tab, if it is not already open.

The **Default Cluster** is the default location where the test runs, and it is listed under the **Host** column. The information about the availability of the default location is displayed. **Important:** You must have added the following remote hosts to your project that are then displayed under the **Override** column:

- Docker hosts that are registered with HCL OneTest[™] Server.
- Kubernetes clusters that are registered with a team space.

Notes:

- If the remote Docker hosts or clusters are not added to your project, the option No
 override options is displayed as the default value and the test runs in the Kubernetes
 cluster of HCL OneTest[™] Server.
- If remote Docker hosts or clusters are added to your project, the added Docker hosts or clusters are displayed along with their availability status and ownership information.

b. Select the location where you want to run the test asset from the following options:

- Select the **Default Cluster** when no remote Docker hosts or clusters are available in your project.
- Select the remote Docker host or cluster from the list when a remote Docker host or cluster is available in your project.
- Select No override options, if you selected any remote Docker host or cluster and want to revert to the Default Cluster to run the test asset.

c. Click Execute.

The test run is initiated.

Results

You have configured and either started or scheduled a test run of a Rate Schedule or VU Schedule.

What to do next

You can choose to perform any of the following tasks after you have initiated or scheduled a run:

- Stop the test run at any point after the test run is initiated from the **Execution** page. See Stopping test runs on page 462.
- Cancel a scheduled test run from the Execution page. See Canceling scheduled test runs on page 465.
- View all the states of the test asset by clicking the **Show in the Progress page** icon C for the test asset for which you started or scheduled the run. See Viewing the state of test assets on page 453.
- View the progress of the test from the **Progress** page. See Viewing the progress of running test assets on page 457.
- View the results, reports, and logs of the test from the **Results** page after the test completes the run. See Test results on page 513.

Related information

Resetting the configuration settings for a test run on page 461

Test run configurations on page 327

Running tests by using Data Fabrication

Starting from V10.0.2, if a test or schedule is associated with a dataset, you can replace the dataset at run time with the schema created from the **Data Fabrication** page.

Before you begin

You must have completed the following tasks:

- · Created a dataset and associated it with a test in desktop clients and added to the Git repository.
- Created a project in HCL OneTest[™] Server. See Test assets and a server project on page 724.
- Configured the repository that contains the test assets in your project. See Adding repositories to a server project on page 728.
- Created a schema from the Data Fabrication page. See Schema fabrication on page 165.

About this task

In HCL OneTest[™] Server, from the **Data Fabrication** page, you can create a schema that can be used while running a test or schedule that is associated with a dataset. For example, after the recording, a test is generated that captures interactions between the client and the server. When you run this test, it uses the same data that you used during recording. For example, if you want to test the application with random test data, you can override the dataset being used in the test or schedule with a schema that you created from the **Data Fabrication** page of HCL OneTest[™] Server.

Whenever you generate test data to perform application testing, the generated data is different. You can produce the same set of data multiple times by setting the seed value. For example, you have used seed value as 1 to generate test data. When you run the test or schedule by providing the seed value as 1, the same set of data is used for testing instead of different data.



Note: You must ensure that the original dataset that is associated with a test or schedule and a schema that you have created have the same column names.

- 1. Initiate the test run on the **Execution** page.
- 2. Create or pick a label for the test run to identify the run.

After the run completes, the label is displayed against the run on the **Results** page.

3. Click the DATA SOURCES tab and perform the following sub-steps:

a. Select a schema to override the dataset that was associated with a test or schedule in the desktop client.



Note: If the dataset and schema have the same column names, only then the Override dropdown list shows the existing schema names.

- b. Enter the number of records that you want to generate in the Number of rows field.
- c. Optional. Enter a seed value in the Seed value (optional) field.

The seed value acts as an instance of random data that can be repeated if required. By default, the seed value is blank. Alternatively, you can use the up-down control button to increment or decrement the Number of rows and Seed value.



Note: You must provide a value in the Number of rows field. Otherwise, you cannot run the test or schedule.

ENVIRONMENT	DATA SOURC		VAI	RIABLES	LOCA	ATION
Data source		Override				
PBW_1002_DS_Encrypt 'PT10_199/Datasets/PBW_1002_DS_En.csv		Excel_Schema/Excel_Group Set override options (required)				
		Number of ro	ows	Seed value	e (optional)	
		5	-	1	÷	Set
Advanced Settings				Canc		Execute

4. Click Set, and then Execute.

What to do next

You can monitor a test run and check the logs to ensure that the data is taken from the schema instead of the dataset when running the test.

Related information

Test assets and a server project on page 724

Configuration of test runs in a GitHub Actions Workflow

You can configure test runs of test resources that are in a project repository of HCL OneTest[™] Server in a GitHub Actions Workflow. You can choose to run test resources that are in your server project in the GitHub Workflow when you do not want to run the test resources without opening the HCL OneTest[™] Server project.

Before you configure a test run for any test resources that are in a project repository of HCL OneTest[™] Server, you must complete certain tasks. See Prerequisites to run tests in a GitHub Actions Workflow on page 441.

After you complete the prerequisite tasks, you can proceed to configure a test run in a GitHub Workflow. See Configuring a test run in a GitHub Actions Workflow on page 442.

Prerequisites to run tests in a GitHub Actions Workflow

Before you configure a test run for any test resources that are in a project repository of HCL OneTest[™] Server, you must complete certain tasks to run the test resources in a GitHub Actions Workflow.

You must be familiar with creating projects and running test resources from HCL OneTest™ Server.

You must complete the following tasks to set up and use HCL OneTest[™] Server:

- Install HCL OneTest[™] Server. See Installation of the server software on page 36.
- Possess valid licenses to use HCL OneTest[™] Server. See Management of licenses in HCL OneTest Server on page 119.
- Create a project on HCL OneTest[™] Server. See Adding a project on page 727.
- Add a repository that contains test resources to the project repository. See Adding repositories to a server project on page 728.
- Generate the Offline User Token on HCL OneTest[™] Server that is required for connecting to HCL OneTest[™] Server from another application such as the GitHub Action. See Managing access to HCL OneTest Server on page 708.
- Open the project to view the details of the test resources that you want to run in a GitHub Actions Workflow.
 You must make a note of the test resource details from the Execution page of HCL OneTest[™] Server.

You must note the following details of the test resource that are to be provided in the YAML file for the GitHub Action:

- ∘ The URL of the HCL OneTest[™] Server instance.
- ∘ The name of the team space that contains the project on HCL OneTest[™] Server.
- ∘ The name of the project on HCL OneTest[™] Server that contains the test resources.
- $\circ\,$ The branch name of the project repository that contains the test resources.
- $\,\circ\,$ The ID of the test resource.

You must complete the following tasks outside of HCL OneTest[™] Server:

• Create an empty Git repository on any GitHub Enterprise server, if you do not already use Git repositories to store the test resources that you create. For more information about creating Git repositories, refer to Creating a new repository.

If you already use Git repositories to store test resources created, you can use the same Git repositories.



Note: You must have the required privileges in the Git repository to create a GitHub Actions Workflow.

• Enable the GitHub Actions option in the Git repository, if it is not available as an option to use. For more information about enabling the GitHub Actions, refer to Learn about GitHub Actions.

You can continue to configure a run of a test, see Configuring a test run in a GitHub Actions Workflow on page 442.

Configuring a test run in a GitHub Actions Workflow

After you complete the prerequisite tasks to run tests in a GitHub Actions Workflow, you can configure the test run in a GitHub Actions Workflow.

Before you begin

You must have completed the following tasks:

- Completed the tasks that are mentioned in Prerequisites to run tests in a GitHub Actions Workflow on page 441.
- Ensured that you are assigned a role as a *Project Owner* or *Tester* in the project. See Managing access to server projects on page 734.
- 1. Perform the following steps to open the Git repository that you use or created, which has the GitHub Actions option enabled:
 - a. Open the Git repository on your GitHub Enterprise server.
 - b. Create a folder with the name as .github/workflows in the root folder of the repository.
 - c. Create an empty YAML file in the <code>.github/workflows</code> folder.

The YAML file is used to define the GitHub Action in the Actions Workflow.

- 2. Perform the following steps to define the YAML file for the GitHub Action:
 - a. Open the GitHub Marketplace (https://github.com/marketplace?type=) in a web browser.
 - b. Search for HCL OneTest Server GitHub Action.
 - c. Open the GitHub Action.

- d. Read through the information provided.
- e. Copy the contents of the YAML file that is provided in the example by clicking the copy icon \square .
- f. Open the YAML file that is in the .github/workflows folder of your repository and paste the copied contents.
- g. Enter the valid details as values for the required attributes in the YAML file by following the actions in the following table:

Attribute	Action		
Required attributes			
serverURL	Specify the URL of the HCL OneTest [™] Server instance.		
offlineToken	Specify the Offline User Token that is generated by HCL OneTest [™] Server.		
teamspace	Specify the name of the team space that contains your project on HCL OneTest [™] Server.		
project	Specify the name of your project on HCL OneTest [™] Server.		
branch	Specify the name of the branch in the repository that contains the test re- sources, which can be found in the Details pane of the test resource on the Execution page.		
assetId	Specify the ID of the test resource, which can be found under the Git de- tails section in the Details pane of the test resource on the Execution page.		
Optional attributes			
environment	Specify the environment that is configured in the test.		
datasets	Specify the dataset that must be used at test run time, which replaces the dataset that is configured in a test.		
labels	Specify text labels to identify a specific test result when the test run is complete.		
secretsCollection	Specify the name of the secret collection that is configured in a test.		
variables	Specify the name of the variable and its value if your test requires variables during the test run time.		
	Note: You can add multiple variables that are separated by a semi- colon.		

h. Save the YAML file.

- 3. Perform the following steps to set up a Runner for the GitHub Action in GitHub:
 - a. Click the Settings icon 🧐.
 - b. Click Actions > Runners > New self-hosted runner.
 - c. Follow the on-screen instructions to set up a self-hosted runner on your computer.

After the runner is installed on your computer, you must verify that the runner is ready to run jobs in the GitHub Actions Workflow and is in the *Active* state. The runner is listed in the **Runners** pane in the Git repository.

- 4. Perform the following steps to start the GitHub Action in the Workflow:
 - a. Click the Actions option in the Git repository.

The GitHub Action that you configured in the YAML file for HCL OneTest[™] Server is displayed as an **Action** under **Workflows**.

b. Click the HCL OneTest Server Action, and then click Run workflow.

Results

You have configured and run a resource that is in your project on HCL OneTest[™] Server in a GitHub Action Workflow.

What to do next

You can perform any of the following tasks on the Git repository page by clicking the job that was completed:

- View the status of the test run by expanding the **Execute test** section.
- View the links to the test results and reports listed in the **Execute test** section.

You can perform any of the following tasks from HCL OneTest[™] Server:

- Stop the test run at any point after the test run is initiated from the **Execution** page. See Stopping test runs on page 462.
- View the progress of the test from the **Progress** page. See Viewing the progress of running test assets on page 457.
- View the results, reports, and logs of the test from the **Results** page after the test completes the run. See Test results on page 513.

Configuration of a scan of an application code

You can use HCL OneTest[™] Server to scan your application code for security vulnerabilities similar to using the HCL AppScan CodeSweep plugin to scan code in Visual Studio.

HCL OneTest[™] Server is enabled to support scanning of your application code that is in a remote repository.

Before you commit your application code to the remote repository, you must complete certain tasks. See Considerations to scan an application code on page 445.

After you commit the assets to the remote repository, you must complete the following tasks:

- 1. Log in to HCL OneTest[™] Server.
- 2. Open the project in your team space.
- 3. Add the remote repository to your project.
- 4. Open the Execution page, and then run a scan of the asset.

For detailed instructions, see Configuring a run to scan the application code on page 447.

Considerations to scan an application code

When you want to use HCL OneTest[™] Server to run a scan of the application code for security vulnerabilities, you must read the considerations that you must take into account and complete certain tasks.

Before you can run a scan of the application code on HCL OneTest[™] Server, you must have completed the following tasks:

- · Created a file that has the following characteristics:
 - \circ The format of the file must be <code>yaml</code>.
 - The name must be .codesweep.
- Committed the following assets or resources to the remote repository:
 - \circ The .codesweep file.
 - The application code can either be in the root directory or another folder in the root directory.



Note: The default root directory is the directory that contains the .codesweep file.

You can specify the following information in the .codesweep file:

- The name of the asset that must be displayed as the test asset in the **Execution** page of HCL OneTest[™] Server. The name must be specified at the first level in the file as the value of the **name** attribute.
- Optionally, the name of folders that contain the application code.

All files and folders in the root directory are scanned as the default action, if no files or folders are specified under the **folders** attribute.

You can specify the files or folders to scan by using any of the following options:

- Specify the files or folders by using an XML file that is in the same format as the HCL AppScan IRX file.
- Specify the files or folders in the .codesweep file under the **includes** or **excludes** attributes under the **folders** attribute.

- Optionally, you can specify the name of files or folders that must be included in the scan.
 You must specify the files or folders as the value of the **includes** attribute under the **folders** attribute.
- Optionally, you can specify the name of files or folders that contain the application code that need not be scanned. You must specify the files or folders as the value of the **excludes** attribute under the **folders** attribute.



Note: You cannot use *wildcard* characters to indicate the files or folders anywhere in the .codesweep file.

- Optionally, you can specify the rules that are to be ignored in the scan. You can specify the rules by using any of the following options:
 - Specify a file, which is a copy of ~/appscan/custom_scanners_service_ignore.json that is created by the CodeSweep plugin for Visual Studio. With this method, you can reuse the preferences that you have configured in your development environment.
 - Specify a list of rules. Each rule is defined by a name and a language identifier.
- Optionally, you can specify the criteria for attributes and their values that specify the verdict of the scan and the range for the security errors in the code.

For example, you can consider the following details:

Where	ls
The name of the asset that is to be displayed on the Exe - cution page	mycode
The folder that contains the code to be scanned	use_code
The folder that contains the code that is to be excluded in the scan	do_not_use_code
The value of the attribute Verdict	
The range for the security errors is classified as follows: • max-high • max-medium • max-low	The conditions for a <i>pass</i> verdict are as follows: • 0 • 10 • 100

The contents of the .codesweep file is as follows:

```
- do_not_use_code

ignore: # lgnore rules, Optional

file: custom_scanners_service_ignore.json # json file coming from visual code, Optional

rules: #list of rules to ignore, Optional

- name: com.ouncelabs.languagelite.nodejs.Rules.NodeJS_PrivateDataExposedviaHTTPURL # Name,

Required

language: NodeJS # Language, Required

- name: com.ouncelabs.languagelite.nodejs.Rules.NodeJS_PrivateDataExposedviaHTTP # Name,

Required

language: NodeJS # Language, Required

verdict: # PASS verdict, Optional

max-high: 0 # default=0, Optional

max-medium: 10 # default=0, Optional

max-low: 100 # default=-1 (no limit), Optional
```

You can continue to configure a run of a scan of the code, see Configuring a run to scan the application code on page 447.

Restriction: You cannot run the test assets on a remote Docker host.

Related information

Configuration of a scan of an application code on page 444

Configuring a run to scan the application code

After you added the assets in the remote repository to a project in your team space, you can configure a run to scan the application code specified in the codesweep file by using the execution service on HCL OneTest[™] Server.

Before you begin

You must have completed the following tasks:

- Read and completed the tasks mentioned in Considerations to scan an application code on page 445.
- Read and completed the tasks mentioned in Considerations for using a remote Kubernetes cluster on page 313, if you want to use a remote Kubernetes cluster as a location to run the test.
- Ensured that you are assigned a role as a *Member* or *Project Creator* in the team space. See Managing members and their roles in a team space on page 720.
- Ensured that you are assigned a role as a *Project Owner* or *Tester* in the project. See Managing access to server projects on page 734.
- 1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

- 2. Open the project that contains the test assets, and then click Execution.
- 3. Select the branch of the repository that contains the test assets.

The test assets that are contained in the selected branch of the repository are displayed in the following tabs on the Execution page:

Tab	Description
SUITES	Lists all suites, compound tests, JMeter tests, JUnit tests, Postman tests, Rate Sched- ules, or VU Schedules that are in the selected branch of the repository.
TESTS	Lists all API tests, functional tests, or performance tests that are in the selected branch of the repository.
ADVANCED	Lists all assets that are displayed when custom filters are applied for assets in the se- lected branch of the repository.

4. Identify the test asset or resource that you want to run by performing any of the following actions:

• Scroll through the list.

i

Tip: You can hover over the icon in the Type column to know the type of the test asset.

Note: You can also identify the type of the asset from the icon that represents the test type as shown in the following table:

lcon	Represents	Listed in the SUITES tab	Listed in the TESTS tab	Listed in the AD- VANCED tab
-63-	API test		0	0
۲	Functional test		0	0
٢	Performance test		0	0
	AFT Suite	0		0
•	API Suite	0		0
© ↔ () ©	Compound Test	0		0
0	HCL AppScan CodeSweep	0		0
/jMeter"	JMeter Test	0		0

lcon	Represents	Listed Listed in the in the SUITES TESTS tab tab	the AD-
Ju	JUnit Test	0	0
0	Postman test	0	0
9	Rate Schedule	0	0
9	VU Schedule	0	0

- Search for the test asset or resource by entering any text contained in the test asset or resource name in the **Search** field.
- Click the **Filter** icon **W** in the **SUITES** or **TESTS** tab to filter the displayed assets based on the asset type.

For example, select **API Suite** in the **SUITES** tab to display all API Suites or select **Functional Test** in the **TESTS** tab to display all functional tests in the selected branch of the repository.

- Click the **Filter** icon **W** in the **ADVANCED** tab, and then create a filter query by using the **New filter** option by performing the following steps:
 - a. Click New filter.
 - b. Enter a name for the filter.
 - c. Select an operator, and add a rule, or a group of rules.
 - d. Add or enter the relevant parameters and either select or enter the condition and the criteria for the condition.

You can select a parameter from the following list:

- Type
- Test Asset Name
- Test Asset Path
- Last Result
- Next Run
- Components
- e. Save the filter query to save and apply the filter query to filter the assets based on the query.

The test assets that match the filter criteria are displayed.

 Retrieve and apply a saved filter query, if you have saved filter queries previously by performing the following steps:

- Note: The filter query applied previously is selected and the assets based on that filter query are displayed. To apply a different filter query, you must have created and saved the filter query.
 - a. Click the **Filter** icon \mathbf{M} in the **ADVANCED** tab.

The filter queries that you created and saved are displayed.

b. Click the filter that you want to apply.

The test assets that match the filter criteria are displayed.

5. Click the **Execute** icon 🕑 in the row of the identified test asset.

The Execute test asset dialog is displayed.

Notes:

- If you have configured some or all of the settings for the current test run, and you do not want to continue with those settings, you can reset the settings by clicking **Reset**.
- If you want to repeat a test run and do not want to use the saved settings from a previous run, you can reset all the saved settings to their default values by clicking Reset.
- 6. Select the version of the test resources that you want to run by completing any of the following actions:
 - Expand the list in the Version field, find the version of the test resources, and then select the version.

Use the following details about the version of the test resources that are displayed to identify the version that you want:

- Commit message.
- Tags labeled by the user for the version committed.
- The user who committed the version to the repository.
- Relative time of the commit. For example, 2 hours ago or 3 days ago.

The list displays the versions of the test resources committed by all users to the branch in the repository. The versions are arranged with the latest version that is committed, and then followed by the versions committed previously.

• Expand the list in the **Version** field, and then search for the version that you want to select by entering a partial or the complete commit message of that version.

The version that matches the search criteria is displayed and it is selected for the test run.

The default value for the version selected for the run is the latest version in the selected branch of the repository. If you do not select any version, then the latest version is selected for the test run.

Notes:

- If you selected a version but you do not want to use that version in the test run, you can remove the selected version by clicking the x icon. As a result, the default version is selected for the test run.
- If you repeated a test or ran the test again from the **Results** page, then the version of the test resources that you chose for the earlier run is shown as selected. You can either retain this version or select any other version from the list. You can also remove the previous version by clicking the x icon.
- 7. Select the time for scheduling the test run from the following options:
 - No action is required if you want to initiate the test run immediately after you click Execute.



Important: Click Execute only after you have configured the other settings in this dialog.



Note: The default time for scheduling a run is Now.

- Select Later and configure the date and time to schedule a test run.
- \circ Select $\mbox{Recurring}$ and perform the following steps to configure recurring test runs:
 - a. Click the **Calendar** icon 📛 under **Start**, and then select the date and time at which the test run must start.
 - b. Set the frequency at which the test runs must run by entering the number in the **Repeat every** field, and then select the period from the list.

For example, if you want the test run to be run every 2 hours, enter 120, and then select the **Minute(s)** option.

- c. Set the option to end the recurring test runs from the following options:
 - Select the Never option, if you do not want the recurring test runs to end.
 - Select the **On** option, and then click the **Calendar** icon .
 You can select the date and time after which the scheduled test runs do not run.
- 8. Enter a label for the test run that helps you to identify the test on the **Results** page.

After the test run completes, the label that you entered is displayed for the test under the **Labels** column on the **Results** page. After you have created a label, any member of the project can use that label.

The default value for the Label field is null or an empty field.

Important: The configuration that you set for the test run in the Execute test asset dialog is preserved when you run the same test again. Those changes are not visible when another user logs in to HCL I

OneTest™ Server. For example, if you created new variables on the server, those variables are available only for you when the same test is run again.

If you want to run the test immediately or at the scheduled time, click **Execute**, or continue with the next step.

- 9. Follow the instructions if you want to change the location of a Kubernetes cluster for running the test:
 - a. Click the LOCATION tab, if it is not already open.

The Default Cluster is the default location where the test runs, and it is listed under the Host column. The information about the availability of the default location is displayed.

Important: You must have added the registered remote Kubernetes clusters to your project that are then displayed under the **Override** column:

Notes:

- If the remote clusters are not added to your project, the option No override options is displayed as the default value and the test runs in the Kubernetes cluster of HCL OneTest[™] Server.
- If remote clusters are added to your project, the added clusters are displayed along with their availability status and ownership information.

b. Select the location where you want to run the test asset from the following options:

- Select the Default Cluster when no remote clusters are available in your project.
- Select the remote cluster from the list when a remote cluster is available in your project.
- Select No override options, if you selected any remote cluster and want to revert to the Default Cluster to run the test asset.
- c. Click Execute.

The test run is initiated.

Results

You have configured and either started or scheduled a run of a scan of the application code that is specified in the codesweep file.

What to do next

You can choose to perform any of the following tasks after you have initiated or scheduled a run:

- Stop the test run at any point after the test run is initiated from the Execution page. See Stopping test runs on page 462.
- Cancel a scheduled test run from the Execution page. See Canceling scheduled test runs on page 465.

- View all the states of the test asset by clicking the **Show in the Progress page** icon C for the test asset for which you started or scheduled the run. See Viewing the state of test assets on page 453.
- View the progress of the test from the **Progress** page. See Viewing the progress of running test assets on page 457.
- View the results, reports, and logs of the test from the **Results** page after the test completes the run. See Test results on page 513.

Related information

Resetting the configuration settings for a test run on page 461 Configuration of a scan of an application code on page 444 Test run configurations on page 327

Management of running tests

Find information about the tasks that you can perform on a test that you configured for a run either while it runs or after it completes the run.

Viewing the state of test assets

After you initiate or schedule a test run on the Execution page, you can view the state of the test assets on the

Progress page by clicking the **Show in the Progress page** icon ^C that is enabled for that test asset on the **Execution** page. You can view all the states of the test asset from the past hour such as In transition, Running, Scheduled, Completed, OF Stopped.

Before you begin

You must have initiated runs of the test assets in your project from the Execution page.

Note: The Show in the Progress page icon is enabled for the test asset only if a run of the test asset is either started or scheduled.

- 1. Click Execution, if you are not already on the Execution page.
- 2. Select the branch of the repository that contains the test assets.

The test assets that are contained in the selected branch of the repository are displayed in the following tabs on the **Execution** page:

Tab	Description
SUITES	Lists all suites, compound tests, JMeter tests, JUnit tests, Postman tests, Rate Sched- ules, or VU Schedules that are in the selected branch of the repository.

Tab	Description
TESTS	Lists all API tests, functional tests, or performance tests that are in the selected branch of the repository.
ADVANCED	Lists all assets that are displayed when custom filters are applied for assets in the se- lected branch of the repository.

- 3. Identify the test asset or resource that you want to run by performing any of the following actions:
 - Scroll through the list.

i

Tip: You can hover over the icon in the **Type** column to know the type of the test asset.

Note: You can also identify the type of the asset from the icon that represents the test type as shown in the following table:

Icon	Represents	Listed in the SUITES tab	Listed in the TESTS tab	Listed in the AD- VANCED tab
-63-	API test		0	0
۲	Functional test		0	0
٢	Performance test		0	0
	AFT Suite	0		0
40	API Suite	0		0
<u>ð</u> ⊕	Compound Test	0		0
0	HCL AppScan CodeSweep	0		0
/JMeter*	JMeter Test	0		0
Ju	JUnit Test	0		0
0	Postman test	0		0
9	Rate Schedule	0		0

~	lcon	Represents	Listed in the SUITES tab	Listed in the TESTS tab	Listed in the AD- VANCED tab
	9	VU Schedule	0		0

- Search for the test asset or resource by entering any text contained in the test asset or resource name in the Search field.
- Click the **Filter** icon **W** in the **SUITES** or **TESTS** tab to filter the displayed assets based on the asset type.

For example, select **API Suite** in the **SUITES** tab to display all API Suites or select **Functional Test** in the **TESTS** tab to display all functional tests in the selected branch of the repository.

- Click the **Filter** icon **W** in the **ADVANCED** tab, and then create a filter query by using the **New filter** option by performing the following steps:
 - a. Click New filter.
 - b. Enter a name for the filter.
 - c. Select an operator, and add a rule, or a group of rules.
 - d. Add or enter the relevant parameters and either select or enter the condition and the criteria for the condition.

You can select a parameter from the following list:

- Type
- Test Asset Name
- Test Asset Path
- Last Result
- Next Run
- Components
- e. Save the filter query to save and apply the filter query to filter the assets based on the query.

The test assets that match the filter criteria are displayed.

 Retrieve and apply a saved filter query, if you have saved filter queries previously by performing the following steps:

- Note: The filter query applied previously is selected and the assets based on that filter query are displayed. To apply a different filter query, you must have created and saved the filter query.
 - a. Click the **Filter** icon \mathbf{M} in the **ADVANCED** tab.

The filter queries that you created and saved are displayed.

b. Click the filter that you want to apply.

The test assets that match the filter criteria are displayed.

4. Click the Show in the Progress page icon \square in the Actions column of the test asset.

The **Progress** page is displayed with the following details:

- The different states of the test asset runs that were initiated or completed in the past hour are displayed as follows:
 - In transition
 - Running
 - Completed
 - Stopped by User
 - Canceled
- The ID of the selected test asset is applied as a filter and is displayed in the filter row.

The applied filter is removed along with the displayed items for this filter when you perform any of the following actions on the **Progress** page:

- You click Hide inactive, and then click Show all.
- You visit any other page in the Navigation pane and return to the **Progress** page.

Results

You have viewed all the states of a specific test asset runs that were initiated during the past hour.

What to do next

You can choose to perform any of the following tasks from the Progress page:

- Stop test assets that are running. See Stopping test runs on page 462.
- Cancel scheduled runs. See Canceling scheduled test runs on page 465.
- View the results or the execution log of the test asset from the **Actions** column by clicking the **Open action menu** icon See Checking logs on page 460.
- View the results, reports, and logs of the completed test run from the **Results** page. See Test results on page 513.

Viewing the progress of running test assets

After you initiate or schedule a test run on the **Execution** page, you can view the progress of the test assets that are running or scheduled to run, from the **Progress** page. You can also view the test assets that have completed their run, are stopped or canceled, during the past hour.

Before you begin

You must have initiated runs of the test assets in your project from the Execution page.

1. Open your project and click Progress.

Any one of the following views is displayed:

- No test assets are displayed in the **Progress** page if there are no test assets that are running, scheduled to run, or have completed their run in the past hour.
- Test assets in your project that are in any of the following states are listed:
 - Running
 - Scheduled
 - Completed
 - Stopped
 - Canceled
- No test assets are displayed but the option **Show all** is enabled. You can click **Show all** to display the test assets that ran in the past hour. Test assets that were hidden from the display when **Hide inactive** was clicked are displayed.
- Note: Test assets are automatically removed from the display after 60 minutes of being added to the Progress page. You can hide the test assets from the display by clicking Hide inactive, so that you can view only the test assets that were added to the Progress page in the past hour. You cannot use the Progress page to view the history of test assets that were run from the Execution page.

2. Identify the test asset by performing any of the following actions:

- Identify the test asset or resource by scrolling through the list.
- Search for the test asset by entering any text contained in the test asset name in the Search text box.
- Create a filter query by using the New filter option by performing the following steps:
 - a. Click New filter.
 - b. Select an operator, and add a rule, or a group of rules.
 - c. Add or enter the relevant parameters and either select or enter the condition and the criteria for the condition.

You can select a parameter from the following list:

- Type
- Name
- Started by

- Started on
- Finished on
- Status
- Verdict
- d. Apply the filter query to filter the assets based on the query.

The test assets that match the filter criteria are displayed.

- e. Save the filter query by performing the following steps, if you want to reuse the filter query later:
 - i. Click Save.
 - ii. Enter a name for the filter query.
 - iii. Click Save.


• Retrieve a saved filter, if you have saved filter queries earlier by performing the following steps:

Note: To open the filter query, you must have created and saved a filter query.

- a. Click the **Open filters** icon \equiv .
- b. Select the saved filter in the Filters dialog.
- c. Click Apply to apply the filter.

The test assets that match the filter criteria are displayed.

- Sort the test assets by the user who started the test by clicking the Started by column header, and find the test asset listed against your name.
- Sort the test assets by the type of the test assets by clicking the Type column header, and find the test asset type you ran or scheduled.
- Click Hide inactive to only display the test assets that are running or scheduled to run. This action removes all completed, canceled, stopped, or failed test assets from the display.



- 🛆 items in the column are sorted in the ascending order or with the earliest record on top.
- 🔽 items in the column are sorted in the descending order or with the latest record on top.

You can view the following details of the test assets on the Progress page:

Column head- er	Description
Туре	Displays the icon for the type of the test asset.

Column head- er	Description
Name	Displays the name of the test asset added to the project from the Git repository. Clicking the test name displays the Details panel. You can view the details of the test such as the description, the branch in the repository that contains the asset, the Git details, and the details of the commits to the repository. You can also view the history of the test runs for the specific test under the History tab of the Details panel.
Started by	Displays the name of the user who started the run of the test asset.
Started on	Displays the date and time when the test run was started.
Finished on	Displays the date and time when the test run completed the run.
Status	Displays the state of the test asset progressively. For example, after the run is in the Initiated state, it moves on to the Running State and ends in its final state depending on the verdict of the test run as either completed, Failed, Or Incon- clusive. If the test run is stopped or a scheduled run is canceled, the status displayed is stopped by User for a stopped run or Canceled for a canceled test.

From the Actions column, you can perform the following operations on your test asset:

- Stop a run.
- Cancel a scheduled run.
- Cancel scheduled recurring test runs.
- View the test log.
- \circ View the result of the test asset on the Results page.
- Query the test result data.

Results

You have viewed the progress of the test assets that you ran from the Execution page.

What to do next

You can choose to perform any of the following tasks from the Progress page:

- Stop test assets that are running. See Stopping test runs on page 462.
- Cancel scheduled runs. See Canceling scheduled test runs on page 465.

- View the results or the execution log of the test asset from the **Actions** column by clicking the **Open action menu** icon See Checking logs on page 460.
- View the results, reports, and logs of the completed test run from the **Results** page. See Test results on page 513.
- Query the test results data. See Test log queries on page 543.

Checking logs

To verify how the test ran or to debug test run failure, you can check the Test Log and Execution log.

About this task

The Test Log displays the interaction between HCL OneTest[™] Server and the application or system under test. After the test run completes, the verdict of the run can be *Pass*, *Fail*, or *Inconclusive*. If the verdict of the run is Pass, the Test Log is available in the **Results** page.

	I	cmptest-1 WebUIProjectCustomCod e/CompoundTests/cmpte st-1.testsuite	cmptest-1	uatester	00:02	:28	Complete	Pass
		DETAILS				Reports		
		Git Repo	git@gson sample.git	/ serve	:r-	Statistic Test Log	cs Report	
		Git Branch	master			Mobile a	and Web UI Repo	ort
		Git Path	WebUIProjectCustomCo 1.testsuite	ode/CompoundTests/cmpt	est-			

The Execution log displays the console messages of the run time process that runs the test. This log is useful in determining the cause of the failure if the verdict of the run is *Fail* or *Inconclusive*. You can view the Execution log from the **Progress** page.

Viewing the Test Log

- 1. Go to the **Results** page and identify the test that you ran.
- 2. Click the test so that the **Reports** panel is displayed.
- 3. Click the Test Log in the Reports panel.

The Test Log is displayed in a browser window.

Viewing the Execution log

- 4. Go to the **Progress** page and identify the test that is in the *Running* state.
- 5. Click the Open action menu icon.
- 6. Click Execution log.

The Execution log is displayed in a browser window.

Related information Test run configurations on page 327

Resetting the configuration settings for a test run

When you are configuring a test run either as a first-run or when repeating the run, and you do not want to proceed with the settings configured or saved for the test run, you can reset the configuration settings. Resetting the configuration reverts all the settings to their default values for the test run.

Before you begin

You must be a member of the project with the Owner or Tester role to run the tests.

You must ensure that you have the **Execute test asset** dialog is displayed before you proceed with resetting the configuration settings for the test run.

About this task

You can reset the configuration settings when you are configuring a test run either for its first run or when you are repeating the test run.

1. Click **Reset** in the **Execute test asset** dialog at any point when you want to reset the configuration settings for the test run.



- If you have configured some or all of the settings for the current test run and you do not want to continue with those settings, clicking **Reset** resets the settings to their default values.
- If you are repeating a test run and do not want to use the saved settings from a previous run, clicking **Reset** reverts all the saved settings to their default values.

The settings in the **Execute test asset** dialog are reset to their default values.

2. Use the following table to find the default values for each of the settings in the Execute test asset dialog:

Window or Tab	Field or Setting	Default value is
Execute test asset	Scheduling the test run	Now is selected.
Execute test asset	Label for settings	Null or empty field.
Advanced	JVM Arguments	Null or empty field.
	Program Arguments	Null or empty field.
	Environment Variables	Null or empty field.

Window or Tab	Field or Setting	Default value is		
ENVIRONMENT tab	API test environment	The environment configured in the test asset.		
	Secrets collection	Null or empty field.		
DATA SOURCES tab	Override list	Null or empty field if the asset has no dataset.		
		The dataset in the test asset if the asset has one dataset.		
		The first dataset on the list of datasets, which are listed in the increasing alphabetical order, if the as- set has multiple datasets.		
VARIABLES tab		Null or empty field.		
LOCATION tab	Agents	Null or empty field if the asset has no agents config- ured.		
		The first agent on the list of agents, which are listed in the increasing alphabetical order, if the asset has multiple agents configured.		
	Docker host	Internal Docker host if no remote Docker hosts or clusters are added.		
		No override options if other Docker hosts or clus- ters are saved in previous runs.		

What to do next

You can complete configuring the settings that you want for the test run. See Test run configurations on page 327.

Stopping test runs

You might want to stop a test run or multiple tests that are running when you realized that you did not configure all the settings or you want to change a few settings for the test runs.

Before you begin

You must have initiated a run for one or multiple test assets from the **Execution** page.

About this task

You can stop either a running test or multiple running tests from the **Progress** page. You can stop the test if it is in either the In transition or Running state. You cannot stop the test run if the test has already completed its run.

1. Go to the **Progress** page and identify the tests in any of the following ways that you want to stop:

You can select the tests that satisfy the following conditions:

- The test must be either in the In transition or Running state.
- \circ The **Stop execution** icon \bigotimes in the **Actions** column must be enabled for the test.
- The checkbox must be enabled for the test.
- 2. Perform the actions in the following table:

If	Action
You want to stop any test that is running	 Perform any of the following actions: Click the Stop execution icon (20) in the Actions column of the selected test. Click the checkbox in the row of the selected test, and then click Stop selected. The Stop execution dialog is displayed.
You want to stop multiple tests that are running	Perform any of the following actions: • Click the checkbox in the row of the selected tests, and then click Stop selected. • Click the Select all checkbox in the header row, and then click Stop selected.
	Note: All running tests are selected when you click the Select all checkbox.
	The Stop execution dialog is displayed.

- 3. Perform the following steps in the Stop execution dialog that is displayed:
 - a. Set the timeout period for stopping the test run. Enter a numeric value and select the unit from the options available as *Seconds*, *Minutes*, or *Hours*.

The time out period is the time during which the test run is allowed to stop on its own and after the timeout period, the test is forced to stop abruptly.

Important: If the timeout period is not set, a value of *30 seconds* is considered as the default timeout period.

- b. Perform any of the following actions:
 - Keep the Capture results option selected, if you want the results to be captured for the test.


The captured results for the test are available to view from the Results page.

• Clear this option if you do not want to capture the results.

Note: The **Capture results** option is selected as the default option.

Important: The results are always captured for API suites even if you clear the Capture results option.

- c. Perform any of the following actions:
 - Keep the **Execute 'finally-block', if present** option selected, if you want the *finally-block* code in the test script, if present, to be run before the test run is stopped.
 - Clear this option if you do not want to run the *finally-block* code in the test script.



Restriction: The *tear-down* steps equivalent to the **'finally-block'** code, if present in API suites are not controllable at test runtime. The **Execute 'finally-block'**, **if present** option has no impact on API suites.

d. Click Stop execution.

A notification is displayed that the running tests are stopped.



Note: If the test run completes before you can configure the options for stopping the test run, a notification is displayed in the **Stop execution** dialog that the test asset has completed its run.

Results

You have successfully stopped a running test or stopped multiple running tests. The stopped test runs are displayed on the **Progress** page with the status as *Stopped by User*. Stopped tests are not considered in the count of tests executed that are displayed on the **Overview** page.

What to do next

You can re-initiate the test run from the **Execution** page or from the **Results** page by completing the configurations that you want for the test.

You can view the results or the execution log of the stopped test from the **Actions** column on the **Progress** page by clicking the **Open action menu** icon.

Related information

Test run configurations on page 327 Viewing the progress of running test assets on page 457 Canceling scheduled test runs on page 465

Canceling scheduled test runs

You might want to cancel a scheduled test run, scheduled recurring test runs, or multiple scheduled test runs when you realized that you did not configure all the settings for the runs, want to change a few settings, or do not want those tests to run.

Before you begin

You must have scheduled runs for one or multiple test assets from the Execution page.

About this task

You can cancel a scheduled test run, all instances of a scheduled recurring test runs, or multiple scheduled tests from the **Progress** page.

- 1. Preform any of the following actions:
 - Click Scheduled under the Next Run column on the Execution page.

The test is displayed on the **Progress** page. If you selected a test that was scheduled as a recurring test, then all the tests that ran and the next scheduled test run are displayed.

Go to Step 2 on page 465.

• Go to the Progress page and identify the tests in any of the following ways that you want to cancel:

You can select the tests that satisfy the following conditions:

- The test must be in the *Scheduled* state.
- The Cancel icon 🛞 in the Actions column must be enabled for the test.
- The checkbox must be enabled for the test.

Go to Step 2 on page 465.

2. Perform the actions in the following table:

If	Action
You want to cancel any test run that is scheduled.	 Perform any of the following actions: Click the Cancel icon (2) in the Actions column of the selected test. Click the checkbox in the row of the selected test, and then click Stop selected.

If	Action
You want to cancel all sched- uled instances of the recur- ring test runs.	The Cancel scheduled execution dialog is displayed. Go to Step 3 on page 466.
You want to stop multiple	Perform any of the following actions:
test runs that are scheduled	 Click the checkbox in the row of the selected tests, and then click Stop selected. Click the Select all checkbox in the header row, and then click Stop selected. Note: All scheduled tests are selected when you click the Select all checkbox.
	The Cancel scheduled execution dialog is displayed.
	Go to Step 3 on page 466.

3. Click Yes in the Cancel scheduled execution dialog. Result

A notification is displayed that the scheduled test runs are canceled.

Results

You have successfully canceled a scheduled test, all instances of the scheduled recurring tests, or multiple scheduled tests. The canceled test runs are displayed on the **Progress** page with the status as *Canceled*. The canceled test runs are not displayed on the **Results** page and are not considered in the count of tests executed that are displayed on the **Overview** page.

What to do next

You can re-initiate the test run from the Execution page by completing the configurations that you want for the test.

Related information

Test run configurations on page 327 Viewing the progress of running test assets on page 457 Stopping test runs on page 462

Management of virtualized services

Disclaimer: This release contains access to the virtual services that virtualize the Istio based services feature in HCL OneTest[™] Server as a Tech Preview. The Tech Preview is intended for you to view the capabilities for virtualized services offered by HCL OneTest[™] Server, and to provide your feedback to the product team. You are permitted to use the information only for evaluation purposes and not for use in a production environment. HCL provides the information without obligation of support and "as is" without warranty of any kind.

You can find information about the tasks that you can perform on and manage the virtualized services that run on HCL OneTest[™] Server. You can start or stop the virtual services that are connected to HCL OneTest[™] Server. You can view the routing rules and usage statistics of virtualized services, agents, or intercepts that are connected to HCL OneTest[™] Server.

You must create stubs or virtual services in HCL OneTest[™] API for the following types of services. You must commit the virtual service resources to a remote repository and then add the repository to your project on HCL OneTest[™] Server before you can run the virtual services on HCL OneTest[™] Server:

- · Virtual services that utilize the WebSphere® MQ transport.
- Virtual services that utilize the HTTP transport.
- Virtual services that virtualize the Istio based services. You can run virtual services for the following types of requests received or sent by the Istio service mesh:
 - Requests received by services in the Istio service mesh.
 - Requests sent from namespaces in the Istio service mesh to external services that are not in the Istio service mesh.

Important: You can run virtual services only in the **Default Cluster** location of HCL OneTest[™] Server. You cannot run virtual services on a remote Docker host.

The following are the considerations that decide how a container of the HCL OneTest[™] Server cluster is selected to run virtual services:

- Before a container is selected to run a virtual service, it is checked for a previous failure to start a virtual service or for a low heap size, and other conditions. If the container was not found suitable, then it is not selected for running the virtual service.
- Multiple virtual services can be run in the same container if the following conditions are satisfied:
 - Subsequent virtual services are started by the same project member.
 - ∘ All virtual services are created and contained in the same HCL OneTest™ API project.
 - The requests to run the virtual services refer to the same version, meaning that the git commit IDs on which they are based are the same. If you use the UI, this means that the **Version** field in the **Execute virtual service** dialog are the same.

- The settings that you configure in the Advanced settings for the virtual services are the same.
- $\circ\,$ The datasets selected for an override are the same, if datasets are used.

Working with virtual services

You can perform the following tasks on virtual services on HCL OneTest[™] Server:

- Read about the considerations before you configure a run of the virtual services. See Prerequisites for running virtual services on page 468.
- Read about the considerations before you configure a run of the Istio based services that are virtualized. See Prerequisites for running virtualized Istio based services in HCL OneTest Server on page 470.
- Set up the HTTP proxy, if you have configured stubs in the test assets to use an HTTP proxy to route requests. See Setting up the HTTP proxy on page 472.
- View all intercepts that are registered with HCL OneTest[™] Server including those that you have not configured. See Viewing intercepts that are registered with a team space on HCL OneTest Server on page 474.
- View virtual service resources in the test assets that are in the repositories added to a project on HCL OneTest[™] Server. See Viewing virtual service resources on page 475.
- Configure runs of virtual services. See Configuring a run of a virtual service on page 478.
- Configure runs of HTTP virtual services to run without using proxies. See Running HTTP virtual services without using proxies on page 491.
- Run Istio stubs that were created in HCL OneTest[™] API to virtualize services in the Kubernetes cluster on which HCL OneTest[™] Server is installed.
- View running instances of virtual services. See Viewing running instances of virtual services on page 496.
- View configurations of a running virtual service instance. See Viewing configurations of running instances of virtual services on page 501.
- Modify the configurations of a running virtual service instance. See Modifying configurations of running instances of virtual services on page 505.
- View details of the usage statistics of the virtual services. See Viewing usage statistics of virtual services on page 509.
- View routing rules of the intercepts. See Viewing routing rules of the virtual services on page 507.
- Stop a running virtual service instance. See Stopping virtual services on page 512.

Prerequisites for running virtual services

You can find information about the prerequisite tasks that you must complete before you configure a run of the virtual services on HCL OneTest[™] Server.

Prerequisites for running HTTP virtual services

You can find information about the tasks that you must complete before you configure a run of the HTTP virtual services on HCL OneTest[™] Server.

Conditions for running of HTTP virtual services

Before you run the HTTP virtual services from HCL OneTest[™] Server, you must check for the following conditions and perform the actions indicated:

If	Then
You want to route the HTTP traffic via the HTTP proxy ei- ther to the virtual service or live systems, based on rout- ing rules.	You must set up the HTTP proxy. See Setting up the HTTP proxy on page 472.
You want to route the HTTP traffic to the virtual service via the HTTP proxy and the proxy is not configured to trust all certificates.	The trust store must be configured to include the certifi- cate authority for the server certificate. See Certificate authority: Importing and extending lists on page 97.
A client application is sending requests directly to the vir- tual service.	The client application must trust the certificate authori- ty for the server certificate. See Certificate authority: Im- porting and extending lists on page 97.
You are working with HCL OneTest™ Server V10.1.3, which is installed on Ubuntu.	HTTP virtual services are exposed via host names are of the following form: in- <unique_id>.<ingress_domain></ingress_domain></unique_id>
	Note: The DNS used by a computer that runs a client application or the HTTP proxy that routes traffic to the virtual service needs to resolve such host names to the IP address of the ingress domain.
	You must perform the following actions that depend on the method you have used to set up the ingress domain:
	 If you used nip.io to form the ingress domain, then that virtual services host names are au- tomatically resolved to the IP address of the ingress domain.
	For example, if you used <pre>nip.io</pre> to form the ingress domain as follows:
	10.1.2.3.nip.io

If	Then
	The virtual services host names are resolved by
	nip.io to the IP address as 10.1.2.3.
	- If your ingress domain does not use ${\tt nip.io}$ then
	you must ensure that the DNS in use by the client
	application or the HTTP proxy can resolve host
	names of the virtual services to the IP address of
	the ingress domain. For example, if the ingress
	domain is as follows:
	myhost.mycom.com
	The DNS must resolve * .myhost.mycom.com to the
	IP address of myhost.mycom.com.

HTTPS virtual service endpoints

When you want to run an HTTP virtual service where the HTTP transport settings have **Use SSL** enabled, the virtual service endpoint that is exposed for the virtual service instance expects an HTTPS request on port *443*. The exposed endpoint is managed by the same ingress controller or the HAProxy that is used for the server endpoints. The SSL/TLS termination occurs at the endpoint before the request is routed to the virtual service instance and results in the following implications:

- The Virtualization (Server) SSL options that are specified in the HTTP transport have no effect.
- The certificate served by the exposed virtual service endpoint is the same as that of server that is signed by the server certificate authority.

Collection of usage metrics

If you want HCL OneTest[™] Server to display the usage statistics of the virtual service instances, you must install the Prometheus server at the time of server installation.

Related information

Setting up the HTTP proxy on page 472

Running HTTP virtual services without using proxies on page 491

Prerequisites for running virtualized Istio based services in HCL OneTest[™] Server

Disclaimer: This release contains access to the virtual services that virtualize the Istio based services feature in HCL OneTest[™] Server as a Tech Preview. The Tech Preview is intended for you to view the capabilities for virtualized services offered by HCL OneTest[™] Server, and to provide your feedback to the product team. You are permitted to use the information only for evaluation purposes and not for use in a production environment. HCL provides the information without obligation of support and "as is" without warranty of any kind.

You can find information about the tasks that you must complete before you run virtualized Istio based services in HCL OneTest[™] Server.

Configuring virtualized Istio based services in HCL OneTest™ Server

When you intend to virtualize services in the Istio mesh in HCL OneTest[™] Server, you can create stubs in HCL OneTest[™] API.

When you create the Istio stubs in HCL OneTest[™] API, you must ensure that you are aware of the fully qualified domain name (FQDN) or the short name of the service that you want to virtualize in the Kubernetes cluster that hosts HCL OneTest[™] Server.

The FQDN of the service is as follows:

<service-name>.<namespace>.<svc>.<cluster-name>

The short name of the service is as follows:

```
<service-name>
```

For example, if you want to virtualize the HTTP traffic in the service named as *reviews* that runs in a namespace named as *bookinfo*, and in the resource named as *svc* in the Kubernetes cluster named as *mycluster*, then the FQDN of the service is as follows:

reviews.bookinfo.svc.mycluster

The short name of the service is as follows:

reviews

You must enter the host of the service that you want to virtualize, in the **Host** field of the physical transport in HCL OneTest[™] API. You can provide either the FQDN or the short name of the service.



Note: The pass-through action in the stubs is not supported.

Considerations for running of stubs that virtualize Istio services

Before you run the stubs that virtualize services in namespaces contained in the HCL OneTest[™] Server Kubernetes cluster, you must install HCL OneTest[™] Server with the *demo* configuration.

When you install HCL OneTest[™] Server by using the *demo* configuration, then HCL OneTest[™] Server is preconfigured to use the **bookinfo** namespace as the virtualization namespace.

Note: You can change or add virtualization namespaces by adding the helm installation argument execution.istio.namespaces along with a list of namespaces in a helm command.

After you author the virtualized Istio based services, you must commit the virtual service resources to a repository and add the repository to the project on HCL OneTest[™] Server. You can configure a run of the virtualized Istio service. See Configuring a run of a virtual service on page 478.

Collection of usage metrics

If you want HCL OneTest[™] Server to display the usage statistics of the virtual service instances, you must install the Prometheus server at the time of server installation.

Related reference

Installation of the server software on page 36

Setting up the HTTP proxy

When you want to run HTTP virtual services on HCL OneTest[™] Server, you can set up an HTTP proxy to route requests to the virtual service. You must configure the HTTP proxy with the HCL OneTest[™] Server URL and offline user token generated from HCL OneTest[™] Server so that the HTTP proxy can register with HCL OneTest[™] Server.

Before you begin

You must have completed the following tasks:

- Installed the proxy component from HCL® Quality Server of the same version as that of HCL OneTest™ Server.
- Read the following procedures:
 - Generating offline user tokens. See Managing access to HCL OneTest Server on page 708.
 - Viewing the *Team Space ID* as the URL alias of the team space. See Viewing the configuration of a team space on page 717.

About this task

You must edit the registration.xml file that is located in the <QS_install_directory>\httptcp directory for the following attributes:

- server base-url
- security-token
- team-space-id

You must enter the HCL OneTest[™] Server URL, offline user token, and the ID of the team space to which the proxies must register as the values for the attributes. After you restart the proxy, the HTTP proxy registers with the team space on HCL OneTest[™] Server. You can view the registered intercepts from the **Infrastructure > Agents and Intercepts** page in your team space.

- 1. Perform the following steps in HCL OneTest[™] Server:
 - a. Log in to HCL OneTest[™] Server.

The Team Space Dashboard page is displayed.

- b. Generate the offline user token by clicking the **User** icon \square , and then click **Create Token**.
- c. Copy the offline user token to a text file.
- d. Click the Settings icon 🔯 of the team space in the My Team Spaces page.

The Team Space Configuration page is displayed.

- e. Copy the text that is displayed under URL alias as the Team Space ID.
- 2. Perform the following steps to edit the registration.xml file that is located in the

<QS_install_directory>\httptcp directory on the computer on which you have installed HCL® Quality Server:

- a. Open the registration.xml file by using a text editor.
- b. Enter the values for the following attributes:



Note: If an entry exists, you must either comment out that entry and add a new one or replace the contents with the values indicated.

Attribute	Value
server base-url	URL of HCL OneTest [™] Server
security-token	Offline user token generated from HCL OneTest™ Server
team-space-id	ID of the team space to which the proxies must register

- c. Save and close the file.
- d. Restart the HTTP proxy.
- 3. Perform the following steps in HCL OneTest[™] Server to view the HTTP proxies that are registered in the team space:
 - a. Log in to HCL OneTest[™] Server.
 - b. Click Infrastructure > Agents and Intercepts to view the registered intercepts.

The HTTP proxies that you configured with your offline user token and Team Space ID are displayed.

Results

You have successfully configured the HTTP proxies and viewed that they are registered in the team space on HCL OneTest[™] Server.

What to do next

You can perform the following tasks:

- Read for the prerequisite tasks that you must perform before you can run the HTTP stubs. See Prerequisites for running HTTP virtual services on page 468.
- Run the virtual service resource. See Configuring a run of a virtual service on page 478.
- View the routing rules for the intercept. See Viewing routing rules of the virtual services on page 507.
- View the routing rules for the intercept in a running instance of the virtual service. See Viewing configurations of running instances of virtual services on page 501.

Viewing intercepts that are registered with a team space on HCL OneTest™ Server

After you install the HTTP proxies and configure them with your offline user token, the proxies register with HCL OneTest[™] Server in a team space as intercepts and you can view the registered intercepts on the **Agents and Intercepts** page for the team space.

Before you begin

You must have completed the following tasks:

- Completed the prerequisite tasks before you configure a run of the HTTP virtual services. See Prerequisites for running HTTP virtual services on page 468.
- Read the prerequisite information about virtualizing the Istio based services. See Prerequisites for running virtualized Istio based services in HCL OneTest Server on page 470.
- Installed the HTTP proxies of the same version as the version of HCL OneTest[™] Server.
- Configured the HTTP proxy with your offline user token so that the proxy can register as an intercept with HCL OneTest[™] Server. See Setting up the HTTP proxy on page 472.
- Ensured that you are assigned a role as a *Member* or *Project Creator* in the team space. See Managing members and their roles in a team space on page 720.
- Ensured that you are assigned a role as a *Project Owner* or *Tester* in the project. See Managing access to server projects on page 734.
- 1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

2. Click Infrastructure > Agents and Intercepts in the navigation pane.

The Agents and Intercepts page is displayed.

You can view the agents, intercepts, or Docker hosts that are registered in the team space on HCL OneTest[™] Server.

3. You can view the intercepts that you own in any of the following ways:

 \circ Search for the intercept by entering the name of the intercept in the Search field.

Note: You can enter either the full name or any text that is in the name. The search is enabled for case-sensitive text that you can enter.

- Sort the Type column to show the items sorted with the intercepts in the rows at the top of the table.
- Sort the Agents column and identify the intercepts by their names or by their owner.

You can view the following details about the intercepts that are registered with HCL OneTest[™] Server:

- Any project is displayed in the **Projects** column indicating that the intercept can be used by virtual services in any project.
- The status of the intercept is displayed in the Status column.

Results

You have viewed the registered intercepts from the Agents and Intercepts page.

What to do next

You can start the virtual services that use the registered intercepts. See Configuring a run of a virtual service on page 478.

Viewing virtual service resources

When project repositories contain virtual service resources and you want to view the resources so that you can start them, you can view the virtual services from the **Resources** page in your team space on HCL OneTest[™] Server.

Before you begin

You must have completed the following tasks:

- Ensured that you are assigned a role as a *Project Creator* in the team space. See Managing members and their roles in a team space on page 720.
- Ensured that you are assigned a role as a *Project Owner* or *Tester* in the project. See Managing access to server projects on page 734.
- Created virtual services that use the HTTP or IBM® WebSphere® MQ transport for tests in your project.

About this task

After you have committed the test assets and resources to the remote repositories and added the repositories to projects in your team space on HCL OneTest[™] Server, you can go to the **Resources** page and perform the following tasks:

- View the virtual service resources that are contained in any branch of the repositories that are added to your project.
- View the components in the System Model that are associated with the virtual service resources.
- Create or use saved filters for viewing virtual service resources.

- Run or start an instance of the virtual service resource.
- View the number of instances of the virtual service resources that are running.
- View all instances of a running virtual service on the Instances page by clicking the Show in instances page

icon 岱.

1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

 Open the project that contains the virtual service resources in the test assets by clicking Projects > My Projects > project_name.

The **Overview** page is displayed.

3. Click **Virtualization > Resources** in the navigation pane.

The **Resources** page is displayed.

4. Complete the steps for the task that you want to perform as listed in the following table:

Task	Action
Viewing the virtual service re- sources that are contained in a branch of any of the repositories that are added to your project.	Select the branch of the repository that contains the virtual services that you want to run from the list in the Branch field. All virtual services in the selected branch are displayed on the Re- sources page.
Viewing the components that are associated with the virtual service resource.	The components that are associated with the virtual service resource are displayed in the Components column. Click the component in the Components column to view the virtual re- source on the System Model page.
Creating or using saved filters for viewing specific instances of virtu- al service resources.	 To create a query, perform the following actions: a. Click New filter. b. Create a rule with an appropriate operator. c. Select criteria such as Name, Path, Instance number, Instance state, or Components. d. Select the condition, and then enter the value for the criteria. e. Apply the filter query. The virtual services that match the filter criteria are displayed. f. Save the filter query for retrieving it from the saved filters list. To use a saved filter query, perform the following actions:

Task	Action	
	Note: To open the filter query, you must have created and save a filter query.	
	 a. Click the Open filters icon b. Select the saved filter. c. Apply the filter. The virtual services that match the filter criteria are displayed. 	
Running an instance of the virtual service resource.	After you identify the virtual service that you want to run, perform the following actions: a. Click the Execute icon b in the row of the identified virtual service.	
	 The Execute virtual service dialog is displayed. b. Run the virtual service with the settings that are configured in the resource by clicking Execute or modify any of the settings, and then click Execute. An instance of the virtual service starts to run. The virtual service is displayed with the state as Running along with the number of instances that are running in the Active instances column. 	
Viewing the number of instances of the virtual service resources that are running.	If any of the virtual services in the project repositories are started by any project member with the <i>Tester</i> or <i>Owner</i> role, you can view the number of instances that are running or active from the Resources page. The virtual services are displayed with the state as Running along with the number of instances that are running, in the Active instances col- umn.	
Viewing all instances of a running virtual service.	Click the Show in instances page icon in the row of the virtual service on the Resources page. The Instances page is displayed with all the running instances of a particular virtual service.	
	You can also view the number of requests that are received by the vir- tual service. The number of requests is displayed as the number of hits when you hover the cursor over the text in the Activity column.	

Results

You have viewed virtual services from the Resources page on HCL OneTest[™] Server.

Related information

Configuring a run of a virtual service on page 478

Configuring a run of a virtual service

Disclaimer: This release contains access to the virtual services that virtualize the Istio based services feature in HCL OneTest[™] Server as a Tech Preview. The Tech Preview is intended for you to view the capabilities for virtualized services offered by HCL OneTest[™] Server, and to provide your feedback to the product team. You are permitted to use the information only for evaluation purposes and not for use in a production environment. HCL provides the information without obligation of support and "as is" without warranty of any kind.

When you have virtual service resources that are in the repositories added to your project, you must configure a run of the virtual service to start an instance of the virtual service on HCL OneTest[™] Server or other remote Kubernetes clusters.

Before you begin

You must have completed the following tasks:

- Ensured that you are assigned a role as a *Project Creator* in the team space. See Managing members and their roles in a team space on page 720.
- Ensured that you are assigned a role as a *Project Owner* or *Tester* in the project. See Managing access to server projects on page 734.
- Created virtual services that use the HTTP or IBM® WebSphere® MQ transport for tests in your project.
- Completed the prerequisite tasks before you configure a run of the HTTP virtual services. See Prerequisites for running HTTP virtual services on page 468.
- Read the prerequisite information about virtualizing the Istio based services. See Prerequisites for running virtualized Istio based services in HCL OneTest Server on page 470.
- Read and completed the tasks mentioned in Considerations for using a remote Kubernetes cluster on page 313, if you want to use a remote Kubernetes cluster as a location to run the test.

About this task

You can start the following types of stubs contained in API Suites from the **Resources** page on HCL OneTest[™] Server:

- Virtual services that utilize the WebSphere® MQ transport.
- Virtual services that utilize the HTTP transport.

- Virtual services that virtualize the Istio based services. You can run virtual services for the following types of requests received or sent by the Istio service mesh:
 - Requests received by services in the Istio service mesh.
 - Requests sent from namespaces in the Istio service mesh to external services that are not in the Istio service mesh.
- 1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

 Open the project that contains the virtual service resources in the test assets by clicking Projects > My Projects > project_name.

The Overview page is displayed.

3. Click Virtualization > Resources in the navigation pane.

The **Resources** page is displayed.

4. Select the branch of the repository that contains the virtual services that you want to run from the list in the **Branch** field.

All virtual services in the selected branch are displayed on the Resources page.

- 5. Identify the virtual service by completing any of the following steps:
 - Search for the virtual service by entering the name or the path of the virtual service in the repository in the Search field box.
 - Create a filter query by using the New filter option and complete the following steps:
 - a. Create a rule with an appropriate operator.
 - b. Select criteria such as *Name, Path, Instance number,* or *Instance state*. Select the condition and enter the value for the criteria. Apply the filter query.

The virtual services that match the filter criteria are displayed.

- c. Save the filter query for retrieving it from the saved filters list.
- Retrieve a saved filter by using the **Open filters** icon = by completing the following steps:

Note: To open the filter query, you must have created and saved a filter query.

- a. Select the saved filter.
- b. Apply the filter.

The virtual services that match the filter criteria in the filter that is applied are displayed.

6. Click the Open action menu icon in the row of the identified virtual service, and then click Execute icon 🕑.

The Execute virtual service dialog is displayed.

- 7. Select the version of the virtual service that is in the repository that you want to start by performing any of the following actions:
 - Expand the list in the Version field, find the version of the test resources, and then select the version.

Use the following details about the version of the test resources that are displayed to identify the version that you want:

- Commit message.
- Tags labeled for the version committed.
- The user who committed the version to the repository.
- Relative time of the commit. For example, 2 hours ago or 3 days ago.

The list displays the versions of the test resources committed by all users to the branch in the repository. The versions are arranged with the latest version committed followed by the versions committed previously.

• Expand the list in the **Version** field, and then search for the version that you want to select by entering a partial or the complete commit message of that version.

The version that matches the search criteria is displayed and it is selected for the test run.

 Select the environment that was used to bind the physical and logical resource in the API project, in the ENVIRONMENT tab.

Important: The configuration that you set for the run in the Execute virtual service dialog is preserved when you run the same virtual service again. The configurations that you set are not available to other members when they want to run the virtual service. For example, if you selected an environment, the same environment is selected when you run the virtual service again.

9. Enter a label, if required.

A label that you enter for the test run that helps you to identify the virtual service instance on the **Instances** page. The label that you entered is displayed for the virtual service under the **Labels** column on the **Instances** page. After you have created a label, any member of the project can use that label.

10. Follow the instructions if you want to modify the configurations for the behavior of the virtual service:

- a. Click the **BEHAVIOR** tab, if it is not already open.
- b. Configure or change the settings for the following options:

Note: The settings displayed are the settings that were configured for the virtual service when it was authored in HCL OneTest[™] API.

Option	Description			
Performance	The following settings are available for handling of requests by the virtual ser- vice:			
	Option	Description		
	Optimize performance	If enabled, attempts are made to reduce the		
		amount of processing between the time the vir-		
		tual service receives a request and the time it		
		sends a response. Specific optimizations de-		
		pend on the message contents, as in the follow-		
		ing examples:		
		When the virtual service receives re-		
		quests, all validations are disabled, and		
		for all XML payloads, the store and filter		
		actions are converted to use XPath ex-		
		pressions.		
		 When the virtualization sends respons- 		
		es, any store actions set on a message		
		are disabled, and any XML content is col-		
		lapsed when the virtual service is com-		
		piled instead of being collapsed every		
		time that a response is sent.		
		The optimization is disabled as the default ac-		
		tion for this setting and you can enable the per-		
		formance optimization if you fully understand		
		the implications of optimizing the performance.		
	Threads			
		The maximum number of threads used in pro-		
		cessing requests received by the virtual service.		
		The default number of threads is 10.		
Operation	Specifies an operation refe	Specifies an operation referenced by the virtual service.		
Response time	Specifies the response time	Specifies the response time behavior for responses sent by the virtual service		
	for the selected operation.			


Option	Description	Description			
	You can modi	You can modify the value by selecting a value from the following options:			
	Option	Option Description			
	No delay	Select this option for a response with no delay.			
	Minimum delay	Select this option for a delay in the response by entering the re- quired delay in milliseconds (ms).			
	Uniform dis- tribution	Select this option for a uniformly distributed response time by specifying the minimum and maximum delay in milliseconds (ms).			
	Gaussian distribution	Select this option for a response time with Gaussian distribution by specifying the minimum and maximum delay in milliseconds (ms).			
Passthrough		pass through behavior for the selected operation when requests ed within the virtual service.			
	You can modi	You can modify the value by selecting a value from the following options:			
	Discard	This option stops the system under test from receiving the inter- cepted message. This option can disrupt the calling system. For example, the system might time out while it waits for a reply.			
	Pass Through	This option passes the intercepted message to the system under test, with an optional delay.			
	Simulate Error	This option returns an error to the calling system. The message is not passed to the system under test.			

11. Follow the instructions, if the virtual service references datasets.

- $\,{}_{\circ}\,$ You can use the dataset referenced in the asset.
- You can choose to override the dataset with another data source. If alternative data sources are available, select from the set of overrides available.
- 12. Follow the instructions if the virtual service requires a variable that must be passed at run time.

- a. Click the VARIABLES tab, if it is not already open.
- b. Choose one of the following methods to add the variables:
 - To add new variables manually, click the **Add Variable** icon (+), enter the name, and value of the variable.
 - To add new variables from your local computer or from the Git repository that is associated

with your server project, click the **Upload** icon and select the **Upload from local system** or **Browse from server** to select the variable file.



- 13. Click Advanced to make the following advanced configurations:
 - a. Enter any JVM arguments that must be passed at run time in the JVM Arguments field.

Note: Each JVM argument should be separated with white space.

For example, you can set a maximum Java heap size.

b. Enter the environment variables that must be passed at run time in the **Environment Variables** field, if applicable.

For example, enter the environment variables when the third-party libraries that are used in the run refer to the environment variables for configuration.

c. Select the stub logging level for the virtual service from the following options in the Logging list:

Option	Description
None	Specifies that the virtual service does not write log messages.
Normal	Specifies that the virtual service writes informational messages.
Debug	Specifies that the virtual service writes informational and debugging messages.

d. Enter other configuration options as parameters and their values in the **Additional Configuration Parameters** fields, if applicable.

You can refer to the additional parameters that you can use for virtual services from the topic in the related links.

For example, if you want to start the virtual service to run in a new container, you can specify the following parameter and its value:

Parameter name	Value
stub.dedicated.container	true



Note: Click Add to add additional parameters.



Note: You must separate the arguments or variables with a white space when you enter them in the same line or start each argument or variable on a new line.

The default value for the fields for the advanced settings is null or an empty field.



- If you have configured some or all of the settings for the current run, and you do not want to continue with those settings, you can reset the settings by clicking **Reset**.
- If you want to repeat a run and do not want to use the saved settings from a previous run, you
 can reset all the saved settings to their default values by clicking Reset.

14. Follow the instructions if you want to change the location of a Kubernetes cluster for running the test:

a. Click the LOCATION tab, if it is not already open.

The **Default Cluster** is the default location where the virtual service resource runs, and it is listed under the **Host** column. The information about the availability of the default location is displayed.

Important: You must have added the registered remote Kubernetes clusters to your project that are then displayed under the **Override** column:

Notes:

- If the remote clusters are not added to your project, the option No override options is displayed as the default value and the virtual service resource runs in the Kubernetes cluster of HCL OneTest[™] Server.
- If remote clusters are added to your project, the added clusters are displayed along with their availability status and ownership information.
- b. Select the location where you want to run the virtual service resource from the following options:
 - Select the Default Cluster when no remote clusters are available in your project.
 - Select the remote cluster from the list when a remote cluster is available in your project.
 - Select No override options, if you selected any remote cluster and want to revert to the Default Cluster to run the virtual service resource.

c. Click Execute.

The test run is initiated.

15. Click Execute.

Results

You have started a virtual service from the **Resources** page on HCL OneTest[™] Server.

What to do next

After you start a run of a virtual service, you can view the status of the virtual service in any of the following ways:

- On the **Resources** page, the virtual services are displayed with the state as Running along with the number of instances that are running in the **Active instances** column.
- On the **Resources** page, you must click the **Show in instances page** icon in the row of the virtual service to view all the running instances of a particular virtual service on the **Instances** page.
- Go to the Instances page by clicking Virtualization > Instances. You can view instances of all the virtual services that are running and are displayed with the state as Running under the State column. You can also view the requests that are received by the virtual service. The number of requests is displayed as number of hits when you hover the cursor over the text in the Activity column.

You can view the details, configuration settings, routing rules, usage statistics, or logs of a specific running instance of the virtual service. See Viewing configurations of running instances of virtual services on page 501.

You can modify the behavior or the logging level of a running instance of the virtual service that you started before running tests on them. See Modifying configurations of running instances of virtual services on page 505.

When you have completed testing the virtual service, you must stop the running virtual service. See Stopping virtual services on page 512.

Related reference

Additional configuration parameters for virtual services on page 485

Additional configuration parameters for virtual services

You can find information about the additional configuration parameters that you can set when you want to run virtual services on HCL OneTest[™] Server.

When you use the server UI to start the virtual service, some of the parameters are handled by fields in the **Execute** virtual service dialog.

You can enter the other parameters as a *name-value* pair in the **Additional configuration parameters** field that is displayed in the **Advanced** settings panel of the **Execute virtual service** dialog.

name

Requirement	Configuration para- meter name	Supported values	An example value	Result of using the example value
To specify a unique identifier for use in	stub.ingress.host.i- dentifier	Any <custom_id> that you specify.</custom_id>	mystub	See Running HTTP virtual services with-
the generated host		Note: The		out using proxies on

<custom_-

id> must start

page 491, to know

specified is used.

how the identifier you

The following additional configuration parameters are supported when you configure a run for a virtual service.

		and end with an alphanu- meric char- acter. The characters supported include a-z, 0-9, and a hy- phen. No oth- er characters can be used in the <cus-< b=""> tom_id>. The <custom_id></custom_id> must not be longer than 32 charac- ters.</cus-<>		specified is used.
To specify whether a virtual service in- stance should be run in a dedicated con- tainer.	stub.dedicated.con- tainer	true false Note: The de- fault value is false.	true	A dedicated contain- er is used to run a single virtual service instance.
To specify whether performance opti- mization is enabled	stub.performance.op- timize	• true • false	true	The performance op- timization is enabled for the virtual service.

Requirement	Configuration para- meter name	Supported values	An example value	Result of using the example value
for the virtual service instance. The value set overrides the set- ting from the stub de- finition. This option can be set in the Behavior tab from the UI.		Note: The default value is <i>false</i> .		
To specify the num- ber of threads to be used for processing requests for the virtu- al service instance. The value set over- rides the setting from the stub definition. This option can be set in the Behavior tab from the UI.	stub.worker.thread- .count	Any number that you specify as number of threads to use.	15	15 threads are used for processing re- quests for the virtual service instance.
To specify the stub logging level for the virtual service in- stance. The value set overrides the setting from the stub defini- tion. This option can be set in the Advanced settings from the UI.	stub.logging.level	• none • normal • debug	debug	The virtual service writes informational and debugging mes- sages to the contain- er log.
To specify the pass- through behaviour type of the virtual ser- vice instance. The value set overrides	stub.pass.through- .behavior	Valid values depend on the stub operation transport type but can be as follows:	simulate_error	This option returns an error to the call- ing system. The mes- sage is not passed to the system under test.

Requirement	Configuration para- meter name	Supported values	An example value	Result of using the example value
the setting from the stub definition. This option can be set in the Behavior tab from the UI.		 simulate_error discard pass_through 		
To specify the delay in passing through from the virtual ser- vice instance. The value set overrides the setting from the stub definition.	stub.pass.through- .delay.period	Any number of sec- onds in milliseconds.	10000	A delay of 10 sec- onds in passing through from the vir- tual service instance.
To specify the status code to use in the vir- tual service instance response when sim- ulating an error. The value set overrides the setting from the stub definition. Note: Ap- plies to HTTP stubs. This option can be	stub.pass.through.s- tatus.code	You must specify a valid HTTP status code as the value. For example, 503.	500	The HTTP error code of 500 is sent in the response if the virtual service simulates an error when passing through.
set in the Behavior tab from the UI.				
To specify the rea- son phrase to use in the virtual service instance response when simulating an error. The value set overrides the setting from the stub defini- tion.	stub.pass.through- .reason.phrase	You must specify the text of the status message as the val- ue.	my custom error msg	The text that you specify is set as the HTTP reason phrase in the response if the virtual service simu- lates an error when passing through.

Requirement	Configuration para- meter name	Supported values	An example value	Result of using the example value
Note: Ap- plies to HTTP stubs.				
This option can be set in the Behavior tab from the UI.				
To specify the type of response-time behav- ior that is required for the virtual service in- stance. The value set overrides the setting from the stub defini- tion.	stub.response.time- .type	 no_delay minimum_de- lay gaussian uniform performance profile 	no_delay	The virtual service sends a response without any delay.
This option can be set in the Behavior tab from the UI.		Note: perfor- mance_profile is only valid if the stub operation in the stub def- inition is de- fined to use a performance profile.		
To specify the min- imum time for the response time be- haviour required for the virtual service in- stance. The value set overrides the setting from the stub defini- tion.	stub.response.time- .minimum	Any number of sec- onds in milliseconds.	5000	The virtual service sends a response af- ter a minimum delay of 5 seconds.

Requirement	Configuration para- meter name	Supported values	An example value	Result of using the example value
This option can be set in the Behavior tab from the UI.				
To specify the max- imum time for the response time be- haviour required for the virtual service in- stance. The value set overrides the setting from the stub defini- tion. This option can be set in the Behavior tab from the UI.	stub.response.time- .maximum	Any number of sec- onds in milliseconds.	20000	The virtual service must send a re- sponse after a maxi- mum delay of 20 sec- onds.

Virtual services where the stub definition refers to multiple operations

When a stub definition has two or more events that refer to different operations and each operation has a different behavior, you must specify the *<operation_id>* suffixed to the configuration parameter name in the **Additional configuration parameters** field.

Note: The *<operation_id>* is the internal ID of the operation that is found in the **Documentation** tab when you open the operation in HCL OneTest[™] API.

When the stub definition refers to multiple operations and you want to start a run of a virtual service, you must append the *<operation_id>* to the *rameter_name>* in the **Additional configuration parameters** field.

The configuration parameter names that you must use for the virtual service, which is associated with a particular operation are as follows:

- stub.pass.through.behavior.<operation_id>
- stub.pass.through.delay.period.<operation_id>
- stub.pass.through.status.code.<operation_id>
- stub.pass.through.reason.phrase.<operation_id>
- stub.response.time.type.<operation_id>
- stub.response.time.<operation_id>
- stub.response.time.maximum.<operation_id>

For example, if the <operation_id> is 7281b750:162483a09f1:-7e68, the parameter name for the

stub.response.time.type option that you must specify is stub.response.time.type.7281b750:162483a09f1:-7e68.

Related information

Configuring a run of a virtual service on page 478

Running HTTP virtual services without using proxies

When you run HTTP virtual services on HCL OneTest[™] Server, the endpoint on which the virtual service is exposed externally uses a host name that includes a generated ID. If a client application is required to call the virtual service directly via its external host name and not via the HTTP proxy, then you might want to determine the host name to configure the client first before you start the virtual service.

Before you begin

You must have completed the following tasks:

- Ensured that you are assigned a role as a *Member* or *Project Creator* in the team space. See Managing members and their roles in a team space on page 720.
- Ensured that you are assigned a role as a *Project Owner* or *Tester* in the project. See Managing access to server projects on page 734.
- Created a project in a team space on HCL OneTest[™] Server and added the repository that contains the HTTP virtual services.
- Completed the prerequisite tasks before you start HTTP virtual services. See Prerequisites for running HTTP virtual services on page 468.
- · Selected the branch of the Git repository to view test resources on the Execution page.

About this task

When you installed HCL OneTest[™] Server on Ubuntu, the default HTTP virtual service endpoints are of the following form:

in-<unique_id>.<ingress_domain>

For example, with an ingress domain as 10.1.2.3.nip.io, a virtual service endpoint might be as follows:

in-cd3a755635574c6fa7e264911301821a.10.1.2.3.nip.io

When you installed HCL OneTest[™] Server 10.2.1 or earlier on Red Hat OpenShift, the default HTTP virtual service endpoints are of the following form:

<ingress_domain_first_label>-<unique_id>.<remainder_of_ingress_domain>

For example, with an ingress domain as **ots.mycluster-123456-0000.region.containers.appdomain.cloud**, a virtual service endpoint might be as follows:

ots-cd3a755635574c6fa7e264911301821a.mycluster-123456-0000.region.containers.appdomain.cloud

The **<unique_id>** is generated when the virtual service is started. The full host name can be viewed in the **Routing to** field of the routing rule created for the virtual service on the **Intercept Rules** page. When traffic is routed to the virtual service via the HTTP proxy, a client application is unaware of this host name. If the client application is required to call the virtual services directly, it must be aware of the host name of the virtual service.

To allow a host name to be known before you start the virtual service, you can replace the generated ID with a user defined value that is specified as an additional configuration parameter when starting the stub. This value is referred to as **<custom_id>**.

Notes:

- The value of the <custom_id> that you specify is used as the <unique_id> for the virtual service.
- The <custom_id> must start and end with an alphanumeric character. The characters supported include a-z, 0-9, and a hyphen. No other characters can be used in the <custom_id>. The <custom_id> must not be longer than 32 characters.

Restriction: The **<custom_id>** must be unique to a virtual service that is running. You must not assign the same **<custom_id>** to another virtual service that is running simultaneously. Doing so might result in an undefined behavior of the virtual service.

For example, on Ubuntu, if you specify the value of the **<custom_id>** for the virtual service as stubl23-test and HCL OneTest[™] Server has an ingress domain as **10.1.2.3.nip.io**. Then the host name of the virtual service endpoint is as follows:

in-stub123-test.10.1.2.3.nip.io

1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

 Open the project that contains the virtual service resources in the test assets by clicking Projects > My Projects > project_name.

The **Overview** page is displayed.

3. Click Virtualization > Resources in the navigation pane.

The **Resources** page is displayed.

4. Select the branch of the repository that contains the virtual services that you want to run from the list in the **Branch** field.

All virtual services in the selected branch are displayed on the Resources page.

- 5. Identify the virtual service that you want to run.
- 6. Click the **Open action menu** icon in the row of the identified virtual service, and then click **Execute** icon 🕑.

The Execute virtual service dialog is displayed.

- 7. Select the version of the virtual service that is in the repository that you want to start by performing any of the following actions:
 - Expand the list in the Version field, find the version of the test resources, and then select the version.

Use the following details about the version of the test resources that are displayed to identify the version that you want:

- Commit message.
- Tags labeled for the version committed.
- The user who committed the version to the repository.
- Relative time of the commit. For example, 2 hours ago or 3 days ago.

The list displays the versions of the test resources committed by all users to the branch in the repository. The versions are arranged with the latest version committed followed by the versions committed previously.

• Expand the list in the **Version** field, and then search for the version that you want to select by entering a partial or the complete commit message of that version.

The version that matches the search criteria is displayed and it is selected for the test run.

 Select the environment that was used to bind the physical and logical resource in the API project, in the ENVIRONMENT tab.

Important: The configuration that you set for the run in the Execute virtual service dialog is preserved when you run the same virtual service again. The configurations that you set are not available to other members when they want to run the virtual service. For example, if you selected an environment, the same environment is selected when you run the virtual service again.

9. Enter a label, if required.

A label that you enter for the test run that helps you to identify the virtual service instance on the **Instances** page. The label that you entered is displayed for the virtual service under the **Labels** column on the **Instances** page. After you have created a label, any member of the project can use that label.

- 10. Follow the instructions if you want to modify the configurations for the behavior of the virtual service:
 - a. Click the **BEHAVIOR** tab, if it is not already open.
 - b. Configure or change the settings for the following options:

Ż

Note: The settings displayed are the settings that were configured for the virtual service when it was authored in HCL OneTest[™] API.

Performance	The following settings are available for handling of requests by the virtual ser- vice:		
	Option	Description	
	Optimize performance	If enabled, attempts are made to reduce the amount of processing between the time the vir- tual service receives a request and the time it sends a response. Specific optimizations de- 	
		cessing requests received by the virtual service. The default number of threads is <i>10</i> .	
Operation	Specifies an operation refe	renced by the virtual service.	
Response time		Specifies the response time behavior for responses sent by the virtual service	

Option	Description	Description		
	You can modi	You can modify the value by selecting a value from the following options:		
	Option	Description		
	No delay	Select this option for a response with no delay.		
	Minimum delay	Select this option for a delay in the response by entering the re- quired delay in milliseconds (ms).		
	Uniform dis- tribution	Select this option for a uniformly distributed response time by specifying the minimum and maximum delay in milliseconds (ms).		
	Gaussian distribution	Select this option for a response time with Gaussian distribution by specifying the minimum and maximum delay in milliseconds (ms).		
Passthrough	-	Specifies the pass through behavior for the selected operation when requests are not handled within the virtual service.		
	You can modi	You can modify the value by selecting a value from the following options:		
	Discard	This option stops the system under test from receiving the inter- cepted message. This option can disrupt the calling system. For example, the system might time out while it waits for a reply.		
	Pass Through	This option passes the intercepted message to the system under test, with an optional delay.		
	Simulate Error	This option returns an error to the calling system. The message is not passed to the system under test.		

- 11. Click **Advanced** to make the following advanced configurations:
 - a. Enter the following configuration options as parameters and their values in the **Additional Configuration Parameters** fields.

Parameter name	Value
stub.ingress.host.identifier	<custom_id></custom_id>

12. Click Execute.

Results

You have started an HTTP virtual service that does not use a proxy. The virtual service exposes the host name that contains a custom ID that you specified.

What to do next

After you start a run of a virtual service, you can view the status of the virtual service in any of the following ways:

- On the **Resources** page, the virtual services are displayed with the state as Running along with the number of instances that are running in the **Active instances** column.
- On the **Resources** page, you must click the **Show in instances page** icon \square in the row of the virtual service to view all the running instances of a particular virtual service on the **Instances** page.
- Go to the Instances page by clicking Virtualization > Instances. You can view instances of all the virtual services that are running and are displayed with the state as Running under the State column. You can also view the requests that are received by the virtual service. The number of requests is displayed as number of hits when you hover the cursor over the text in the Activity column.

Viewing running instances of virtual services

After you start virtual services from the **Resources** page, you can view the instances of the virtual services that are running from the **Instances** page in HCL OneTest[™] Server. You can view the details, configuration settings, routing rules, usage statistics, or logs of a specific running instance of the virtual service. You can also stop the running instance.

Before you begin

You must have completed the following tasks:

- Been assigned a Member or Project Creator role in a team space.
- Been assigned the *Viewer, Tester,* or *Owner* role in the project so that you can view the virtual services that are running.
- Started the virtual service resources as a Tester or Owner from the Resources page.

About this task

After you started the virtual services from the **Resources** page on HCL OneTest[™] Server, you can go to the **Instances** page and you can perform the following tasks:

- View all running instances of the virtual services that are contained in the project repositories.
- View the components in the system model that are associated with the virtual service instances.
- Search for a specific instance of the virtual service for which you want to view the details.
- Create or use saved filters for viewing specific running instances of the virtual service.
- View the details, configuration settings, routing rules, usage statistics, or logs of a specific running instance of the virtual service.

- Change the behavior or logging level of a running instance of the virtual service before you run tests on the virtual service.
- Stop a specific running instance of the virtual service.
- · Stop multiple instances or all instances of the virtual service that are running.
- 1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

 Open the project that contains the virtual service resources in the test assets by clicking Projects > My Projects > project_name.

The **Overview** page is displayed.

3. Click Virtualization > Instances in the navigation pane.

The **Instances** page is displayed.

Any one of the following views is displayed:

- No instances of virtual services are displayed if there are no instances that are running or were stopped in the past hour.
- All running instances of virtual services in your project are displayed.
- No running instances of virtual services are displayed but the option Show all is enabled. You can click
 Show all to display the instances that were stopped in the past hour. Instances that were hidden from the display when Hide inactive was clicked are displayed.
 - Note: All instances that were stopped are automatically removed from the display after 60 minutes of being stopped. You cannot use the Instances page to view the history of stopped instances. You can hide the stopped instances from the display by clicking Hide inactive, so that you can view only the running instances.

You can find the following information about the running instances that are displayed on the **Instances** page.

- \circ The name and path of the virtual service in the project repository are displayed in the Name column.
- The tags or labels added to the instance when the run was configured is displayed in the **Labels** column.
- The name of the environment associated with the operation in which the virtual service was created in HCL OneTest[™] API is displayed in the **Environment** column.
- The state of the running instance is displayed as Running in the State column.
- The activity of the running instance of the virtual service based on the number of requests received in the previous hour is displayed in the Activity column. The activities are classified and displayed as indicated in the following table:

Activity load	Activity displayed as
Received 0 requests	None

Activity load	Activity displayed as
Received 1 - 10 requests	Low
Received 11 - 100 requests	Mid
Received 101 - 1000 requests	High
Received more than 1000 requests	Very High

• The **Stop** icon **O** is displayed in the **Actions** column and stops the running instance of the virtual service, when clicked.

4. Complete the steps for the task that you want to perform as listed in the following table:

Task	Action
Searching for a specific instance of the virtual service for which you want to view the details or want to stop the instance.	Enter either the complete text or part of the text in the name or the path of the virtual service that is in the repository in the Search field. The instances of the virtual services that match the text searched are displayed.
Viewing the component associat- ed with the running instance of the virtual service.	You can view the name of the associated component that is displayed on the Instances page in the Filter row only if you clicked the icon on the System Model page to view all running instances of the virtual services .
Creating or using saved filters for viewing specific instances of virtu- al service resources.	 To create a query, perform the following actions: a. Click New filter. b. Create a rule with an appropriate operator. c. Select criteria such as Name, Path, Labels, Environment, State, or Activity. d. Select the condition, and then enter the value for the criteria. e. Apply the filter query. The virtual services that match the filter criteria are displayed. f. Save the filter query for retrieving it from the saved filters list. To use a saved filter query, perform the following actions: Note: To open the filter query, you must have created and saved a filter query. a. Click the Open filters icon \$\$\$. b. Select the saved filter.

Task	Action
	c. Apply the filter.
	The virtual services that match the filter criteria are displayed.
Viewing the details, configuration settings, routing rules, usage sta- tistics, or logs of a specific running instance of the virtual service.	 After you identify the virtual service instance for which you want to view the details, perform the following actions: a. Click the Expand icon in the row of the identified instance of the virtual service.
	 The Details panel of the instance is displayed. You can find the following details about the instance displayed: Name Path Labels API Environment Version Started at Started by Execution location Associated components Documentation b. Click Behavior to expand the panel and view the behavior that was configured for the virtual service. c. Click Routing Rules to expand the panel and view the graphical representation of the activities performed by the virtual service. e. Click Diagnostics to expand the panel and view the logging con-
Changing the behavior or logging level of a running instance of the virtual service.	figuration of the virtual service and the links to the logs. After you identify the virtual service instance for which you want to view the details, perform the following actions: a. Click the Expand icon in the row of the identified instance of the virtual service. The Details panel of the instance is displayed. Perform any of the following actions: • Click Behavior to expand the panel. Perform the following steps to change the behavior configura- tions:

Task	Action
	a. Click the Edit icon 🔼
	b. Select a different operation for the virtual service, if
	available.
	c. Select a different response time and enter the values for
	the delay that you want to set.
	d. Click apply .
	 Click Diagnostics to expand the panel.
	Perform the following steps to change the logging level configu-
	ration:
	a. Click the Edit icon 📿.
	b. Select a different logging level.
	c. Click apply .
Stopping a specific running in- stance of the virtual service.	 a. Click the Stop icon on the row of the virtual service instance. b. Click Ok in the Stop virtual service instance dialog that is displayed.
	The running virtual service instance is stopped.
Stopping multiple running in- stances or all the running in- stances of virtual services.	 a. Perform any of the following actions: Select the checkbox in the row of the virtual service instances that you want to stop, and then click Stop selected. Select the Select all checkbox in the header row, and then click Stop selected.
	Note: All running instances are selected when you click the Select all checkbox.
	 b. Click Ok in the Stop all selected virtual service instances dialog that is displayed. The running virtual service instances are stopped.

Results

You have viewed running instances of the virtual services from the **Instances** page on HCL OneTest[™] Server.

What to do next

You can perform the following tasks:

- View the configurations of a running instance of the virtual service. See Viewing configurations of running instances of virtual services on page 501.
- Modify the behavior or logging level of a running instance of the virtual service before you run tests on the virtual service. See Modifying configurations of running instances of virtual services on page 505.
- Stop a running instance or all running instances of the virtual services. See Stopping virtual services on page 512.

Viewing configurations of running instances of virtual services

After you start virtual services from the **Resources** page, you can view the details, configuration settings, routing rules, usage statistics, or logs of a specific running virtual service instance from the **Instances** page on HCL OneTest[™] Server.

Before you begin

You must have completed the following tasks:

- Been assigned a Member or Project Creator role in a team space.
- Been assigned the *Viewer, Tester*, or *Owner* role in the project so that you can view the virtual services that are running.
- Started the virtual service resources as a Tester or Owner from the Resources page.

About this task

After you have started the virtual services from the **Resources** page on HCL OneTest[™] Server, you can go to the **Instances** page and view the information about a specific running virtual service instance.

1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

 Open the project that contains the virtual service resources in the test assets by clicking Projects > My Projects > project_name.

The **Overview** page is displayed.

3. Click Virtualization > Instances in the navigation pane.

The Instances page is displayed with all running instances of the virtual services that are in your project.

- 4. Identify the running instance of the virtual service of which you want to view the details, configuration settings, and other information.
- 5. Click the **Expand** icon \geq of the instance of the virtual service.

The **Details** panel of the instance is displayed with the following details about the virtual service instance:

Note: The information displayed pertains to the configuration settings that were configured in the virtual service at the time it was created or run.

Option	Information displayed
Name	Displays the name of the virtual service.
Path	Displays the path of the virtual service resource in the project repository.
Labels	Displays the labels or tags that were entered for the virtual service when a run of the virtual service was configured.
API Environment	Displays the name of the environment associated with the operation in which the vir- tual service was created in HCL OneTest [™] API or the environment selected for the run.
Version	Displays the version of the virtual service resource that is in the project repository that was started as an instance.
Started at	Displays the date and time when the virtual service instance started.
Started by	Displays the name of the project member who started the virtual service instance.
Execution location	Displays the location of the Kubernetes cluster on which the virtual service instance ran.
	Note: The name of the remote Kubernetes cluster is displayed if the virtual service instance ran on the remote cluster or <i>Default Cluster</i> is displayed if the virtual service ran on HCL OneTest [™] Server.
Associated compo- nents	Displays the components in the system model that are associated with the virtual ser- vice.
Documentation	Displays the text that was entered on the Documentation tab of the Stub Editor when the virtual service was created in HCL OneTest [™] API.

The other panels that you can view are as follows:

- Behavior
- Routing Rules
- Statistics
- Diagnostics
- 6. Expand each panel by clicking the panel to view the information in that panel.

You can view the following information in the different panels:

Panel	Details	Details			
Behavior	The Behavior panel of the instance is displayed when expanded with the following details about the virtual service instance: Note: The information displayed pertains to the configuration settings that were configured in the virtual service at the time it was created or run.				
	Option		Information displayed		
	Performance		Displays the optimization setting and the maximum number of threads in use by the virtual service.		
	Operation Response time		Displays the operations referenced by the virtual service. You can select each operation to view the related response time and the pass through settings.		
			Displays the response time option that is in use for the selected operation within the virtual service.		
	Passthrough		Displays the pass through option that is in use for the selected op eration within the virtual service.		
Routing Rules	The Routing Rules panel of the instance is displayed when expanded. The routing rules that relate to the virtual service are displayed.				
	Column	Description			
	Activity	Indicates the routing type.			
	Target	Displays the endpoint of the target service for which requests are being routed.			
	Recipient	Displays the endpoint of the virtual service that receives the routed re- quests			

You can expand the panel for each intercept by clicking on the expand icon \nearrow . You can then find the following information:

Panel	Details	Details					
	Tab	Tab Description					
	Details	The Details panel provides the following information:					
		Option	Information displayed				
		Condition	Lists the condition that causes the traffic to be routed to a virtual service.				
			You can view the detailed condition of the rule defined for the intercept by clicking the View icon .				
			The detailed condition of the rule is displayed in the Full condition window.				
			Note: You can copy the detailed condition if you intend to use it elsewhere.				
		Routing to	Lists the virtual service to which traffic is routed.				
		Created by	Lists the user who created the rule.				
		Created at	Lists the date and time when the rule was created.				
	Activity	The Activity panel lists the log of the activities performed in relation to the routing rule. This panel also displays the details of the activity, date and time, and message for that activity.					
Statistics	The Statist	The Statistics panel of the instance is displayed when expanded.					
	displayed a	The requests received by the instance of the virtual service in the previous hour are displayed as a graph. The total requests received is indicated in the Total hits field and the activity load in the previous hour are displayed in the Activity field.					
	The view ca	The view can be refreshed by clicking the Refresh icon 乏					
Diagnostics	The Diagno details:	The Diagnostics panel of the instance is displayed when expanded with the following details:					

Panel	Details	
	Option	Description
	Logging	Displays the logging level that was configured for the virtual service.
	Init container log	Displays the link to the log of the Init container. Note: This logs contains messages that relate to con- figuring the container which is ready to run the virtual service.
	Main container log	Displays the link to the log of the main container. This log con- tains messages logged by the virtual service based on the se- lected logging level.

Results

You have viewed the information about the configuration, routing rules, usage, or logs of the virtual service instance.

What to do next

You can modify the behavior or logging level configurations of the running virtual service instance before you run tests on the instance. See Modifying configurations of running instances of virtual services on page 505.

Related information

Configuring a run of a virtual service on page 478

Modifying configurations of running instances of virtual services

After you start virtual services from the **Resources** page and before you run tests on the virtual service, you might want to modify the configurations for the behavior or the logging level of the running instance.

Before you begin

You must have completed the following tasks:

- Been assigned a Member or Project Creator role in a team space.
- Been assigned the *Viewer, Tester*, or *Owner* role in the project so that you can view the virtual services that are running.
- Started the virtual service resources as a Tester or Owner from the Resources page.

About this task

After you have started the virtual services from the **Resources** page on HCL OneTest[™] Server, you can go to the **Instances** page and identify the running instance of the virtual service for which you want to modify the configurations. You can modify the configurations for the behavior or logging levels of the running instance of the virtual service.

1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

 Open the project that contains the virtual service resources in the test assets by clicking Projects > My Projects > project_name.

The **Overview** page is displayed.

3. Click Virtualization > Instances in the navigation pane.

The Instances page is displayed with all running instances of the virtual services that are in your project.

- 4. Identify the running instance of the virtual service for which you want to modify the configurations.
- 5. Click the **Expand** icon \ge of the instance that you want to modify the configurations.

The **Details** panel of the instance is displayed.

- 6. Click **Behavior** to expand the panel and perform the following steps to change the configurations:
 - a. Click the Edit icon 🧖

The options that you can modify are enabled for editing.

- b. Select a different operation for the virtual service, if available, from the list for the Operation option.
- c. Select a different response time from the list for the **Response time** option, and then enter the values for the delay that you want to set.

You can modify the value by selecting a value from the following options:

Option	Description
No delay	Select this option for a response with no delay.
Minimum delay	Select this option for a delay in the response by entering the required delay in mil- liseconds (ms).
Uniform distribu- tion	Select this option for a uniformly distributed response time by specifying the mini- mum and maximum delay in milliseconds (ms).

Option	Description
Gaussian distri- bution	Select this option for a response time with Gaussian distribution by specifying the minimum and maximum delay in milliseconds (ms).

- d. Click apply to apply the modified settings.
- 7. Click **Diagnostics** to expand the panel and perform the following steps to change the logging level that is configured:
 - a. Click the **Edit** icon 🖉.

The Logging level option is enabled for editing.

b. Select a different logging level from the following options.

Option	Description
None	Specifies that the virtual service does not write log messages.
Normal	Specifies that the virtual service writes informational messages.
Debug	Specifies that the virtual service writes informational and debugging messages.

c. Click apply to apply the modified settings.

Results

You have viewed and modified the configurations of a running virtual service instance from the **Instances** page on HCL OneTest[™] Server.

What to do next

You can run tests that are in an API Suite in your project, which then run on the virtual service instance. See Configuring an API Suite or an API test run on page 343.

Viewing routing rules of the virtual services

When you run virtual services that are created to run on proxies or intercepts and have routing rules defined, you can view the proxies or intercepts and the routing rules from the **Intercept Rules** page.

Before you begin

You must have completed the following tasks:

- Been assigned a *Member* or *Project Creator* role in a team space.
- Been assigned the *Viewer, Tester*, or *Owner* role so that you can view the routing rules defined for the virtual services from the **Intercept Rules** page.
- Started the virtual service resources as a Tester or Owner from the Resources page.

About this task

After you run the virtual service resources that are in your project on HCL OneTest[™] Server, you can view the routing rules for the running instances of the virtual service resources, from the **Intercept Rules** page.

1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

 Open the project that contains the virtual service resources in the test assets by clicking Projects > My Projects > project_name.

The **Overview** page is displayed.

3. Click Virtualization > Intercept Rules in the navigation pane.

The Intercept Rules page is displayed.

The agents, proxies, or intercepts that are configured in the virtual service resources that are in your project are displayed.

You can find the following information that is displayed on the Intercept Rules page.

Column	Description
Activity	Lists the agent or proxy.
Target	Lists a summary view of the endpoint that was recorded or virtualized.
Recipient	Lists the destination where messages sent to are captured.

4. Expand the proxy or intercept panel by clicking the **Expand** icon \ge .

The details of the proxy or intercept are displayed in the **Details** tab in the expanded panel.

5. Click each tab to view the following information:

Tab	Description		
Details	The Details panel provides the following information:		
	Option	Description	
	Condition	Lists the condition that causes the traffic to be recorded or routed to a vir- tual service.	

Tab	Description	n				
	Option	Description				
		You can view the detailed condition of the rule defined for the proxy or in- tercept by clicking the View icon (O) .				
		The detailed condition of the rule is displayed in the Full condition window.				
		Note: You can copy the detailed condition if you intend to use it elsewhere.				
	Routing to	Lists the virtual service to which traffic is routed.				
	Created by	elsewhere. Routing to Lists the virtual service to which traffic is routed.				
	Created at	Lists the date and time when the rule was created.				
Activity		anel lists the log of the activities performed by the proxy or intercept. This plays the details of the activity, date and time, and message for that activity.				

Results

You have viewed the routing rules for the virtual service, proxy, or intercept that are running or connected to HCL OneTest[™] Server.

What to do next

You can perform any of the following tasks:

- You can view the usage statistics of the virtual services that are running. See Viewing usage statistics of virtual services on page 509.
- You can stop the running instances of the virtual services. See Stopping virtual services on page 512.

Related information

Management of virtualized services on page 467

Viewing usage statistics of virtual services

After you start virtual service resources that are in the project repositories, and then run tests on the virtual service, you can view the usage statistics of the virtual services from the **Usage** page on HCL OneTest[™] Server.

Before you begin

You must have completed the following tasks:

- Completed the prerequisite tasks before you configure a run of the HTTP virtual services. See Prerequisites for running HTTP virtual services on page 468.
- Read the prerequisite information about virtualizing the Istio based services. See Prerequisites for running virtualized Istio based services in HCL OneTest Server on page 470.
- Been assigned a *Member* or *Project Creator* role in a team space.
- Started the virtual service resources as a Tester or Owner from the Resources page.
- Been assigned the *Viewer, Tester,* or *Owner* role in the project so that you can view the usage details of virtual services.
- Ran API Suites with tests that run on the virtual service resources that are configured.

About this task

After you run the virtual services that are in a project, you can view details of the usage statistics of the virtual services from the **Usage** page on HCL OneTest[™] Server.

Important: The settings such as the **Period**, or **From** and **To** that you configure to view the usage details are retained for you during your ongoing session and the settings are retained even when you perform the following activities:

- Log out of the server and log in again.
- Log in after a server restart.
- 1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

 Open the project that contains the virtual service resources in the test assets by clicking Projects > My Projects > project_name.

The **Overview** page is displayed.

3. Click Virtualization > Usage in the navigation pane.

The Virtual Service Usage page is displayed.

The total requests that were received by all virtual services on the server are displayed as a graph.

The default view displays the usage data of the virtual services that are gathered during the previous week and grouped in an hourly interval. The total requests received from when the virtual service was started are displayed.

The metric data that is reported is for the number of requests that are received by a virtual service. The requests can be requests, messages, or other calls that are received by the virtual service.

4. Change the default settings to view the graph for the period for which you want to view the usage.

Option	Description
1 Hour	Displays the usage data of the virtual service that are gathered during the previous hour and grouped in a 20-second interval.
1 Day	Displays the usage data of the virtual service that are gathered during the previous day and grouped in an eight-minute interval.
1 Week	Displays the usage data of the virtual service that are gathered during the previous week and grouped in an hourly interval. Note: This is the default view.
Range	Displays the usage data of the virtual service that are gathered during the date range specified in the From and To fields. You can select the date and time for both the From and To fields. The data is dynamically grouped in intervals that depend on the range selected.

You can change the default view by selecting an option from the following options:



Note: You can refresh the view at any time to present the graph for the latest data by clicking Refresh.

5. View details of the virtual service by hovering the mouse over any of the data-points to view the details at that point.

The following details about the virtual service are displayed when you hover the mouse over the data-point:

- $\, \circ \,$ The date and time of the request received.
- $\,{}^{\circ}$ The number of requests received.

Results

You have viewed the usage details of the virtual services in your project that ran on HCL OneTest[™] Server.

What to do next

You can perform any of the following tasks:

- You can view the routing rules defined in the virtual service, agent, proxy, or intercept. See Viewing routing rules of the virtual services on page 507.
- You can stop the virtual service instances that are running. See Stopping virtual services on page 512.

Related information

Management of virtualized services on page 467

Stopping virtual services

After you started instances of the virtual services from the **Resources** page, you must stop the running instance from the **Instances** page when you do not want to use the instance. You can stop a single instance, multiple, or all running instances.

Before you begin

You must have started the virtual service from the **Resources** page. See Configuring a run of a virtual service on page 478.

1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

 Open the project that contains the virtual service resources in the test assets by clicking Projects > My Projects > project_name.

The **Overview** page is displayed.

3. Go to the Instances page and identify the instance of the virtual service that you want to stop.

You can select the virtual service instances that satisfy the following conditions:

- \circ The virtual service instance must be either in the In $\tt transition$ or $\tt Running$ state.
- The **Stop** icon **U** in the **Actions** column must be enabled for the virtual service instance.
- The checkbox icon 🛄 must be enabled for selection for the virtual service instance.
- 4. Perform the actions indicated in the following table:

lf	Action
You want to stop any virtual service instance that is run- ning	Perform any of the following actions: • Click the Stop icon • in the Actions column of the virtual service instance.
	 The Stop virtual service instance dialog is displayed. Select the checkbox in the row of the virtual service instance, and then click Stop selected. The Stop all selected virtual service instances dialog is displayed.

If	Action
You want to stop multiple vir-	Perform any of the following actions:
tual service instances that	${}_\circ$ Select the checkbox in the row of the virtual service instance, and
are running	then click Stop selected.
	\circ Select the Select all checkbox in the header row, and then click $\ensuremath{\text{Stop}}$
	selected.
	Note: All running instances are selected when you select the Select all checkbox.
	The Stop all selected virtual service instances dialog is displayed.

5. Click Ok.

A notification is displayed that the running virtual service instances are stopped.

Results

You have stopped a single instance, multiple, or all running virtual service instances. The stopped virtual service instance on the **Instances** page is displayed with the status as *Stopped by User* in the **State** column.

What to do next

You can restart the virtual service by completing the configurations that you want from the Resources page.

You can open and view the Main container log of the stopped virtual service.

Test results

After the tests, Suites, or schedules are run and completed, you can view the results and open the reports in HCL OneTest[™] Server to analyze the verdict, the performance, and statistics. You can also re-execute tests and schedules from the **Result** page with the same commit id.

Summary

The Results page displays the verdict summary for all the tests run in the project.

In this page, you can perform any of the following tasks:

- Display the suites only, or the tests only, or tests and suites that are run with advanced settings.
- Searching for test results. You can filter test results by using any of the following ways:
 - $^{\circ}$ By using the Search field to search for results by name.
 - \circ By selecting predefined time interval from the Selection interval drop-down list.
 - \circ By selecting To and From date from the Date Interval option.

- By clicking verdict from the Verdict summary slider (Pass, Fail, Inconclusive, or Error).
- By creating filter queries.
- Adding labels if you have a tester or an owner role.
- Adding text in the Notes field. You can also group the notes similar to a conversation in a chat channel.
- Locking test results: Locked results can be unlocked by the project owner or the project member who locked the results.
- Deleting test results.
- Comparing performance reports.
- Viewing trending reports.
- Viewing multiple reports depending on the test types and the parameters set when you execute the tests: Statistics reports, Functional Test reports, Test logs or Result data queries
- Re-executing tests with the same commit id.

For more details, see the links in the next section of this page.

Test results and reports

HCL OneTest[™] Server is a single location for hosting the results and reports of all tests run on different desktop clients and for tests run from the server.

Test results list

When a test run is complete, you can see the results on the **Results** page that you open from **Analyze > Results** in the navigation pane.

The list of test results is organized by types, you can display the suites only in the **Suites** tab, or the tests only in the **Tests** tab, or the tests and suites that are run with advanced settings in the **Advanced** tab.

Qs	Sea	rch							Selection interval	Custom ▽	No date selecte	d 📋
Verdic	ct	sum	nmar	y: 🧧 Pass 50.0%				Fail 50.0%				
New	filt	er -	Đ	G								٢
	т	ype	¢	Test \ominus	Started by	Started on 🔝	Duration 🖨	Verdict \Leftrightarrow	Components	Labels 🕀		Actions
		Ð	1	MultiplySuite StubTestNew/Logical/calcul	meenal123	Apr 28, 2021 4:49 PM	00:00:23.721	Pass	serviceA UIComp0	TS	+	• :
		Ð		AddSuite StubTestNew/Logical/calcul	meenal123	Apr 28, 2021 4:42 PM	00:00:16.312	E Fail	ServiceAB UICompOTS			o :

When you expand the results, the results details and reports cards are displayed.

Results, reports, and logs are generated for tests run from HCL OneTest[™] Server, or from desktop clients such as HCL OneTest[™] Performance, HCL OneTest[™] UI, or HCL OneTest[™] API.

You must have configured the desktop clients to publish reports of tests that are run from the desktop client to the HCL OneTest[™] Server. For more information about the publishing procedure, refer to the links at the end of this page.

Test result details

By using the default settings, you can view the following details about the test assets used in the test run in the Details card:

- The status of the test results, the date and time it was executed and completed.
- The details about the Git repository that contains the test assets.
- The execution location that uses the test asset for a test run.



Note: The execution location can be the default cluster or the location that you indicate to override a docker host or the agent location when you execute a test. For more information about test configuration, see the link at the end of this page.

- The Resource Monitoring labels (override) used in a performance schedule to control Resource Monitoring sources. For more information about controlling Resource Monitoring sources, see the link at the end of this page.
- The components column displays the components of the system model that are associated with the test execution. You can click the components to view each of them.

You can configure the information displayed in the **Details** card and the **Results** columns from the **View Settings** window. You access this window by clicking the **Settings** icon ⁽²⁾.

Depending on the attribute you cleared in the **View Settings** window, the **Details** card displays additional information about the test results.

The selected attributes are displayed in columns of the Result view.

New	filter +							index mile danse	E.
	Id	Туре	Test	Branch	Version	Result	Started by	Started on -	
	1004	88	emptyCm WebUIProje	master	b983bfe commit: b9	emptyCm	nm	Jun 2, 2020 4:59 PM	
	1005	88	cmptest-ja WebUIProje	master	b983bfe commit: b9	cmptest-ja	a nm	Jun 2, 2020 5:07 PM	
			DETAILS			R	eports		
			Finish on	Jun 2, 2020 5:09 PM			Statistics Repo	rt	đ
			Duration Status	00:02:25.608)		Mobile and We	b UI Report	Ô
			Verdict	Complete Pass			Functional Test	Report	Ô
			Labels			+	Test Log		Ō
			Git repo Git path Git commit	git@github01.h WebUIProjectCu: b983bfe commit: b983bfe	stomCode/Com				
			Execution location	Default Cluster					

Reports

The Reports card contains the links to the test reports and the logs that are displayed in a web browser.

As a default configuration, test logs are delivered in a traditional format for the executed compound tests and schedules. You can still set the __history jaeger Program Argument to produce Jaeger traces when you run the tests.

The reports are generated for Compound Tests, Schedules, and Test Suites, or for other tests (Postman or JMeter tests for example). They can be run from a desktop client or from HCL OneTest[™] Server.

You can run Web UI tests and SAP tests from HCL OneTest[™] UI and publish them to the server from version 10.1.3. You can also run and publish these tests from HCL OneTest[™] Server.

The following table lists the reports that are generated for each type of test and the links to help pages.

Table 10. Analyzing Reports

Report	Tests type	Product	More information
	API Suite	HCL OneTest™ API	Viewing reports
Functional Test Report	Compound Test	HCL OneTest™ UI	
	AFT Suite		Unified Demont
	Functional Test (for SAP test)		Unified Report

Report	Tests type	Product	More information		
	Functional test (For Web UI tests)				
Mobile and Web UI Report	Compound Test	HCL OneTest [™] UI and HCL OneTest [™] Performance	Mobile and web UI test result reports		
кероп	AFT Suite	HCL OneTest™ UI	Unified Report		
	Compound Test	HCL OneTest [™] UI and HCL OneTest [™] Performance	Reports and counters		
	AFT Suite	HCL OneTest™ UI	Service Performance report		
Statistics Report	Functional test (For SAP and	HCL OneTest™ UI	From the Statistic reports, you can add coun- ters. Refer to Adding additional counters on a separate page.		
	Web UI tests) VU Schedule	HCL OneTest [™] Performance	You can also display the statistics of coun- ters on graphs. Refer to Displaying counter data in tables or as graphs.		
	Rate Schedule Compound Test	HCL OneTest™ UI			
	AFT Suite				
Test Log	Functional tests API Suites and API tests	HCL OneTest™ API	See Test logs on page 529.		

Table 10. Analyzing Reports (continued)

Related information

Publishing test results to the server from HCL OneTest API Publishing test results to the server from HCL OneTest Performance Publishing test results to the server from HCL OneTest UI Test run configurations on page 327 Creating search queries to filter test results on page 517

Creating search queries to filter test results

To filter the test and suite results list, you can create a search query that you apply as a filter in HCL OneTest[™] Server.

About this task

To filter the list of test and suite results, you can use rules and group of rules in your query. This procedure explains how to create a query that contains two rules and a group of rules as an example, and how to select other filters.

1. Click New filter on the Result page.

Follow these steps to add a rule in your query:

- 2. Select Add a rule in your query, and enter or select the required attribute in the fields to define the rule:
 - a. Select the first attribute that you want to query in the drop-down list.
 Example
 Select Verdict.
 - b. Select the condition as equal to (=) or not equal to (!=), Contain or Not contain.
 - Example

Select =.

c. Select a value for the first attribute you selected.

The content of this field depends on the option you selected as first attribute. Enter a value for the **id**, **TypeTest**, **Version**, **Result**, **Labels**, **Branch**, **Test path**, and **Text** attributes. For the other attributes, select a value in the drop-down list.

Example

Select Fail.

- d. Select either the **AND** or the **OR** operator in the first field to add a condition to compare the first rule with another rule.
- e. Select Add rule in the drop-down list.
- f. Select an attribute, a condition, and select or enter a value.

Example

Select Test as an attribute, select = as a condition operator, and enter mytest as a value.

Follow these steps to add a group in your query:

3. Select Add group in the drop-down list.



Note: A group is a collection of rules and can also contain other groups within a query. You can add a rule or a group within this group.

4. Select a condition operator.

Example

Select Or.

- 5. Select **Add rule** in the drop-down list to add a rule in the group.
- 6. Select the required an attribute, an operator, and enter a value for the rule.

Example

Select the Type attribute, = as an operator, and Compound Test as a value.

- 7. Select Add rule to add another rule in the group.
- 8. Select and enter the appropriate parameters as you did for the other rules.

Example

Select Type as an attribute, = as a condition, and VU Schedule as a value.

9. Click **Apply** if you want to apply the filter now.

You can cancel the query or save the query when the results are found.

Test	*	=	-	mytest			×	
	Туре		=		Compound Test	•	×	
Or -	Туре	•	=	•	VU Schedule	•	×	

10. Click Save.

Proceed as follows to select your filters:


11. Enter a name for the filter and save in the dialog that is displayed.

Result

The filter is displayed as a favorite filter.

Verdict summary:	Pa:	ss 50.0%		In	conclusive 50.09	6		
New filter +	myfil	ter X					#	Ø
🗸 Туре	Test	Started by	Started on \checkmark	Duration	Verdict	Labels		Actions

12. Click the icon $\stackrel{\Rightarrow}{=}$ to select the filters you created from the list of saved filters.



13. Click a filter in the list of saved filters. If a filter does not display in the list, enter the name of a filter in the search field and select it.



Note: You can delete a filter from the list or disable filters by selecting none in the list.

14. Apply the selected filter.

Result

The filter is displayed as a new favorite filter in the **Results** page.

Comparing test reports

After you run performance tests, you can analyze the difference between two or multiple test results in HCL OneTest[™] Server. For example, you can compare the performance of an application at different time slots or different milestone builds between two test results.

About this task

You can compare the test runs for performance tests that are in the same project or in different projects.

- 1. Select results in the **Results** page by checking the boxes in the first column.
- 2. Click the 🔛 icon



Note: When comparing multiple runs, you cannot compare multiple time-ranges or stages.



Result

The two or multiple test results are displayed in a browser window in the same report.


Viewing trending reports

When the performance test runs are complete, you can view the trend of response time for an application over a period of time in HCL OneTest[™] Server from trending reports. In addition to the response time, you can view the trend for the loops, transactions, and performance requirements for the application.

About this task

The trending reports are available for performance tests only.

- 1. Select results in the first column in the **Results** page.
- 2. Click the eigen icon to view the trending reports.



Results

You can analyze the trend information for multiple test results in the same report from a browser window.

Re-executing tests from results

You can re-execute a test, a schedule, a collection of tests or schedules from HCL OneTest[™] Server if you want to keep the same commit id.

Before you begin

You must have executed a test or multiple tests from the Execution page in HCL OneTest[™] Server.

Re-executing a test from the **Results** view requires a Tester or an Owner role.

About this task

The following procedure describes how to re-execute a single test or multiple tests at a time.

Perform all the following steps from the Results page.

- · Proceed as follows to re-execute one test at a time:
 - Identify the test that you want to re-execute and click the **Re-execute** button in the Actions column.
 Result

The **Execute test asset** dialog displays the same parameters as the ones that were set to execute the initial test from the **Execution** page.

2. Select another Version of the test.

Note: If you select another version of the test, the settings configured in the dialog and in the **Environment**, **Data Sources** and **Locations** tabs might change.

3. Modify the Schedule parameters.



Note: If you don't want to execute the test now, schedule the time when you want the test to be re-executed.

- Click the Environment tab and select another API test environment if multiple environments were initially set for a test that is running an API Suite.
- Click the Data Sources tab and select an override option if multiple data sources were defined for the initial test run.
- 6. Click the **Variables** tab and add a new variable if you want to re-execute a test asset with a different variable from the one configured in the asset.
- Click the Location tab to override the default cluster location if the test asset has a docker host or static agents configured.
- 8. Click Advanced to modify the advanced parameters that were set for the initial test run.
- 9. Enter a new **Program Argument** if applicable to the test.



Note: If Jaeger is installed with HCL OneTest[™] Server, you can enter the -history jaeger Program Argument to produce Jaeger traces when you run the tests.

- 10. Enter a new instance of Java arguments if applicable to the test.
- 11. Enter the environment variables that must be passed to the test run at runtime in the **Environment** Variables field.
- 12. In the **Resource Monitoring** tab, click the **+**, and press the Ctrl + Space keys, or enter the initial letter of a label to select a label in the list and override the current sources in the schedule.

Note: The Resource Monitoring tab is displayed for performance schedules and only if you have enabled the Resource Monitoring from Service option from HCL OneTest[™] Performance.

The label field is grayed if you don't have any label entered in your current project. To collect data during the test execution, you must first enter labels in the Resource Monitoring sources page from HCL OneTest[™] Server.

For more details about controlling Resource Monitoring sources and labels, see the links at the end of this page.

- 13. Click the **Re-execute (**) icon to re-execute the test now or at a scheduled time.
- · Proceed as follows to re-execute multiple tests at a time:
 - Click the checkboxes for the tests that you want to re-execute. You can select them one by one or select all of them.
 Result

A toolbar is displayed.

2. Click the **Re-execute** icon **O** in the toolbar.

Result

A message indicates the number of selected tests and the number of tests to be re-executed. The tests are re-executed with the same initial commit ids and parameters.

3. Click Execute.

Result

You can view the results, logs, and reports of the re-executed tests in the Results page.

Related information

Adding a project on page 727 Test results and reports on page 514 Controlling resource monitoring sources in a schedule on page 581 Test run configurations on page 327

Test results data in Grafana

By using HCL OneTest[™] Server Results Data and Grafana, you can retrieve and explore test log data that is generated in HCL OneTest[™] Server. You must install and configure the HCL OneTest[™] Server Results Data plugin in Grafana and create an instance of a data source that you use to explore your test log data.

Grafana is a visualization and analytics software. You can use Grafana to explore HCL OneTest™ Server metrics.

You must use HCL OneTest[™] Server Results Data, which is a data source plugin, to make requests to HCL OneTest[™] Server and represent data in a Grafana dashboard.

Installing and configuring HCL OneTest Server Results Data

You must install and configure HCL OneTest[™] Server Results Data that is delivered as a plugin along with HCL OneTest[™] Server to view and analyze the log data in Grafana. You can view the test log data that is generated when you run a test from HCL OneTest[™] Server in a Grafana dashboard.

Before you begin

You must have configured your installation so that Grafana server can access HCL OneTest™ Server.

- 1. Download HCL OneTest[™] Server Results Data plugin from the following URL: <your server address>/ artifacts/grafana/hcltechsw-otsresults-datasource.zip.
- 2. Install HCL OneTest[™] Server by extracting the compressed file into your Grafana plugin directory.

Important: Before you install HCL OneTest[™] Server, you must be aware that you must use an additional helm command parameter **gateway.allowedOrigin** during the installation or you can run this command after installation too as detailed in Additional Helm parameters on page 58.

- 3. Restart the Grafana server.
- 4. Enter the address of the local Grafana server in your web browser:

Important: The plugin is signed to be used with http://localhost:3000 or http://localhost:8080 URLs.

5. To verify that HCL OneTest[™] Server Results Data is available in Grafana, follow these steps:

- a. Click Configuration > Plugin in the left navigation panel of Grafana.
- b. Enter ${\tt HCL}$ <code>OneTest Server Results Data</code> in the search bar in the Plugins tab.
- c. Click HCL OneTest[™] Server Results Data in the search results.

Result

The HCL OneTest[™] Server Results Data readme page is displayed. You can find the links to HCL OneTest[™] Server documentation and the plugin's description in this page.

6. Create an instance of data source in Grafana for HCL OneTest™ Server Results Data.

Note: Only users with the organization admin role can add data sources.

- a. Click **Configuration > Data sources** in the left navigation panel.
- b. Click Add data source.
- c. In the search bar, enter ${\tt HCL}$ <code>OneTest Server Results Data, and press Enter.</code>

HCL OneTest Results Data is displayed in the search results.

d. Click Select.

The data source configuration panel is displayed to enter the data source settings.

e. Click **Default** if you want to define this instance of HCL OneTest[™] Server Results Data as the default data source in Grafana.



Note: Ensure that HCL OneTest[™] Server Results Data is accessible through a web browser.

- f. Enter a name to identify the data source.
- g. Enter HCL OneTest^m Server URL in Server.
- h. Enter the token that you created from HCL OneTest[™] Server to enable third-party integrations.
- i. Click Save and test.

Result

If the test is successful, an instance of data source is created for HCL OneTest™ Server Results Data.

Results

HCL OneTest[™] Server Results Data is displayed in the list of data sources in Grafana.

What to do next

You can retrieve the test log data in HCL OneTest[™] Server by using queries.

Related information Download Grafana Install Grafana plugins Managing access to HCL OneTest Server on page 708 Add a data source Explore Viewing test results data in Grafana on page 526

Viewing test results data in Grafana

After you install and configure HCL OneTest[™] Server Results Data, you can retrieve and view the test log data, generated in HCL OneTest[™] Server, by using queries. Then you can analyze your test log data in a graph and a table, or in a Grafana dashboard.

Before you begin

To be able to view your test log data in the HCL OneTest[™] Server Results Data dashboard, you must have performed the following tasks in HCL OneTest[™] Server:

- Run your tests with the appropriate option in the advanced settings to get test logs results in HCL OneTest™ Server. For more information about the procedure, refer to Test logs on page 529.
- Installed the HCL OneTest[™] Server Results Data plugin.

- Run Grafana with one of these ports: http://localhost:3000 or http://localhost:8080.
- Created an instance of data source for HCL OneTest[™] Server Results Data. For more information about the procedure, refer to Installing and configuring HCL OneTest Server Results Data on page 525.
- 1. Click Configuration > Data sources in the navigation panel in Grafana.
- 2. Click HCL OneTest[™] Server Results Data in the list of data sources.
- 3. Click **Explore** in the navigation bar.
- 4. Enter the Project id.

The Project id is required.

5. Enter the Result id.

The Result id is optional.

Note: If you enter your project id only, you get all the results that are generated in your project.

- 6. Click the Events or the Activities tab according to the target you want to be returned in your query.
- 7. Enter the Query Filters.
- 8. Enter the Timing value and Value.

The timing values are sorted in ascending order.

The value must be numeric so that it can be used in a graph.

Tip: To find all the information needed in the **Explore** page of HCL OneTest[™] Server Results Data (project and result numbers, query filters for the activities or the events, query filters, and timing values), perform one of the following procedures:

- Select a result in the Queries page in HCL OneTest[™] Server and copy the result number, query filters for the events or the activities, query filters, and timing values. You can find the project number in the URL of the Queries page.
- Click Copy curl command in the Queries page in HCL OneTest[™] Server and paste the curl command in a text editor. You can find all the information you need in the command.
 curl-X:POST[™] + 'accept: application/json' -H'Content-Type: application/json' -d'("operator","and","rules":[["field","Type","operator","sule","JMeterAction"]])' https://n
- 9. Click **Add query** if you want to combine queries from different projects, results ids, or with different properties in the query filters.
- 10. Click Run query.
- 11. Select the appropriate time range to explore the data in the default graph and table in Grafana.

Results

Your queries are set for your project and results, you can explore the log data.

What to do next

You can build a dashboard including graphs, charts, gauges, tables to get customized visual representations of your test result data and select options to display the test result values. See Dashboard overview for more details about dashboards in Grafana.

Viewing Surefire format reports

After you execute JMeter, JUnit, API, and Functional tests with advanced settings in HCL OneTest[™] Server, you can view the test results in a Surefire format report by using dedicated URLs.

Before you begin

You must have configured your tests with one of the following parameters:

• For JMeter, JUnit, Postman, and HCL AppScan CodeSweep Suites, set the history parameter with cisterna

value in the Additional Configuration Parameters field in the Advanced settings

• For API Suites, AFT Suites, Compound tests, Functional tests, and API tests, set the -history cisterna

parameter in the **Program Arguments** field in the **Advanced** settings

About this task

When a test run is complete, you can see the test result data in a report that is in a Surefire format. You can view this report by using dedicated URLs, and you do not have to do any import task.

1. Click **Analyze > Results** in the navigation pane.

Result

The **Results** page is displayed.

2. Click a test result and note its project identifier and test result identifier (Id) in the URL of the test log that is displayed in your browser. The URL is in the following format: https://myProductionServer.com/#/Initial/

project/<ProjectId>/analyze/test-log/<ResultId>.

The identifiers are required to view the Surefire test logs in the following steps.

3. Enter one of the following URLs with the appropriate information in a web browser or in an external tool that you use to view Surefire reports:

o /rest/projects/<ProjectId>/data/views/surefire/

Enter your REST API address and the project identifier to view the list of all test cases in the project with details about their status.

Example: https://myProductionServer.com/rest/projects/230200/views/surefire/

° /rest/projects/<ProjectId>/results/<ResultId>/data/views/surefire/

Enter your REST API address, the project identifier, and the test result identifier to view the results for this test result id in the project.

Example: https://myProductionServer.com/rest/projects/230200/results/80250/data/views/surefire/

Results

The test result reports are displayed in a Surefire format.

Related information Test logs on page 529 Test log queries on page 543

Test logs

When you start a run of a test asset, HCL OneTest[™] Server starts to log information about the test run in a test log. You can view the test log while the test runs and after the run is completed from the **Test Log** page.

Overview

HCL OneTest[™] Server captures the test log for the supported tests that you can run on HCL OneTest[™] Server. For the list of supported tests, see Suites and tests that are supported on HCL OneTest Server on page 21.

HCL OneTest[™] Server uses an in-built PostgreSQL database to store information about the test while the test runs on the server. HCL OneTest[™] Server captures and displays the test log as the default configuration and you do not have to configure other settings during or after installation of the server.

Supported formats of test logs

The formats in which you can view the test logs are as follows:

Log format	Description	Action	
Default format	Displays the test log in the in-built format on the Test log page. For example, the test log can be as follows:	You do not have to set any Program argumen while you configure the test run.	
Text format	 o End Displays the test log in a plain text format and is displayed in a different browser tab or window than the one that displays the Test log page. For example, the test log can be as follows: 	You must set the -history testlog Program Argu- ment in the Advanced settings dialog while you configure the test run.	

Table 11. Supported formats for test log display

Log format	Description	Action
	Name: autoResults Description: Test Version: null Verdict: fail Type: com.ibm.rational.test.lt.lttest 	
Jaeger trace	Displays the test log as Jaeger traces and is displayed in a different browser tab or window than the one that displays the Test log page. For example, the test log can be as follows:	Before you can configure the server to display the test log as a Jaeger trace, you must ensure that you have installed Jaeger in the cluster. See Considerations for using Jaeger traces in re- ports on page 283. You must set the -history jaeger Program Argu- ment in the Advanced settings dialog while you configure the test run.

Table 11. Supported formats for test log display (continued)

Activities and events

The information about the tests that is collated by HCL OneTest[™] Server can be classified into the following types:

Table 12. Types of inform	mation collated for test logs
---------------------------	-------------------------------

Information type	Description
Activity	Specifies the events that are performed when the test runs as part of a test step. An activity comprises different events and is represented as a collection of events that were performed over time.

Information type	Description
	For example, opening a specific web page by using a web browser in the test can be an ac- tivity that comprises the different events such as connecting to the web site, sending of a request, and receiving a reply. Each of these events might take a specific amount of time, which are captured in the test log.
Event	Specifies an action performed as part of a test step. For example, start connection can be an event in a test that requires a specific web page to be opened in a web browser, as detailed in the example for an activity. The exact time at which this event occurred when the test ran is captured in the test log.

Table 12. Types of information collated for test logs (continued)

Test log tasks

You can find information about the tasks that you can perform on the the test logs in the **Test log** page. The test logs for the tests that you ran on HCL OneTest[™] Server are displayed in the **Test log** page.

The tasks that you can perform on the test logs are summarized in the following table:

Table 13. Test log tasks

Task	More information
Viewing test logs after you start a test run on the Execu- tion page.	Viewing test logs after you start a test run on page 531
Viewing test logs after the test run is completed.	Viewing test logs after the test run is completed on page 532
Viewing details about the test log.	Test log details on page 536

Viewing test logs after you start a test run

When you configure and start a test run, you can view the test log that is created progressively while the test runs.

Before you begin

You must have configured and started a test run. See Test run configurations on page 327.



1. Click **Show in progress page** icon ¹ in the **Actions** column of the test asset on the **Execution** page.

The asset is displayed on the **Progress** page.

- 2. Click the Open action menu icon 1.
- 3. Click the **View test log** option.

The **Test log** page is displayed with the test log collated for test run.



Note: Because the test log is collected progressively as the test runs, you must click **Refresh** to view the latest or the updated test log.

Results

You have viewed the test log for the test asset that you ran.

What to do next

You can view the details of the test log and decide on the actions you might want to take on the test log. See Test log details on page 536.

Viewing test logs after the test run is completed

After you configure a test run and the run is completed, you can view the test log that is created for the test.

Before you begin

You must have configured and started a test run, and noted that the test run has the status as *Complete* displayed on the **Progress** page.

About this task

You can view the test log that is created for a specific test run from the following pages:

- The Progress page. To view the test log from the Progress page, go to Step 1 on page 532.
- The Results page. To view the test log from the Results page, go to Step 2 on page 533.
- The Test log page. To view the test log from the Test log page, go to Step 3 on page 535.
- 1. Perform the following steps after the test completes its run:
 - a. Go to Execute > Progress, if you are not already on the Progress page.

The test assets that are running or have completed their run are listed. If you are already on the **Progress** page, only the test asset that you selected on the **Execution** page is displayed with the status as *Complete*.

- b. Click the **Open action menu** icon under the **Actions** column in the row of the test asset.
- c. Click the View test log option.

The **Test log** page is displayed with the test log collated for test run.

- d. Go to Results on page 536.
- 2. Perform the following steps after the test completes its run:
 - a. Go to **Analyze > Results**.

The test assets that have completed their run are listed.

b. Select the tab based on the type of test assets that you ran as indicated in the following table:

If	Then
You want to run AFT Suites, API Suites, Com- pound Tests, Rate Schedules, VU Schedules, JMeter tests, JUnit tests, or Postman tests	Click the SUITES tab.
You ran API tests, Functional tests, or Perfor- mance tests.	Click the TESTS tab.
You want to find Suites and tests by using cus- tom filters, when you ran Suites and tests.	Click the ADVANCED tab.

- c. Identify the test asset that you ran by performing any of the following actions:
 - Scroll through the list.

i **Tip:** You can hover over the icon in the **Type** column to know the type of the test asset.

Note: You can also identify the type of the asset from the icon that represents the test type as shown in the following table:

lcon	Represents	Listed in the SUITES tab	Listed in the TESTS tab	Listed in the AD- VANCED tab
-63-	API test		0	0
•	Functional test		0	0
٢	Performance test		0	0

	lcon	Represents	Listed in the SUITES tab	Listed in the TESTS tab	Listed in the AD- VANCED tab
		AFT Suite	0		0
	5	API Suite	0		0
	© ⊕ ⊕	Compound Test	0		0
_	0	HCL AppScan CodeSweep	0		0
	/ JMeter	JMeter Test	0		0
	Ju	JUnit Test	0		0
	0	Postman test	0		0
	6	Rate Schedule	0		0
	0	VU Schedule	0		0

- Search for the test asset by entering any text contained in the test asset name in the **Search** field.
- Click the **Filter** icon in the **SUITES** or **TESTS** tab to filter the displayed assets based on the asset type.

For example, select **API Suite** in the **SUITES** tab to display all API Suites or select **Functional Test** in the **TESTS** tab to display all Functional tests that are in the branch.

- Click the **Filter** icon **W** in the **ADVANCED** tab, and then create a filter query by using the **New filter** option by performing the following steps:
 - i. Click New filter.
 - ii. Enter a name for the filter.
 - iii. Select an operator, and add a rule, or a group of rules.
 - iv. Add or enter the relevant parameters and either select or enter the condition and the criteria for the condition.

You can select a parameter from the following list:

- Type
- Test Asset Name
- Test Asset Path
- Last Result
- Next Run
- Components
- v. Save the filter query to save and apply the filter query to filter the assets based on the query.

The test assets that match the filter criteria are displayed.

• Retrieve and apply a saved filter query, if you have saved filter queries previously by performing the following steps:

Note: The filter query applied previously is selected and the assets based on that filter query are displayed. To apply a different filter query, you must have created and saved the filter query.

i. Click the Filter icon \mathbf{V} in the ADVANCED tab.

The filter queries that you created and saved are displayed.

ii. Click the filter that you want to apply.

The test assets that match the filter criteria are displayed.

You have identified the test asset that you ran.

d. Click the test asset under the Test column.

The results and reports panel is displayed.

- e. Click the Reports tab, if it is not already open.
- f. Click the Test Log link.

The test log created for the test run is displayed in the Test log page.

- g. Go to Results on page 536.
- 3. Perform the following steps after the test completes its run:
 - a. Go to Analyze > Test Log.

The Test log page is displayed. The test assets that were run are displayed.

- b. Identify the test asset by its name or the type for which you want to view the test log.
- c. Click the test asset under the Test column.

The test log created for the test run is displayed.

d. Go to Results on page 536.

Results

You have viewed the test log for the test asset that you ran.

What to do next

You can view the details of the test log and decide on the actions you might want to take on the test log. See Test log details on page 536.

Test log details

You can find information about the details that are displayed for a test log on the **Test log** page. You can also find information to use the different options in the UI to change the view of the test log, find details of the events captured, navigate through the log, view or download attachments that are captured.

Before you can view the test log, you must have started a test run and opened the test log that is displayed on the **Test log** page.

An example of a test log that is displayed on the **Test log** page is as follows:

Test · Test log				
5cmptestsAFT May 23rd 2022 4:38 PM	Back to test logs Refresh			
Q Search events Flat view Tree view Expand C :	Properties UI Step - Start http://www.google.com/?gws_rd= Date Tin			
✓ ■ Execution - 5cmptestsAFT ✓ % User Group - firefox 1 > % User Group - firefox 1 > % User Group - firefox 2 > % User Group - firefox 3 > % User Group - firefox 4 > % User Group - firefox 5 < Run Status Changed: Initializing Computer(s)				
	A1E938D3B637DCC0F90CB73137383237			

You can find the following details that are displayed on the Test log page:

Details about	Examples as displayed in the Test log page
The project name	An example of the project name that is displayed is as follows: Test
The name of the page	An example of the page name that is displayed is as follows:
	You can click the <u>Test log</u> link to view the test logs of all tests that ran in your project, if you are viewing the test log of a specific test run.
The name of the test asset	An example of the name of the asset that is displayed is as follows: 5 cmptestsAFT
The date and time when the test run was started from the Execution page	An example of the date and time when the test run was started that is dis- played is as follows: May 23rd 2022 4:38 PM
The activities and events captured in the test log are displayed in the Tree view in the Test log panel.	An example of the log in the tree view that is displayed is as follows:

Table 14. Test log details (continued)

Details about	Examples as displayed in the Test log page	
An event in the test log. Details of the event is displayed in the Properties panel.	Image: Construction of the end of t	

Details about	Examples as displayed in the Test log page
The link to a URL that is recorded in an event. The URL is displayed as a link. When you click this link, the spe- cific URL opens in a web browser.	An example of a link recorded in the event. Url http://detectportal.firefox.com/canonical.html
An attachment of an event in the test log. The details of the attachment is displayed in the Properties panel.	An example of a text extracted from the attachment. Status Line HTTP/1.1 200 OK Content Size 89,461 i span[data-mw-comment-start][position:relative;top::lem].ext-discussiontools-init-replylink-buttons[user- select::one;display:none;text-indent:0].mw-content-ltr .ext-discussiontools-init-replylink-buttons[mergin- left:0.5:em].mw-content-rtl .ext-discussiontools-init-replylink-buttons[display:inline-Tlex].client- nojs.ext-discussiontools-replytool-enabled .ext-discussiontools-init-replylink-buttons[display:inne].ext-discussiontools-init-replylink-buttons[display:inne].telk. overlay .ext-discussiontools-init-replylink-buttons[display:inne].ext-discussiontools-init-replylink-buttons.ext-discussiont
The reason of a Verification Point (VP) that is captured in an event in the test log is displayed in the Prop - erties panel.	An example of the reason in a VP that is displayed in the Properties panel is as follows: Reason Test failed: code expected to equal / ******* received : [[[200]]]

Table 14. Test log details (continued)

You can perform the actions detailed in the following table to change the view of the test log, find details of the events captured, navigate through the log, view or download attachments that are captured.

Table 15. Tasks that you can perform on the Test log page

Task	Action
Changing the <i>Tree view</i> to a <i>Flat view</i> for the display of events in the test	Click O to toggle from the Tree view to the Flat view .
log panel.	

Task	Action
Note: The <i>Tree view</i> is the default view of the events in the test log.	Note: You can change the view from the one that is displayed by clicking .
Expanding the display of events in the test log panel.	Click Expand to expand the events that are contained within the event selected in the test log panel. For example, the collapsed view in the test log panel can be as fol-
	 Execution - 5cmptestsAFT Evention - 5cmptestsAFT Evention - 5cmptestsAFT Event is cript Event is event is even event is event is event is even even event is even even even even even even even eve
	When the event is expanded, the view in the test log panel can be as fol-
	Image: Second state of the second
	lows:

Table 15. Tasks that you can perform on the Test log page (continued)

Task	Action
Collapsing the display of events in the test log panel.	Click Collapse to collapse the events that are contained within the event selected in the test log panel.
Viewing primary activities when all activities are displayed.	Perform the following actions in the test log panel:
	1. Click the Open action menu icon.
	2. Click Show only primary activities.
	The primary activities captured in the test log are displayed.
Viewing all activities when only pri- mary activities are displayed.	Perform the following actions in the test log panel:
	1. Click the Open action menu icon.
	2. Click Show all activities.
	All the activities captured in the test log are displayed.
Viewing failures captured in the test log.	The test log displays events marked with a colored vertical bar as follows:
	• A green bar is marked for an event that passed in the test step.
	 An orange bar is marked for an event that had an error in the test step.
	• A red bar is marked for an event that failed in the test step.
	For example, the view can be as follows:
	 ✓ Ju JUnit container - min-ju ✓ & JUnit container - min-ju
	✓ ♥ Test - subtractio ♥ Complete
	> C Test - addition
	V 🛛 Test - division
	You can navigate up and down in the view from one error or failed event to
	another one by using arrows 🧿 🗐.
Searching for events in the test log.	In the search bar, you can enter text to find instances of events and proper-
	ties that match with the text you entered.

Table 15. Tasks that you can perform on the Test log page (continued)

Task	Action	
	As a result of the search, the title of the nodes in the view and the names of the properties are highlighted. When the number of results found is dis- played, you can press the F3 key to navigate from one search result to an- other in the tree view or flat view. You can press Ctrl and F3 to navigate from one result to another in the properties pane.	
Viewing the properties related to the event that you select in the test log panel.	When you select an even in the test log panel, its properties are displayed in the properties panel. For example, the details that are displayed for an event can be as follows:	
	Properties UI Step - Start http://www.google.com/?gws_rd= Date Time Time Mon, May 23rd 2022 4:42:23.379 PM Data : CoPreview Free Start Provide Free Start Prov	
	 The date stamp showing the time at which the event was captured in the test log. You can toggle between the calendar time and the duration from the time the test started its run in the cluster by clicking the Date and Time toggle icon . In the example, the date that is displayed in the Time field is as follows: 	

Table 15. Tasks that you can perform on the Test log page (continued)

Task	Action		
	Time		
	Mon, May 23rd 2022 4:42:23.379 PM		
	When the Time option is selected, the duration that is displayed in the Time field is as follows:		
	Time 00:03:42.177		
	This time is the time that has elapsed from the start of the test run to the event in the test step.		
	The name of the event.		
	• The event ID.		
	• Data that was captured as part of the test step. The items that are		
	captured can be images, text files, PDF files, XML files, JSON files, and other supported formats.		
	You can view the attachment that is in the Data field, if it is support-		
	ed to be viewed in a web browser by clicking the attachment. The at-		
	tachment displays in a browser tab other than the one in which the		
	Test log page is displayed.		
	You can also copy the URL of the attachment or download a copy to your computer to use the attachment elsewhere.		
Viewing all test logs in the Test log	When you view the test log of a specific test asset and you want to return to		
page.	the Test log page to view the test logs of the other test assets, you can click		
	the Back to test logs option.		

Test log queries

When a test run is complete in HCL OneTest[™] Server, if a test log is generated, you can run queries to extract and view test log data. The query is used to search for the events or activities in the test logs with a project or a result scope.

The query page contains a configuration section in which you enter and select search criteria.

The difference between an activity and an event are the following ones:

- An activity is characterized by a duration whereas an event is characterized by a particular time.
- An activity contains events.

When you define the search criteria and run a query, the returned test log data is displayed in a table. You can manage the data in the table by adding, moving, or deleting the columns.

Prerequisites

To get result log data queries, you must configure your tests with one of the following parameters to enable the test log and data query process:

• For JMeter, JUnit, Postman and HCL AppScan CodeSweep Suites, set the **history cisterna** parameter in the **Additional Configuration Parameters** field in the **Advanced** settings

Advanced

• For API tests and Suites, AFT Suites and Functional test, and Compound tests, set the -history

cisterna parameter in the Program Arguments field in the Advanced settings.



Note: When you set this parameter, you can run your queries to collect test log data into HCL OneTest[™] Server.

Query scope

A **Test result query** link is available in the test reports in the **Results** page when a test log is generated. If you click the link, it opens the query page in HCL OneTest[™] Server where you can view all the events or all the activities for the current test result only. In the **Scope** field of the query page, you find the result id. You can run new queries with different properties as search criteria for this result.

You can also run new queries with different properties as search criteria for all the results in a project if you open the query page from **Analyze > Queries** in the navigation pane. In this case, the **Scope** field is at the project level.

In the Queries page, you can perform the following actions:

- Filter the events or activities.
- Sort your query results in an ascending or a descending order.
- Add, move, or delete fields in the columns of the table that displays the data of the query.
- Save a query, rename, reset or delete a query.
- Export a query.

You can export the queries to Shell, Curl, or PowerShell scripts. You can select the script, the output format, and the number of results that are returned by the query.

Configuring and running log queries

When a test run is complete and a test log created, you can configure and run queries to view test log data in HCL OneTest[™] Server for one test log result or for all the test log results in a project.

Before you begin

You must have completed the following tasks:

- Configured and run a test. See Test log queries on page 543.
- Opened the Queries page from the Results page or the navigation panel.

Scope: Result 2204		
✓ All events	\bigtriangledown	Save as
All events		Events Activities
Query All activities		
Typ My query		
~ <u>h</u>		
Sort by		
id ASC		
~		
Copy Curl command Add co	blumn	Run Query
id id	time 1	type properties
102150.2204	Dec 14, 2021 11:43 AM	Namespace::createResult
102150.2204.A	Dec 14, 2021 11:44 AM	Element::createJMeterTest

About this task

In the **Queries** page, you can configure a query and save it. You can customize the way the log data is displayed in the results table.

- 1. Click Events or Activites.
- 2. Enter properties and operators in the Query filters to filter the list of events or activities.



Note: You can use the **Ctrl-Space** keyboard shortcut in this field to get the list of properties and operators that you can enter as filters to create your query.



Example: Select Activities and enter 'type is JUnitTest' in Query filters.

3. Click Run Query.

4. Perform the following steps to save a query:

- a. Click Save as.
- b. Enter a name to identify the new query and click Save.



Example: Enter 'My query'.

Result


The new query is displayed in the events and activities list.

- 5. Perform any of the following actions to configure the results table:
 - Enter a property followed by the ASC operator or DESC in Sort by to sort the data in the table.
 - ا 🔪 ۱

Note: ASC is used to sort the data from the lowest value to the highest value and **DESC** to filter the data in a descending order. You can use the **Ctrl-Space** keyboard shortcut to assist you. If you enter a combination of sort criteria, separate them with commas.

Example: Click the Sort by field, press Ctrl-Space and select in the list 'time' and enter 'ASC'.

- Click the action menu in a column of the table to change the column display, and then perform any of the following actions:
 - Click Insert new column, enter a field name in Search new column and click Add.
 - Click Move to move a column before or after another one in the table.
 - Click **Remove** to remove a column from the table.
- Follow these steps to add a column to the end of the table:
 - a. Click Add column.



- b. Enter a field name in Search new column.
- c. Click Add.
- 6. Click **Save** to save the configuration of the results table.
- 7. Follow these procedures to manage your query after it is created:
 - Click the action menu that is next to the **Save** button and select **Reset** if you have just modified a query and you want to undo your modification.
 - Click the **i** action menu and select **Delete** to delete the new query from the **Events and activities** list.

• Click Copy Curl command if you want to export a query.



Note: The curl command is copied to the clipboard. You can paste it in a command interface to use the query in an external tool.

Resource monitoring

When you apply load to a system under test, the amount of resources consumed by your system is increasing. If the capacity of the resources does not match the load, you can see performance issues in the results. Resource monitoring in HCL OneTest[™] Server helps you monitoring the resources of a system and establish the performance metrics and usage data of the system. Thus, you can observe the health of these resources while a schedule is running.

You can use resource monitoring while running a schedule to capture data, such as processor or memory usage, or to monitor the availability of hosts and services by using counters. HCL OneTest[™] Server provides a comprehensive view of a system under test to help determine problems. Hosts and services can be servers, virtual machines, or any local host or network services. You can also monitor remote hosts and services with agents.

Monitoring a host or a server

You can use resource monitoring to monitor any host and network service. This method is used for host targets that the service can reach directly. With HCL OneTest[™] Server, you can also monitor performance metrics that are collected and stored by a monitoring system that is monitoring a host. You can use a Prometheus server or a data collector through an exporter, OpenMetrics exporter, for example.

To monitor resources on a local system, you must add the source of the resource monitoring data from the resource monitoring page. Then you have to enter some connection settings and select the counters to monitor the sources. The metrics and usage data are exposed in a graph for each selected counter.

Monitoring a remote host with monitoring agents

You can monitor remote hosts and services with agents through wider sets of data collectors, computers, and networks. The purpose is to capture CPU load, disk space, memory, and the running process for example.

Agent-based monitoring is useful when remote services are not directly accessible from HCL OneTest[™] Server through the network. Agents are closer to the target that you want to monitor. You can set up the agent on an authorized host, for example, when access to an Apache httpd or NGINX server status page or a JVM JMX port, a Prometheus server, or an OpenMetrics exporter is restricted to one or few client hosts only. The configuration task is simplified, and no security changes are required.

Agent-based monitoring is mandatory to collect data from a Windows or Linux Performance host or from a Docker host.

To monitor a host across a monitoring agent, you must first set up a resource monitoring agent on the target host for which you want to collect the performance statistics and usage data. The agent establishes a connection with HCL OneTest[™] Server. When the connection is set, the agent is showing up in the list of agents on the resource monitoring main page. Then, you can select the agent in the list of target sources in the dialog **Access target from** in the dialog that opens from **Add a Source**.

Click the links in the next section of this page for more details on the resource monitoring tasks that you can perform in HCL OneTest[™] Server.

Related information

Resource monitoring capabilities on page 548 Resource monitoring agents on page 567

Resource monitoring capabilities

With HCL OneTest[™] Server, you can monitor a host or a service that you add to a project as a source. You can select the statistics counters that are used to collect metrics and the resource usage data throughout the monitoring system. You can visualize metrics and data that are gathered during the monitoring process in HCL OneTest[™] Server.

Requirements:

- You must be a *Team Space Owner* to create, modify and remove resource monitoring sources in a team space. Any team space *Member* (not owner) can only view resource monitoring sources.
- You must be a project *Owner* to create, modify and remove resource monitoring sources in a project. Any project *Member* (not the owner) can only view resource monitoring sources.

Supported sources

With HCL OneTest[™] Server, you can monitor resources for the following sources:

- Apache httpd server: You can optionally use agents.
- NGINX and NGINX Plus: You can optionally use agents.
- · Java Virtual Machine: You can optionally use agents.

You can monitor JVM resources from a local or a remote system. Some parameters must be set in the command before running the Java Virtual Machine. For more details, see the link to the page about starting a Java Virtual Machine on this page.

Windows Performance host:

To monitor the performance of a Windows host, you must have installed an agent on the target Windows host

or on a Windows host that is configured to access the performance data of the Windows host target.

Linux Performance host:

To monitor the performance of a Linux host, you must have installed an agent on the target Linux host.

Docker host:

A resource monitoring agent is mandatory to get a Docker data collector. The Docker host source is added to the list of resource monitoring data collectors when the agent is installed.

Prometheus server:

You can monitor metrics of a host under test that are collected by a Prometheus server. Prometheus collects metrics from monitored targets by regularly requesting appropriate HTTP endpoints on these targets (called *scraping*).

The metrics data are collected through data collectors sets (groups of monitoring counters) that are tracking the system performance. The performance data results are stored in the Prometheus database so that they can be consumed by external systems through a REST API.

In HCL OneTest[™] Server, you can query these performance metrics collected by Prometheus servers. 'PromQL' is the language for querying Prometheus metric data. Refer to Prometheus PromQL documentation for information about this query language.

You can select default queries, or create additional ones.

A Prometheus server is required. It must be configured to scrap a set of exporters, every 15 seconds by default. Pushgateway, service discovery, and Alertmanager are optional.

If HCL OneTest[™] Server cannot directly reach the Prometheus server, you can consider setting up an agent on an authorized host or on the same host that is running Prometheus.

OpenMetrics exporter:

You can monitor the metrics of a host under test that are collected and exposed through an OpenMetrics format or a Prometheus exporter format.

HCL OneTest[™] Server can scrap metrics exposed by an OpenMetrics or Prometheus exporter through metric counters. No Prometheus server installation is required, you only need to set up one or multiple OpenMetrics, or Prometheus exporters that fit your software or host target.

If HCL OneTest[™] Server cannot directly reach the Prometheus server, you can consider setting up an agent on an authorized host or on the same host that is running Prometheus.

Monitoring an NGINX server

To monitor an NGINX server, you must add the NGINX server source to HCL OneTest[™] Server, enter connection settings and select the counters that are used to capture the monitoring usage data.

Before you begin

You must have logged in HCL OneTest[™] Server and be the owner of an existing new project.

If you monitor a remote host, it must be connected with the computer that you use to access resource monitoring. See Resource monitoring agents on page 567.

You can optionally use agents.

About this task

This task applies to NGINX and NGINX Plus.

If you use an agent to connect

- 1. Click Infrastructure > Resource Monitoring.
 - The resource monitoring page opens.
- 2. In the resource monitoring page, click Add a Source and select Add an NGINX server....
- 3. Fill in the following connection settings in the New server dialog:
 - a. In **Target host**, enter the IP address or host name and port number of the host where the server to monitor is installed.

Note: For hosts that are already connected to HCL OneTest[™] Server through an agent, you have only the Access target from field enabled. Move directly to step 4.

b. In Server edition, select the appropriate server from the drop-down list.

c. In Path to the status page of the server, enter the name of the page to view the status of the server.

Note: If you select NGINX Plus (with API version 3) as a source, you must specify the name of the path to view the API root of the NGINX Plus server.

d. In Security, select the following options:

Secured with TLS/SSL

If the application server is secured with TLS/SSL.

Trust self-signed certificate

To accept the server certificate.

Do not verify host name

To ignore verification of the host name in the certificate.

Require credentials

If the server requires log-in credentials, enter a User name and Password.

e. Click Add.

The Choose Data Counters dialog opens.

4. Select and save the statistics counters to monitor the source. You can select them from the list where they follow the server logical organization.

For a faster selection, select the counters from the built-in sets drop-down list where they are organized by theme and save your selection.

HTTP Serv	ver Zones (8/8) HTTP Server Zones Errors (2/2)	-
Conne	ections and Request	
🗸 НТТР	Server Zones	
	Server Zones Errors	
Stream	m Server Zones	
Stream	m Server Zones Errors	

Note:

For Docker host, you can select different sets of counters.

 The first level of counters: Generic counters that are related to a Docker Image and all its running Docker Containers (in an exit, running or paused, created, restarted, removing, dead or transitive state).

 The second level of counters: Specific counters that are related to the existing Docker Containers.

Results

When the selected counters are saved, two tables are displayed in the resource monitoring main page. They contain the total number of sources you have added and the number of sources ordered by type.

fotal Sourc	es: 1			
	1		0	1
Av	ailable	-	Unavailable	Warning
ll Types				
1 NGINX s	erver			
1	0	1	1	

What to do next

You can click the links in the tables to view the performance metrics of your monitored system.

Related information

Viewing resource monitoring usage data on page 588

Monitoring an Apache httpd server

To monitor an Apache httpd server, you must add the Apache httpd server source to HCL OneTest[™] Server, enter connection settings and select the counters that are used to capture the monitoring usage data.

Before you begin

You must be logged in HCL OneTest[™] Server and be the owner of an existing new project.

You can optionally use agents. See Resource monitoring agents on page 567.

1. Click Infrastructure > Resource Monitoring.

The resource monitoring page opens. See Resource monitoring agents on page 567.

- 2. In the resource monitoring page, click Add a Source and select Add an Apache httpd server....
- 3. Fill in the following connection settings in the New server dialog:



Note: For hosts that are already connected to HCL OneTest[™] Server through an agent, you have only the Access target from field enabled. Move directly to step 4.

- a. In **Target host**, enter the IP address or host name and port number of the host where the server to monitor is installed.
- b. In Server edition, select the appropriate server from the drop-down list.
- c. In Path to the status page of the server, enter the name of the page to view the status of the server.

d. In Security, select the following options:

Secured with TLS/SSL

If the application server is secured with TLS/SSL.

Trust self-signed certificate

To accept the server certificate.

Do not verify host name

To ignore verification of the host name in the certificate.

Require credentials

If the server requires log-in credentials, enter a User name and Password.

4. Click Add.

The Choose Data Counters dialog opens.

5. Select and save the statistics counters to monitor the source. You can select them from the list where they follow the server logical organization.

For a faster selection, select the counters from the built-in sets drop-down list where they are organized by theme and save your selection.

Results

When the selected counters are saved, two tables are displayed in the resource monitoring main page. They contain the total number of sources you have added and the number of sources ordered by type.

What to do next

You can click the links in the tables to view the performance metrics and resource monitoring usage data for the monitored server.

Related information

Resource monitoring on page 547

Viewing resource monitoring usage data on page 588

Monitoring metrics collected by a Prometheus server

You can monitor your system resources by using metrics data that are collected by a Prometheus server while executing a schedule.

Before you begin

You must have created a project in HCL OneTest[™] Server.

You must have installed and configured a Prometheus server.

Read the concept information about resource monitoring and monitoring Prometheus server source. See Resource monitoring on page 547

About this task

The following procedure describes how to select and create Prometheus queries in HCL OneTest[™] Server. You must set a connection between HCL OneTest[™] Server and the Prometheus server first to access to the Prometheus queries.

Enter the connection settings, then select queries.

- 1. Click Add a source and select Add a Prometheus Server.
- 2. Enter the connection settings in the New server dialog box,.
 - a. In **Target host**, enter the IP address or host name and port number of the host where the Prometheus server is installed.
 - b. Enter the **Path to the API root of Prometheus** to point to the Prometheus API where the monitoring data are saved.
 - c. Enter the security parameters if required. For information about this section, see related links.
 - d. Click Add to close the dialog.

Result

The Prometheus server source is created successfully in the background and a dialog opens to select the Prometheus data queries.

3. In the **Select Prometheus queries** dialog, select queries that are available in the list to collect Prometheus metrics data by clicking the checkboxes.

You can reset the selection.

Select Prometheus queries


Choose the data to be collected from Prometheus at tp-

		Add a query \varTheta
•	Name C	Actions
~	HTTP server requests count	• 0
•	HTTP server requests seconds	• 0
~	Node CPU busy seconds	• 0
~	Node disk read bytes	• 0
~	Node disk read time	• 0
~	Node disk write time	• 0
~	Node disk written bytes	• 0
-		_ *
	Cancel Rese	t Save

- 4. Follow these steps to create a query:
 - a. Click Add a query.
 - b. Enter a name for the new query in the Create a Prometheus query dialog.
 - c. Enter a PromQL query.any keyword and press Ctrl+Space in the **Type and test your PromQL query. Result**

All the possible combinations of keywords and metrics related to your searched keyword are listed.

Type and test your PromQL query 🕕



- d. Select a query in the list.
- e. Click the link that points to the 'Querying Prometheus documentation' page in the information tool tip to find other examples of queries in a web page that you can use as samples.

Name

f. Click Test query.

If the test is successful, a green check is displayed, otherwise you get a red check with an error message.

- g. Click Create.
- 5. Proceed as follows to duplicate a query:
 - a. Click the **Duplicate** icon ^[] to duplicate a standard query.
 - Rename the duplicated query in the View the Prometheus query dialog.
 Make sure that the name you give to the query is not already used.
 - c. Modify the query type.

- d. Test the query .
- e. Click Create.

Note: You can click Create or Duplicate only if the test of the query is successful and the name of the query is not already in use.

Create a Prometheus query

Name	
JVM Memory	
Type and test your PromQL query 🕧	
jvm_memory_committed_bytes	
Test query	0
	Cancel Create

- 6. Proceed as follows to modify a query:
 - a. Click the **Modify** icon 🧖 .
 - b. Modify the name and type of the query.
 - c. Test the query.
 - d. Click Update.
 - e. Delete duplicated or created queries.
 - f. Click Save to close the Select Prometheus queries dialog.
- 7. Click Save and close the Select Prometheus queries dialog.

Results

The resource monitoring page displays the total number of sources you have added to your project and the number of sources ordered by type in cards.

What to do next

Click the links in the cards to go to the sources page and see the performance metrics for each source you added to your project. For more details, see Viewing resource monitoring usage data on page 588

Related information

Resource monitoring on page 547 Viewing resource monitoring usage data on page 588

Monitoring metrics exposed by an OpenMetrics exporter

With HCL OneTest[™] Server, you can monitor your system resources by using metrics data that are exposed by an OpenMetrics or a Prometheus exporter through metric counters while executing a schedule.

Before you begin

You must have at least one exporter or software to expose monitoring metrics with an OpenMetrics or Prometheus format.

You must have created a project in HCL OneTest[™] Server.

No Prometheus server installation is required, you only need to set up one or multiple OpenMetrics, or Prometheus exporters that fit your software or host target. Refer to the link at the end of this page to see the list of exporters.

About this task

The following procedure describes how to select and create OpenMetrics counters in HCL OneTest[™] Server. You must set a connection between HCL OneTest[™] Server and the OpenMetrics exporter to select counters.

- 1. Click Add a source and select Add an OpenMetrics exporter .
- 2. In the **New OpenMetrics exporter** dialog that opens, enter the OpenMetrics exporter details to access its exposition endpoint as follows:
 - a. In **Target host**, enter the IP address or host name and port number of the host where the server is installed.
 - b. Enter the **Path to the exposition endpoint** to point to the application where the data performance results must be stored. As the path depends on the type of exporter used, refer to the exporter's documentation and configuration to indicate the right path.
 - c. In Security, enter the security parameters if required.
 - d. Click Add to close the dialog.

Result

The source is created successfully in the background. A dialog box opens to select the OpenMetrics counters.

- 3. Click the checkboxes to select counters in the Select OpenMetrics counters dialog.
- 4. Follow these steps to create a counter:

- a. Click Add a counter.
- b. Enter a name for the new counter, in the **OpenMetrics counter**.
- c. Select metrics in the drop-down list or enter a keyword in the **Dimensions** field to enable the dynamic input help. You can also use the search field that appears in the list of metrics.

Choose a metric		
Search	٩	
http_server_reque	sts_seconds	
http_server_reque	sts_seconds_count	
http_server_reque	sts_seconds_max	
http_server_reque	sts_seconds_sum	
jvm_buffer_count_	buffers	

d. Select Dimensions from the dynamic fields when they are required.

Metric node_uname_info Dimensions domainname Show (none) machine Hide x86_64 nodename Enter a regular expression Hide matching * release Show all 4.15.0-29-generic sysname Show all Linux

- e. Select the appropriate OpenMetrics counter that you are looking for.
- f. Click Create.

Create an OpenMetrics counter

Ivm_memory_used_bytes			*
Dimensions area			
Show all	*	heap,nonheap	
d			
Show all	*	6 items selected	

- 5. Follow these steps to duplicate a counter:
 - a. Select a counter in the list, and click the **Duplicate** icon \square .
 - b. Modify the name of the counter and the Dimensions.
 - c. Click Create.
- 6. Proceed as follows to modify a new counter:
 - a. Click the Modify icon.
 - b. Modify the name, Metrics, and Dimensions of the counter in the Modify the OpenMetrics counter.
 - c. Click Update.

Note: You can create, duplicate, or update a counter only if the name of the counter is not already used.

7. Click Save and close the Select OpenMetrics counters dialog.



Note: You can delete counters, but only the ones that you created or duplicated.

Results

The resource monitoring page displays the total number of sources you have added to your project and the number of sources ordered by type in cards.

What to do next

Click the links in the cards to go to the sources page and see the performance metrics for each source you added to your project. For more details, see Viewing resource monitoring usage data on page 588.

Related information

Exporters and Integrations

Resource monitoring on page 547

Monitoring a Java Virtual Machine

To monitor a Java Virtual Machine, you must add the Java Virtual Machine source to the project in HCL OneTest[™] Server and select the counters that are used to capture the monitoring metrics.

Before you begin

You must have completed the following tasks:

• Configured and started the Java Virtual Machine from a command to connect it HCL OneTest[™] Server.

See Starting a Java Virtual Machine on page 578.

- Logged in HCL OneTest[™] Server. You must be the owner of an existing new project.
- You can optionally use agents. See Resource monitoring agents on page 567.

About this task

The Java Virtual Machine source is added to the list of resource monitoring sources when the agent is installed.

1. Click Infrastructure > Resource Monitoring.

The resource monitoring page opens.

- 2. In the resource monitoring page, click Add a Source and select add a Java Virtual Machine.
- 3. Fill in the following connection settings in the New server dialog:
 - Note: For hosts that are already connected to HCL OneTest[™] Server through an agent, you have only the Access target from field enabled. Move directly to step 4.
 - a. In **Target host**, enter the IP address or host name and port number of the host where the server to monitor is installed.
 - b. In Server edition, select the appropriate server from the drop-down list.
 - c. In Path to the status page of the server, enter the name of the page to view the status of the server.

d. In Security, select the following options:

Secured with TLS/SSL

If the application server is secured with TLS/SSL.

Trust self-signed certificate

To accept the server certificate.

Do not verify host name

To ignore verification of the host name in the certificate.

Require credentials

If the server requires log-in credentials, enter a User name and Password.

4. Click Add.

5. Select and save the statistics counters to monitor the source. You can select them from the list where they follow the server logical organization.

For a faster selection, select the counters from the built-in sets drop-down list where they are organized by theme and save your selection.

Result

When the selected counters are saved, two tables are displayed in the resource monitoring main page. They contain the total number of sources you have added and the number of sources ordered by type.

otal Sources: 1		
1	0	1
Available	Unavailable	Warning
ll Types		
1 NGINX server		
1 0	1	

What to do next

You can click the links in the tables to view the performance metrics and usage data in a graph for the monitored Java Virtual Machine.

Related information

Resource monitoring on page 547

Viewing resource monitoring usage data on page 588

Monitoring a Docker host

To monitor a Docker host, you must add the Docker host source to HCL OneTest[™] Server, enter connection settings and select the counters that are used to capture the monitoring usage data.

Before you begin

You must have completed the following tasks:

- Logged in HCL OneTest[™] Server and you must be the owner of an existing new project.
- Installed a Docker agent. A resource monitoring agent is mandatory to get a Docker data collector. Resource monitoring agents on page 567.
- Started the Docker server to connect the Docker host to HCL OneTest[™] Server through the agent.

About this task

The Docker host source is automatically added to the list of resource monitoring sources when the agent is installed.

1. Click Infrastructure > Resource Monitoring.

The resource monitoring page opens.

- 2. In the resource monitoring page, click Add a Source and select add Docker host.
- 3. Select an address to connect to the target host in Access target from.
- 4. Click Add.
- 5. Select and save the statistics counters to monitor the source. You can select them from the list where they follow the server logical organization.

For a faster selection, select the counters from the built-in sets drop-down list where they are organized by theme and save your selection. You can select different sets of counters:

- The first level of counters contain generic counters that are related to a Docker Image and all its running Docker Containers (in an exit, running or paused, created, restarted, removing, dead or transitive state).
- The second level of counters contains specific counters that are related to the existing Docker containers.

Result

When the selected counters are saved, two tables are displayed in the resource monitoring main page. They contain the total number of sources you have added and the number of sources ordered by type.

'otal Sources: 1			
1		0	1
Available	-	Unavailable	Warning
ll Types		_	
1 NGINX server			
1 0	1		

What to do next

You can click the links in the tables to view the performance metrics and usage data in a graph for the Docker host source.

Related information

Resource monitoring on page 547

Viewing resource monitoring usage data on page 588

Monitoring a Windows Performance host

To monitor a Windows Performance host, you must add the Windows Performance host source to the project in HCL OneTest[™] Server and select the counters that are used to capture the monitoring usage data.

Before you begin

You must have completed the following tasks:

- Installed and started an agent. See Resource monitoring agents on page 567.
- Logged in to HCL OneTest[™] Server. You must be the owner of an existing new project.

About this task

The Windows Performance host source is added to the list of resource monitoring sources when the agent is installed.

1. Click Infrastructure > Resource Monitoring.

The resource monitoring page opens.

2. In the resource monitoring page, click Add a Source and select add a Windows Performance host.

- 3. Select an address to connect to the target host in Access target from.
- 4. Click Add.
 - The Choose Data Counters dialog opens.
- 5. Select and save the statistics counters to monitor the source. You can select them from the list where they follow the server logical organization.

For a faster selection, select the counters from the built-in sets drop-down list where they are organized by theme and save your selection.

Result

When the selected counters are saved, two tables are displayed in the resource monitoring main page. They contain the total number of sources you have added and the number of sources ordered by type.

Total Sources: 1			
1		0	1
Available		Unavailable	Warning
All Types			
1 NGINX server			
1 0	1		

What to do next

You can click the links in the tables to view the performance metrics and usage data in a graph for the monitored Windows Performance host.

Related information

Resource monitoring on page 547

Viewing resource monitoring usage data on page 588

Monitoring a Linux Performance host

To monitor a Linux Performance host, you must add the Linux Performance host source to the project in HCL OneTest[™] Server and select the counters that are used to capture the monitoring usage data.

Before you begin

You must have completed the following tasks:

- Installed and started an agent. See Resource monitoring agents on page 567.
- Logged in to HCL OneTest[™] Server. You must be the owner of an existing new project.

About this task

The Linux Performance host source is added to the list of resource monitoring sources when the agent is installed.

1. Click Infrastructure > Resource Monitoring.

The resource monitoring page opens.

- 2. In the resource monitoring page, click Add a Source and select add a Linux Performance host.
- 3. Select an address to connect to the target host in Access target from.
- 4. Click Add.

The Choose Data Counters dialog opens.

5. Select and save the statistics counters to monitor the source. You can select them from the list where they follow the server logical organization.

For a faster selection, select the counters from the built-in sets drop-down list where they are organized by theme and save your selection.

Result

When the selected counters are saved, two tables are displayed in the resource monitoring main page. They contain the total number of sources you have added and the number of sources ordered by type.

Fotal Sources: 1		
1	0	1
Available	Unavailable	Warning
ull Types	_	
1 NGINX server		
1 0	1	

What to do next

You can click the links in the tables to view the performance metrics and usage data in a graph for the monitored Linux Performance host.

Related information

Resource monitoring on page 547

Viewing resource monitoring usage data on page 588

Resource monitoring agents

You can connect agents to HCL OneTest[™] Server from other hosts to monitor a larger set of data collectors, computers, servers, or systems, or if a server to monitor requires authorization access. To monitor these remote servers, you must configure and run the agents so that a connection is set between HCL OneTest[™] Server resource monitoring service and the agents.

Requirements:

- To connect resource monitoring agents to HCL OneTest[™] Server in a team space, you must be a *Team Space Owner*. Any other team space *Member* (not owner) can only view the resource monitoring agents.
- To connect resource monitoring agents to HCL OneTest[™] Server in a project, you must be a project *Owner*. Any project *Member* (not the owner) can only view the resource monitoring agents.
- Agent-based monitoring is mandatory to collect data from a Windows or Linux Performance host or from a Docker host.

For testing, you might need many hosts. For example, you might have one host with the application server, another host with the database server, and some hosts to apply the user load. Due to network or firewall issues, sometimes, it becomes difficult for multiple hosts to connect to each other. Resource monitoring agents are installed on the target hosts so that they can establish a connection with HCL OneTest[™] Server to gather resource statistics of the target host.

The agents always try to connect with the server through the HTTPS protocol. You must install the agent and start it. From the resource monitoring page in HCL OneTest[™] Server, you can copy the command lines to download files and run the agents. When you stop the agent, the monitoring sources that you have already added persist but the live data will not be available.

You can configure your resource monitoring agent as a service so that the agent automatically runs when the host is restarted. For details, see the documentation pages about starting resource monitoring agents on Windows or Linux.

When the agent is connected to HCL OneTest[™] Server, it is added to the main page of the resource monitoring service. Then, you can select the agent in the list of target sources in the dialog **Access target from** in the dialog box that opens from **Add a Source**.


Sources: 4							Resource	se Monitoring A	gents: 1		
4			0		0			(1)		0	
Available		Unav	ailable		Warning			Connected		Disconnected	
pes											
penMetrics expo	rter	1 Prometh	eus server		1 Docker I	ost		1 Windows	Performanc	e host	
1 0 0		1	0	0	1	0	0	1	0	0	

Installing and running a Docker agent on a remote host

You must install the resource monitoring Docker agents on the target host for which you want to monitor the resources and collect the metrics. You need to run an agent to establish a connection with HCL OneTest[™] Server.

Before you begin

- The resource monitoring service does not require access to the agent host but the agent must have reached the service host over HTTPS.
- The Docker agent must have been launched in a Docker container and requires Docker 19.03.
- 1. Click **Set up Agents to extend Resource Monitoring service** link in HCL OneTest[™] Server to access the agents page where you can find the instructions and commands that are to be used to install and run the agents.



Context	ليراك
Configure the Java agent	0
 Configure the Docker agent 	
1. Install the Docker agent Download Dockerfile	
Alternatively, you can use one of the following commands to download the Dockerfile resource:	
curl -O -J https://tp-cicd6.nonprod.hclpnp.com:/rm/agent-Dockerfile	
Or:	
wgetcontent-disposition https://tp-cicd6.nonprod.hclpnp.com:/rm/agent-Dockerfile	
2. Build the Docker image	
Once you have downloaded the Dockerfile on your host system, launch the following command to build a dedicated Resource Monitoring Docker image:	
docker buildnetwork=hostrm -t rmagent .	

2. Expand Configure the Docker agent and click Download Dockerfile to download a Docker agent.

You can also use the *curl* or *wget* commands to download the agent without accessing the resource monitoring web UI.

For more facility, use the code snippets to copy and fill in the commands with the valid offline token and the Docker file name.

For Windows:

```
curl -0 -J https://hostName/rm/agent-Dockerfile
```

For Linux:

wget --content-disposition *hostName*/rm/agent-Dockerfile

Copy the build command that is under Build the Docker image, paste it in your console and run it to build a resource monitoring Docker image.

Before you start the a Docker agent, you must build a Docker image.

docker build --network=host --rm -t rmagent


- 4. Follow these steps to run the agent:
 - a. Click to fill in the appropriate command for Windows or Linux with the valid offline token.
 - b. Click Let to copy the command to clipboard and paste the command in the console.
 - Command on Windows:

```
docker run -it --rm --privileged -e PROJECT_ID=230200 -e HCL_ONETEST_OFFLINE_TOKEN=(Enter
your offline token here) --network host -v //var/run/docker.sock:/var/run/docker.sock
rmagent
```

- Command on Linux:

```
docker run -it --rm --privileged -e PROJECT_ID=230200 -e HCL_ONETEST_OFFLINE_TOKEN=(Enter
your offline token here) --network host -v /var/run/docker.sock:/var/run/docker.sock
-v /etc:/etc -v /proc:/proc rmagent
```

c. Paste the command in the console and run the command.



Results

When the agent is started, the agent is connected to HCL OneTest[™] Server. The agent is displayed in the list of connected resource monitoring agents with the host name and status of the agent. The agent is also added to the main page of the resource monitoring service in HCL OneTest[™] Server.

What to do next

You can add a new resource monitoring source. It can be collected from a service or from the named agents, depending on the capabilities supported by the environment.

Related information

Resource monitoring capabilities on page 548

Installing and running a Java agent on a remote host

You must install the resource monitoring java agent on the target host for which you want to monitor the resources and collect the metrics. You need to run the agent to establish a connection with HCL OneTest[™] Server.

Before you begin

- The resource monitoring service does not require access to the agent host but the agent must have reached the service host over HTTPS.
- The Java agent must have been launched from a jar file and requires a Java 8 virtual machine.
- 1. Click **Set up Agents to extend Resource Monitoring service** link in HCL OneTest[™] Server to access the agents page where you can find the instructions and commands that you can use to install and run the agents.

otal Sources: 1				Add a source
1		0	0	No agents are connected to this project Set up agents to extend Resource Monitoring service
Available		Unavailable	Warning	
ll Types 1 OpenMetrics exporter	-			
1 0	0			

2. Expand **Configure the Java agent** and click **Download jar file** to download the Java agent.

You can also use the *curl* and *wget* commands to download the agent without accessing the resource monitoring web UI. For more facility, use the code snippets to copy and fill in the commands with the valid offline token and the jar file name.

For Windows:

curl -0 -J https://hostName/rm/Agent-jar

For Linux:

wget --content-disposition https://hostName/rm/Agent-jar

- 3. Configure the command as follows to run your agent:
 - a. Copy the appropriate command for Windows or Linux with the code snippets.
 - b. Enter the path to the directory that contains the agent .jar file, and paste the command.

Example

On Windows:

Example

On Linux:

```
sudo HCL_ONETEST_OFFLINE_TOKEN=(Enter your offline token here) java -jar (Enter the name of the
downloaded jar file here) --ServiceUrl=portNumber/rm --projectId=<project_id>
```

Results

When the agent is started, the agent is connected to HCL OneTest[™] Server. The agent is displayed in the list of connected resource monitoring agents with the host name and status of the agent. The agent is also added to the main page of the resource monitoring service in HCL OneTest[™] Server.

												Add a severce
tal Sourc	æ 4							Resour	ce Monitoring A	Igents: 1		
	4			0		0			(1)			0)
Available		Unav	ailable		Warrsin	1		Connected		Disconnected		
Types												
OpenMet	trics exporter		1 Promethy	eus server		1 Docker I	teo		1 Windows	Performance	e host	
1	1 0 0		1	0	0	1	0	0	1	0	0	

What to do next

You can use another method to start an agent. See Starting a resource monitoring Java agent as a service on Windows on page 572 or Starting a resource monitoring Java agent as a service on Linux on page 575. You can then add a new resource monitoring source. Resource monitoring metrics can be collected from a service or from the named agents, depending on the capabilities supported by the environment.

Related information

Resource monitoring capabilities on page 548

Starting a resource monitoring Java agent as a service on Windows

To ensure that the resource monitoring Java agent starts by itself when the host is running, you can set up the environment in such a way that the resource monitoring agent can be started as a service.

Before you begin

You must have completed the following tasks:

- Installed Java 8 on the host.
- Added HCL OneTest[™] Server to the PATH environment variable.

• Created an offline token to connect the agent securely with appropriate permissions.



Note: You can create an offline token from the User menu of the resource monitoring page or you can re-use your active offline token. The token expires if it is not used for a month.

To allow remote access to the performance data on Windows 10, you must have considered the following information:

- The user name and password are the same on the local and remote servers. Otherwise you must have provided remote server credentials.
- The remote user must be a member of the Performance Monitor Users group (start lusrmgr.msc and add the user to this group).
- The Remote Registry service must be running on the remote host (start services.msc) and must have verified the Remote Registry status).
- File and printer sharing must be enabled on the Network Interface of the remote host that is implied in the communication with the local host.
- You must have activated the following Windows Firewall rules so that the remote firewall does not block the access:
 - File and Printer Sharing (NB-Name-In)
 - File and Printer Sharing (NB-Session-In)
 - File and Printer Sharing (*)
- 1. Download the latest release of winsw.

You can choose to download WinSW.Net2.exe or WinSW.Net4.exe depending on the version of .Net framework that you already have on the host Windows.

- 2. Create a folder on your local hard drive like RMAgent-winservice.
- 3. Copy the downloaded executable to this new folder and rename the file to RMAgent-winservice.exe.
- 4. Create a new text file in the same folder and name it RMAgent-winservice.xml.
- 5. Copy and adapt the following content to this new RMAgent-winservice.xml file to set up the offline token:

```
<service>
        <id>RMAgent-winservice</id>
        <id>RMAgent-winservice</id>

            (id>RMAgent-winservice
            (anme>Resource monitoring agent
            (description>This service runs the resource monitoring agent.
            (env name="HCL_ONETEST_OFFLINE_TOKEN" value="(Enter your offline token here"/>
            (anguments>-jar %BASE%\RMAgent.jar --serviceUrl=https://<service-host>/rm
            --projectId=<projet-id>
            --autoUpgradeDownloadThen=execute:cmd,/c,start,%BASE%\auto-upgrade.bat</arguments>
            (onfailure action="restart" delay="10 sec"/>
            (logmode>rotate</logmode>
```





∘ Replace <service-host> by the host name of the host that runs HCL OneTest[™] Server. • Replace <project-id> which is the number that you find after /projects/ in the browser's URL when you browse to this project.

- 6. Create a new text file in the same folder and name it auto-upgrade.bat.
- 7. Copy the following content to this new file to upgrade the agent .jar file automatically:

```
@echo off
for /f "tokens=*" %%a in ('dir /b /od %BASE%\com.hcl.test.rm.agent-*.jar') do set newest=%%a
%BASE%\RMAgent-winservice.exe stop
del %BASE%\RMAgent.jar
mklink %BASE%\RMAgent.jar %BASE%\%newest%
%BASE%\RMAgent-winservice.exe start
```

8. Start the command prompt as an administrator and change the directory to the newly created directory:

RMAgent-winservice.


- 9. Download the agent .jar file that is available from the agents page in the resource monitoring service, under the Extend the Resource Monitoring service with agents section and save it to the same directory.
- 10. Enter the following command in the command prompt to create a symbolic link named RMAgent. jar to the agent jar file:

mklink RMAgent.jar com.hcl.test.rm.agent-<version-and-datetime>.jar

Disconnected

11. Enter the following commands:

RMAgent-winservice install RMAgent-winservice start Add a source Resource Monitoring Agents:



Notes:

In the Services Windows application, you can check whether the service is up and running. You can see in the resource monitoring page whether the resource monitoring agent is disconnected or connected.

The resource monitoring agents write the logs to the same folder in files named RMAgent-winservice.out.log, RMAgent-winservice.err.log and RMAgentwinservice.wrapper.log. If the Windows service for the agent is not started or if it is not connected to the resource monitoring service, verify the log files.

Results

The Java agent starts as a service on Windows. When the agent is connected to HCL OneTest[™] Server, it is automatically added to the list of resource monitoring sources in HCL OneTest[™] Server.

What to do next

You can monitor the Windows agent by selecting counters. See Monitoring a Windows Performance host on page 564.

Related information Other commands winsw file Resource monitoring capabilities on page 548

Starting a resource monitoring Java agent as a service on Linux

To ensure that the resource monitoring Java agent starts by itself when the host is restarted, you can set up the environment in such a way that the resource monitoring agent can be started as a service.

Before you begin

You must have completed the following tasks:

- Installed Java 8 on the host.
- Added HCL OneTest[™] Server to the PATH environment variable.
- Created an offline token to connect the agent securely with appropriate permissions.



Note: You can create an offline token from the User menu of the resource monitoring page or you can re-use your active offline token. The token expires if it is not used for a month.

About this task

This topic relies on systemd services that are the default on most modern Linux distributions. Other ways mi require adaptations of the instructions but the provided script will be a good basis in most cases.

- 1. Create a folder on your local hard drive like /opt/RMAgent-linuxservice.
- 2. Download the agent .jar file that is available from the Agents page in the resource monitoring service, below the **Extend the Resource Monitoring service with agents** section and save it to the same directory.
- 3. Create a new file /etc/systemd/system/RMAgent-linuxservice.service.
- 4. Add the following content to this new file:

```
[Unit]
Description = Resource monitoring agent
After = network.target
[Service]
Type = forking
ExecStart = /opt/RMAgent-linuxservice/RMAgent-linuxservice.sh start
ExecStop = /opt/RMAgent-linuxservice/RMAgent-linuxservice.sh stop
Restart = on-failure
RestartSec = 10
[Install]
WantedBy = multi-user.target
```

5. Create another file /opt/RMAgent-linuxservice/RMAgent-linuxservice.sh.

```
#!/bin/sh
#!/bin/sh
# Update the 3 following variables with the Server's host name, project id and offline token:
SERVICE_URL=https://<hostname>/rm
PROJECT_ID=<project-id>
export HCL_ONETEST_OFFLINE_TOKEN=<offline-token>
ARGS="--serviceUrl=$SERVICE_URL --projectId=$PROJECT_ID --autoUpgradeDownloadThen=exitFailure"
SCRIPT=$(readlink -f "$0")
RMAGENT_HOME=$(dirname "$SCRIPT")
# Ensure we're using the latest downloaded jar file
```

```
PATH_TO_JAR=`ls -t $RMAGENT_HOME/com.hcl.test.rm.agent-*.jar | head -1`
if [ -z "$PATH_TO_JAR" ]
then
 cd $RMAGENT_HOME && { curl -k -O -J $SERVICE_URL/agent-jar; cd -; }
 PATH_TO_JAR=`ls -t $RMAGENT_HOME/com.hcl.test.rm.agent-*.jar | head -1`
 if [ -z "$PATH_TO_JAR" ]
 then
    echo "Start the server at $SERVICE_URL to allow download of the latest agent jar file"
    echo "Exiting..."
    exit 1
 fi
fi
SERVICE_NAME="Resource monitoring agent"
#Pid file will reside in this script's folder
PATH_TO_PID=$RMAGENT_HOME/RMAgent-pid
#Log file will reside in this script's folder
PATH_TO_LOG=$RMAGENT_HOME/RMAgent.log
case $1 in
    start)
        echo "Starting $SERVICE_NAME ..."
        if [ ! -f $PATH_TO_PID ]; then
            nohup java -jar $PATH_TO_JAR $ARGS >> $PATH_TO_LOG 2>&1 &
                        echo $! > $PATH_TO_PID
            echo "$SERVICE_NAME started ..."
        else
            echo "$SERVICE_NAME is already running ..."
        fi
    ;;
    stop)
        if [ -f $PATH_TO_PID ]; then
            PID=$(cat $PATH_TO_PID);
            echo "$SERVICE_NAME stopping ..."
            kill $PID;
            echo "$SERVICE_NAME stopped ..."
            rm $PATH_TO_PID
        else
            echo "$SERVICE_NAME is not running ..."
        fi
    ;;
    restart)
        if [ -f $PATH_TO_PID ]; then
            PID=$(cat $PATH_TO_PID);
            echo "$SERVICE_NAME stopping ...";
            kill $PID;
            echo "$SERVICE_NAME stopped ...";
            rm $PATH_TO_PID
            echo "$SERVICE_NAME starting ..."
            nohup java -jar $PATH_TO_JAR $ARGS >> $PATH_TO_LOG 2>&1 &
                        echo $! > $PATH_TO_PID
            echo "$SERVICE_NAME started ..."
        else
            echo "$SERVICE_NAME is not running ..."
        fi
    ;;
esac
```



- ∘ Replace <service-hostname> by the host name of the host that runs HCL OneTest[™] Server.
- Replace <project-id> which is the number you'll find after /projects/ in the browser's URL when browsing to this project.

Results

The resource monitoring Java agent starts automatically when the host restarts. The Linux agent is added to the main page of the resource monitoring service in HCL OneTest[™] Server.

What to do next

You can monitor the Linux Performance host source by adding counters. See Monitoring a Linux Performance host on page 565.

Related information

systemd services

Resource monitoring capabilities on page 548

Starting a Java Virtual Machine

To monitor the sources from a Java Virtual Machine (JVM), you must first start the JVM. You must enter the IP address of the JVM, the IP port, and the security parameters in the command before running the Java Virtual Machine.

- 1. Enter The IP address of the JVM (local or remote host) and the IP port in the command that is used to run the Java Virtual Machine.
- 2. **Optional:** You can use the authentication security data to start the virtual machine. In this case, you must enter the name of the password file. You can also enter the name of an access file that might be needed if user privileges are required.

Exemple

Parameters used to launch a JVM without security:

```
java
-Dcom.sun.management.jmxremote
-Dcom.sun.management.jmxremote.port=9010
-Dcom.sun.management.jmxremote.local.only=false
-Dcom.sun.management.jmxremote.authenticate=false
-Dcom.sun.management.jmxremote.ssl=false
-jar MyapplicationFile.jar
```

Parameters used to launch a JVM with authentication security:

```
java
-Dcom.sun.management.jmxremote
-Dcom.sun.management.jmxremote.port=9010
```

```
-Dcom.sun.management.jmxremote.local.only=false
-Dcom.sun.management.jmxremote.authenticate=true
-Dcom.sun.management.jmxremote.ssl=false
-Dcom.sun.management.jmxremote.password.file=jmxremote.password
-Dcom.sun.management.jmxremote.access.file=jmxremote.access (this command is optional)
-jar MyapplicationFile.jar
```

Related information

Resource monitoring agents on page 567

Monitoring a Java Virtual Machine on page 561

Managing sources

After you add and connect monitoring sources to your project, you might want to modify the sources in you project and the configuration of the sources.

Before you begin

You must be a project owner or team space owner to add or delete sources.

About this task

In the page where you can view the resource monitoring usage data and metrics, you can also manage your sources. You can modify or delete a source, add or change statistic counters, add labels to identify the sources and use them when you execute a test to collect resource monitoring results.

1. Click Infrastructure > Resource Monitoring in the navigation pane.

If you have sources and agents in your project, you can see the cards with the number of available sources and agents in your project.

- 2. Click a link in the card of available sources to open a list of sources.
- 3. Perform any of the following actions for a monitoring source:
 - Click the **Delete** icon **III** to delete the monitoring source and click **Delete** to confirm the deletion in the dialog box.

The source is removed from the list of sources.

Click the Edit icon
 to change the target host settings.

You can change the target host address, the port, the path to the server status page and the security parameters.

- Click the **Selection** icon **t** to select additional counters or change the selected counters for other ones. The changes are reflected in the resource monitoring usage data graph.
- Click to add a label to identify the source.
- Click Add a source to add a source to your project from the list of sources.

Related information

Resource monitoring capabilities on page 548

Viewing resource monitoring usage data on page 588

Creating labels

After you connect a host or service to a project, you can add monitoring labels to identify the monitoring sources that are used when you execute a schedule from HCL OneTest[™] Server. You can also use labels in any test to collect resource monitoring usage data during a test run for a defined period of time.

Before you begin

You must have connected sources to your project in HCL OneTest[™] Server. See Resource monitoring capabilities on page 548.

About this task

You must be a project owner to add labels to the resource monitoring sources in a project and you must be a team space owner to add labels in a team space.

- 1. Click a source that is available in your project, either in the **Total Sources** cards or in the **All Types** cards from the resource monitoring page.
- 2. Click **the Labels** column of a resource monitoring source to add a label.
- 3. Enter a name for the label and press the Enter key.



Note: You can add one label or multiple labels for the same resource monitoring source. A label can contain a maximum of 200 characters.

i

Tip: You can create the same label for different sources that belong to the same logical group to monitor the whole group with only one label.

Results

The host source is identified by a label.

What to do next

You can use the created labels in tests to collect resource monitoring results or persistent usage data. See Controlling resource monitoring sources in a schedule on page 581 and Collecting and viewing resource monitoring usage data on page 586.

Controlling resource monitoring sources in a schedule

In HCL OneTest[™] Server, you can control the resource monitoring sources that are collected in a performance schedule and override them with the labeled resource monitoring sources that are available in your current Server project.

Before you begin

- You must have performed the following tasks in HCL OneTest[™] Performance:
 - Created a performance schedule of Rate or VU type.
 - Added resource monitoring sources, or the labels of resource monitoring sources to a schedule. See and Adding resource monitoring sources to a performance schedule by using labels.
 - Enabled HCL OneTest[™] Server as resource monitoring service only if you want to replace resource monitoring labels set in HCL OneTest[™] Performance with the labels that you created in HCL OneTest[™] Server.
- You must have created a project and added resource monitoring sources to your project in HCL OneTest[™] Server. See Resource monitoring capabilities on page 548.

About this task

This procedure describes how to create resource monitoring labels in HCL OneTest[™] Server and how to use them to override the source or label settings related to resource monitoring in a performance schedule. The procedure applies to the following use cases:

- To replace the resource monitoring labels that were initially set in a schedule from HCL OneTest[™] Performance with the labels that you create in HCL OneTest[™] Server.
- To enable resource monitoring sources that were not enabled from HCL OneTest[™] Performance. In that case, you can enable resource monitoring sources from the **Execution** dialog in HCL OneTest[™] Server.
- To ignore resource monitoring sources that were set in the schedule and to change them for labels that match sources that are available in the HCL OneTest[™] Server project.

- Notes: You must be a project owner to add labels to the resource monitoring sources in a project and you must be a team space owner to add labels in a team space. You must have a project owner or a tester role access to add labels to a performance schedule in a project.
 - 1. Click a source that is available in your project, either in the **Total Sources** cards or in the **All Types** cards from the resource monitoring page.

otal Sourc	es: <u>5</u> ,							Resour	ce Monitoring /	Agents: 1		
	2		3		3 0			0		(1)	
	Available		Una	vailable		Warnin	9		Connected		Disco	nnected
ll Types												
1 OpenMet	trics exporter	1	1 Promet	heus server		1 Docker?	vost		2 Windows	Performanc	e hosts	
1	Ó	0	1	0	Û	0	1	0	0	2	0	
											4	

2. Click **the Labels** column of a resource monitoring source to add a label.

+	Sources	All Types 👻	Any Status *				
	Name		Status	Added	Observed	Labels	
>	OpenMetrics at to-		available	7 hours ago	6 hours ago	(BUTv2)	•
>	Prometheus at a guine		available	7 hours ago	29 minutes ago	\$UTV2 *	•

3. Enter a name for the label and press the Enter key.

Example: Enter 'SUTv2' in three different resource monitoring sources.



Note: You can add one label or multiple labels for the same resource monitoring source. A label can contain a maximum of 200 characters.

i **Tip:** You can create the same label for different sources that belong to the same logical group to monitor the whole group with only one label.

- 4. Click **Execution** in the navigation pane and click **O** on a performance schedule in the list of tests to execute a schedule.
- 5. Click the Resource Monitoring tab in the Execute Test Asset dialog.



Note: There are different use case scenarios:



 If the Resource Monitoring from Service option was not enabled in HCL OneTest[™] Performance (see Figure 1), no source is available in HCL OneTest[™] Server project.

Figure 1:

VU Sched	ule Details
Category:	Resource Monitoring from Service

Enable resource monitoring from service

A message indicates in the **Resource Monitoring** tab that Resource Monitoring was not enabled. You can run the schedule with the resource monitoring sources that are created and labeled in HCL OneTest[™] Server (steps 1 to 6 in this procedure) by selecting labels that are in your HCL OneTest[™] Server project (step 6).

If the Resource Monitoring from Service option was enabled in HCL OneTest[™] Performance, and data is collected from the sources you added to the performance schedule in HCL
 OneTest[™] Performance (see Figure 2), the Resource Monitoring tab displays the list of these sources that are available in your HCL OneTest[™] Server project.

Figure 2:

VU Schedule Details

Category: Resource Monitoring from Service

Enable resource monitoring from service

Collect from the following sources

O Collect from sources matching at least one of the following labels

Title	Polling Time
✓ I OpenMetrics exporter	
> 🟮 OpenMetrics a	5 Seconds
✓ ⊨ Prometheus server	
Prometheus at	5 Seconds

To override the initial sources with the sources that you created in HCL OneTest[™] Server, select the labels that are in your HCL OneTest[™] Server project and that match the Server sources (step 6 in this procedure).

Ż

If you added sources to your performance schedule by using labels in HCL OneTest[™]
 Performance (see Figure 3), the **Resource Monitoring** tab displays the list of labels that are available in your HCL OneTest[™] Server project.

Figure 3:

VU Schedule Details

Category: Resource Monitoring from Service

Enable resource monitoring from service

Collect from the following sources

Collect from sources matching at least one of the following labels

OpenM	Add	i
Prom	Edit	
SUTv2	Euli	
	Remo	ove

To select resource monitoring labels from your schedule, follow step 6 in this procedure.

In the list of sources or labels that is displayed in the Resource Monitoring tab:

- Green icons identify either labels that match the sources or sources that are found in the current project.
- Red icons indicate that the sources are not running,
- Yellow icons identify either labels that do not match the sources, or sources that are not found in the current project.

Data is collected for the sources that match labels only.

6. Click the to select a label in the list.

Example: Select 'SUTv3'.

ENVIRONMENT	DATA SOURCES	VARIABLES	LOCATION	RESOURCE MON	ITORING
Asset settings: list o	of labels				
▲ L1_ITS: not match	ing				
▲ L2_Proj_ITS: not n	natching				
To collect data during	this execution, you can	select existing lab	els that match sour	ces:	
SUTv3 ×					+
Label selection sumn	nary:				
	tp-junit1.nonprod.hclpr ttp-junit1.nonprod.hclp	· · · · · · · · · · · · · · · · · · ·	Defined in team space		
Advanced	Reset			Cancel	Execute

You can see all the labels that you added to the resource monitoring sources in HCL OneTest[™] Server.

Note: You can select labels matching resource monitoring sources that are created in a team space in addition to the ones that are created in a project.

- 7. Select the labels that match the sources.
- 8. Click **Execute** to execute the performance schedule.
- 9. Click the **Result** view in the navigation bar of HCL OneTest[™] Server when the schedule is complete.
- 10. Expand the performance schedule result to see the resource monitoring label name in the **Details** card.

The **Details** card displays the resource monitoring labels that are used in the schedule to override the initial labels and collect resource monitoring sources (in the example, the 'SUTv3' label). For other details about the **Results** page, see the link at the end of this page.

SchedListOfRMSourcest proj_RM_1011/Schedules/	Enabled SchedListOfRMSourcesEnabled.tes dilip		Sep 8, 202 10:16 AM	20	00:04:25.153	Pass	-	0
DETAILS					Reports			
ld Branch	1751 Dilip_1011				Statistics Rep	ort		8
Result Finish on	SchedListOfRMSourcesEnabled Sep 8, 2020 10:20 AM				Test Log (Text	0		
Status	Complete							
Git repo	https://jilliningprodu	cts/PT_SVT	_TestAsset.git					
Git path	proj_RM_1011/Schedules/SchedListOfRMSou	cesEnabled.	testsuite					
Git commit	commit sch with RM sources CRC server committed 22 days ago (#refs/heads/Dilip_1011)	٥	d24e819	0				
Execution location Resource Monitoring labels (override)	Default Cluster							

In the **Report** card, you find the link to the Statistics Report that is generated. In the **Resource** tab of the Statistics Report, you can view the information related to the Server sources matching the labels set in the schedule.

11. Click the **Statistics Report** link in the **Reports** card to see the performance metrics of the monitoring sources matching the selected labels.

Pages 💽									_		1.11.1.1		
Overall		Se	rver sources	matchir	ng the labels	set through	erver exec	ution setting	s (*Source	defined in t	eam space)	
Summary	Label 🕚 *									_			
age Performance	SUTv3	[Pro	metheus at tp-j	unit1.nonp	prod.hclpnp.com	:48090, Open#	letrics at tp-ju	nit1.nonprod.h	clpnp.com:48	080 (*)]			
Response vs. Time Summary						1	esources						
Response vs. Time Detail	Node disk v	vritten bytes	(device=sda, in	stance=lo	rice=dm-0, insta calhost:48100} JVM memory co	Node disk w	ritten bytes (d	evice=sr0, inst	ance=localho	st:48100} Op			
Page Throughput								5.0					
erver Throughput			7	_					-013				
Server Health Summary													
erver Health Detail						\backslash							
Caching Details						$\langle \rangle$							
Resources													
Page Size						<u> </u>		_					minutes
Frors	1	1:06	1:12	1:18	1:24	1:30	1:36	1:42	1:48	1:54	ż	2:06	2:12
age Health			/			<u> </u>							

Example: You can see the statistics for the sources tagged with the 'SUTv3' label.

Note: In the Resources report, each resource name followed by an asterisk identifies a resource monitoring source that is defined in a team space.

Related information

Test results and reports on page 514

Collecting and viewing resource monitoring usage data

With HCL OneTest[™] Server, you can collect resource monitoring data in a timeframe and view the resource monitoring usage data in a graph while the test is running. You can also create queries to retrieve the resource monitoring usage data.

About this task

While monitoring a system, you can view the current data in a graph but you might also want to view persistent data that is collected during a test run in a timeframe. To view the persistent data, you can configure the test with additional parameters before the test execution. While the test is running, you can view the resource monitoring usage data in a graph. When the test is running or complete, you can create queries to retrieve the collected data results.

To collect and view resource monitoring data, perform these tasks:

- 1. Configure a test with two additional parameters in the advanced settings.
- 2. View the resource monitoring usage data in a graph.
- 3. Create queries to retrieve the resource monitoring usage data.

Related information

Configuring a test on page 587

Viewing resource monitoring usage data on page 588

Creating queries for resource monitoring usage data on page 590

Configuring a test

You must configure a test with two parameters to collect resource monitoring usage data in a timeframe when the test is running.

Before you begin

You must have completed the following tasks:

- Added and configured a source.
- Created resource monitoring labels for your source.

About this task

You can collect resource monitoring usage data during a test run for all types of monitoring sources, and all test types, except API stubs.

- 1. Click Execution, In the navigation pane.
- 2. Select the test that you want to run and click 🕑 in the **Actions** column to open the **Execute test asset** window.
- 3. Click Advanced settings.
- 4. Enter the following parameters and values in Additional Configuration Parameters:

Parameter name	Value
rm.log.labels	Enter a label name in the second edit field as the pa- rameter value.
	If you enter multiple labels, enter a comma to sepa- rate them in the list.

Parameter name	Value
	Example: For two labels with the following names: 'LabelA' and 'LabelB': rm.log.labels LabelA,LabelB
	If a label contains a comma in its name, you must add two commas in order to collect the resource monitoring usage data.
	Example: For a label named 'Label1A,Label1B', enter the following parameter and value:
	rm.log.labels Label1A,,Label1B
rm.log.period.seconds	Enter a sampling period in the second edit field as the parameter value. The minimum period is one second.

- 5. Click Add for each parameter.
- 6. Click Execute.

Results

The monitoring data is collected while your test is running. You can see the collected data in a graph of the resource monitoring page, even 3 minutes after the test is complete.

What to do next

You can view the resource usage data on the resource monitoring page. See Viewing resource monitoring usage data on page 588.

Viewing resource monitoring usage data

After you add and configure monitoring sources in HCL OneTest[™] Server, you can view the resource monitoring usage data in a graph for each monitored source and for each selected counter.

Before you begin

You must have completed the following tasks:

- Added and connected a monitoring source, and an agent when required, to your project to be able to view the list of available sources and agents, and the resource monitoring usage data in your project.
- Configured a test with advanced parameters to view persistent usage data in a graph.

About this task

After you add a monitoring source to HCL OneTest[™] Server, configure the source and select monitoring counters, you can view the current resource monitoring usage data for each selected counter in a graph. If you configure the test to collect data, you can also view the resource monitoring usage data that is collected for a defined timeframe. In this case, the data is still visible in the graph three minutes after the test run is complete. After this time, you can create queries to retrieve the data.



Note: For a Prometheus source, as data comes from the Prometheus database, it no longer shows up in the graph when the test run is complete. However, the data is collected and shows up in the queries if it matches a label.

1. Click a link either in the **Total Sources** cards or in the **All Types** cards from the resource monitoring page to access the resource monitoring usage data.

The tables display the total number of sources in your project and the number of sources by type. You can also view the number of available and unavailable sources, and the number of sources that contain warnings. If you have added '4' sources to your project, for example, click '4' in the table to access the page where you can see the resource usage data for each source.

If you have added agents to your project, you can also view the number of agents that are connected and disconnected to your project.

											Add a source
tal Sourc	er. 4							Resour	ce Monitoring /	Igents: 1	
	4			0		0			(1)		0
1	Available		Unav	ailable		Warning	2		Connected		Disconnected
Types											
OpenMet	trics exporter		1 Prometh	eus server		1 Docker N	teost		1 Windows	Performan	ce host
1	0	0	1	0	0	1	0	0	1	0	0

Result


The list of sources is displayed in a new page.

You can filter the list of sources by collector type or by status.

2. Expand a monitoring source under the Name column to see the current monitoring data usage in a graph.

3. Click the down arrow Y to select a counter in the list.

A graph is displayed for each counter.



What to do next

From the page where you can view the resource monitoring usage data, you can also manage your sources. See Managing sources on page 579.

Related information

Collecting and viewing resource monitoring usage data on page 586

Creating queries for resource monitoring usage data on page 590

Creating queries for resource monitoring usage data

After you execute a test to collect resource monitoring usage data, you can create queries to retrieve the data.

Before you begin

You must have added resource monitoring sources to a project.

About this task

You can no longer view the monitoring usage data in graphs 3 minutes after completion of the test. However, you can create queries to retrieve the list of activities and events in your tests. You can use the following procedure as an example to create your own queries.

- 1. Follow these steps to filter the list of activities that are collected for a duration of less than 300 seconds:
 - a. Click Activities.
 - b. Enter 'Type is RMsource and duration < 300' in the Query filters field.
 - c. Enter 'time ASC' in the Sort by field to sort data by ascending order.
 - d. Click Run Query.
 - e. Click Save as.
 - f. Enter a name to identify the new query and click Save.

The list of activities that are collected for a duration of less than 300 seconds is displayed in the query result table, and this list is sorted in an ascending order.

- 2. Follow these steps to filter the list of observations that are performed during a test execution and defined by the test result identifier:
 - a. Click Events.
 - b. Enter the following filters in the Query filters field:

```
type is observation and anyParentActivity matches ( anyChildActivity matches (requesterNature =
'test-result' and requesterId=1202 ))
```

c. Enter 'time ASC, parentActivity.description ASC, specifier ASC' in the Sort by field to sort data by ascending order.




Note: You can use the Ctrl-Space keyboard shortcut to enter the properties and operators.

- d. Click Run Query.
- e. Click Save as.
- f. Enter a name to identify the new query, and then click Save.

The new query results are displayed in the table of activities and events.

- 3. Follow these steps to manage your query:
 - Click the action menu that is next to the **Save** button and select **Reset** if you have just modified a query and you want to undo your modification.
 - Click the **action menu and select Delete** to delete the new query from the **Events and activities** queries list.
- 4. Follow any of these steps to configure the query result table:
 - Click the action menu in a column of the table to change the column display, and then perform any of the following actions:
 - Click Insert new column, enter a field name in Search new column and click Add.
 - Click Move to move a column in the table.
 - Click **Remove** to remove a column from the table.
 - Follow these steps to add a column at the end of the table:
 - a. Click Add column.



b. Enter a field name in Search new column.

c. Click Add.

5. Click **Save** to save the configuration of the results table.

Results

You have created two queries in your project to display:

- The list of activities that are collected for a duration of less than 300 seconds.
- The list of observations that are performed during a test execution and defined by the test result identifier.

Related information Configuring and running log queries on page 545

Configuration of a change management system

When you use any application to create and track defects (bugs), issues, or other work items, you can configure the application as a change management system on HCL OneTest[™] Server. You can then create defects (bugs), issues, or other work items without the need to open your application.

You use HCL OneTest[™] Server to run tests for the software that you develop and view their results. When you discover that you might want to raise defects (bugs), issues, or other types of work items for these tests, you are required to open the application that you use. You can only then, create defects (bugs), issues, or other work items in your application.

When you configure your application as a change management system on HCL OneTest[™] Server, you can create defects (bugs), issues, or other work items without the need to open your application.

You can find details in the following table about the usage of the applications that you can configure as a change management system on HCL OneTest[™] Server.



Note: You can configure only one application as the change management system on HCL OneTest[™] Server.

Issue track- ing application	Usage as a change management system	Go to
Atlassian Jira Software	You can create stories, defects, or tasks as is- sues in your project in Jira from HCL OneTest [™] Server and also launch your project in Jira from HCL OneTest [™] Server to track and manage these issues.	Configuration of Atlassian Jira as a change management system on page 593
Azure DevOps	You can create work items in your project in Azure DevOps from HCL OneTest [™] Server and also launch your project in Azure DevOps from HCL OneTest [™] Server to track and manage these work items.	Configuration of Azure DevOps as a change management system on page 603
HCL® Compass	You can use HCL® Compass as a change man- agement system in HCL OneTest™ Server. You	Configuration of HCL Compass as a change management system on page 611

Issue track- ing application	Usage as a change management system	Go to
	can also launch HCL® Compass from HCL	
	OneTest [™] Server to track and manage change	
	requests and other records.	

Configuration of Atlassian Jira as a change management system

You can use Atlassian Jira as a change management system in HCL OneTest[™] Server to create issues in the Jira project for the tests that ran in HCL OneTest[™] Server. Links to the Jira issues are displayed on the **Results** page in HCL OneTest[™] Server, and you can then view and track the Jira issues in Jira.

Prerequisites

Before you configure Jira as a change management system on HCL OneTest[™] Server, you must have completed the following tasks:

- Installed Jira Software. See Supported installations on page 593.
- Ensured that you obtained the access and authentication details to Jira from the Jira administrator.
- Ensured that you are assigned a role as a *Project Owner* or *Tester* in the project. See Managing access to server projects on page 734.
- Created a project in your team space in HCL OneTest[™] Server. See Adding a project on page 727.

Supported installations

The following types of Jira Software installations are supported that can be configured as a change management system on HCL OneTest[™] Server:

- On-premise Jira Software installations.
- On-cloud Jira Software installations.

Task flow

You can follow the tasks that are listed in the following table when you want to use Jira as a change management system on HCL OneTest[™] Server. The table also provides you the links to the information about the tasks.

Task	Go to	
Add a Jira Software server URL on the Integration page of HCL OneTest [™] Server, and then generate the API keys that authenticate HCL OneTest [™] Server as an application in Jira.	Adding a Jira Software server URL on page 594	
Set up an application link for HCL OneTest [™] Server in the Jira server.	Setting up an application link in the Jira server on page 595	

Task	Go to
Configure the Jira server as a change management sys- tem on HCL OneTest [™] Server.	Configuring the Jira server as a change management system on page 596
Create defects or issues for tests that ran on HCL OneTest [™] Server.	Creating Jira issues for tests that ran on page 598

You can manage the Jira server settings that you configured in HCL OneTest[™] Server. You can edit the saved configuration or you can delete the configuration. For more information, see Managing the Jira server configuration on page 601.

Adding a Jira Software server URL

You must first add the URL of the server on which you have installed Jira Software on the **Integration** page of HCL OneTest[™] Server. You must copy the API keys that are generated by HCL OneTest[™] Server to be used to authenticate HCL OneTest[™] Server as the application to connect in Jira.

Before you begin

You must have completed the following tasks:

- Read about the prerequisite tasks in Prerequisites on page 593.
- Verified that you can access the Jira server.
- Ensured that you are assigned a role of a *Project Owner* in the project. See Managing access to server projects on page 734.
- Created a project in your team space in HCL OneTest[™] Server. See Adding a project on page 727.
- 1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

2. Click Active projects > My projects > project_name to open the project that contains the test assets.

The **Overview** page of the project is displayed.

- Click Manage > Integration in the navigation pane.
 The Integration page is displayed.
- 4. Click the CHANGE MANAGEMENT SYSTEM tab.
- 5. Click Add New, and then select the Jira Software option from the list.

The Add Jira server dialog is displayed.

6. Enter the URL of the Jira server in the **URL of the Jira server** field, and then click **Add**.

HCL OneTest[™] Server verifies the connection with the Jira server and generates the API keys, which are displayed on the **Copy the generated keys** dialog.

- 7. Click the **Copy** icon ⁽¹⁾ in the **Public Key** field to copy the key, and then paste the copied key into a text file.
- 8. Click the **Copy** icon 🕒 in the **Consumer Key** field to copy the key, and then paste the copied key into a text file.

Results

You added the URL of the Jira server and generated the public and consumer keys that you must use to configure HCL OneTest[™] Server as an application in the Jira server. You can view that the URL of the Jira server is displayed on the **CHANGE MANAGEMENT SYSTEM** tab and the status is displayed as *Not configured*.

What to do next

You must share the public and consumer keys with the administrator of the Jira server to set up an application link in Jira to HCL OneTest[™] Server. However, if you are an administrator of the Jira server, you can set up an application link in the Jira server. See Setting up an application link in the Jira server on page 595.

Setting up an application link in the Jira server

You must set up an application link in the Jira server to establish a connection between the Jira server and HCL OneTest[™] Server.

Before you begin

You must have completed the following tasks:

- Ensured that you are assigned the privileges of an administrator in Jira.
- Generated a public key and a consumer key for the project in HCL OneTest[™] Server and saved the keys in a text file. See Adding a Jira Software server URL on page 594.
- Copied the URL of HCL OneTest[™] Server.
- 1. Log in to the Jira server.
- 2. Select any of the following options based on the method that you used to install the Jira server:
 - If you installed the Jira server on cloud, go to Step 3 on page 595.
 - If you installed the on-premise Jira server 8.21.x or earlier, go to Step 4 on page 596.
 - If you installed the on-premise Jira server 8.22.x or later, go to Step 5 on page 596.
- 3. Perform the following steps to create the application link in the Jira server that is installed on cloud:
 - a. Click Settings > Products.
 - b. Click Application links in the left navigation.
 - c. Click Create link.
 - d. Select Direct application link.
 - e. Enter the URL of HCL OneTest[™] Server in the Application URL field, and then click Continue.
 - f. Verify the URL on the Configure Application URL dialog, and then click Continue.
 - g. Go to Step 6 on page 596.

- 4. Perform the following steps to create the application link in the on-premise Jira server 8.21.x or earlier:
 - a. Click Settings > Applications
 - b. Click Application links in the left navigation.
 - c. Verify the URL on the Configure Application URL dialog, and then click Continue.
 - d. Go to Step 6 on page 596.
- 5. Perform the following steps to create the application link in the on-premise Jira server 8.22.x or later:
 - a. Click Settings > Applications
 - b. Click Application links in the left navigation.
 - c. Click Create link, and then select Atlassian product as application type.
 - d. Verify the URL on the Configure Application URL dialog, and then click Continue.
 - e. Go to Step 6 on page 596.
- 6. Perform the following steps on the **Review link** dialog to provide the information about HCL OneTest[™] Server:
 - a. Enter a name for HCL OneTest[™] Server in the **Application Name** field.

You must provide a unique name to HCL OneTest[™] Server. For example, onetest.

- b. Select Generic Application as Application Type from the list.
- c. Select the **Create incoming link** checkbox to set up a one-way incoming link from HCL OneTest[™] Server to the Jira server.
- d. Click Continue.
- e. Enter the consumer key that was generated on HCL OneTest[™] Server and copied into the text file, in the **Consumer Key** field.
- f. Enter a name in the **Consumer Name** field. For example, HCL.
- g. Enter the public key from the text file in the Public Key field.

7. Click Continue.

The link to the application you configured in Jira is displayed on the Application links page.

Results

You have set up the application link to HCL OneTest[™] Server in the Jira server.

What to do next

You can configure the Jira server in your project on HCL OneTest[™] Server. See Configuring the Jira server as a change management system on page 596.

Configuring the Jira server as a change management system

You must configure the Jira server as a change management system in your project in HCL OneTest[™] Server before you can create issues in the Jira project for the tests that ran.

Before you begin

You must have completed the following tasks:

- Ensured that you are assigned a role as a *Project Owner* or *Tester* in the project. See Managing access to server projects on page 734.
- Generated a public key and a consumer key for the project in HCL OneTest[™] Server and saved the keys in a text file. See Adding a Jira Software server URL on page 594.
- Shared the public key and consumer key with the administrator of the Jira server to set up an application link in Jira, if you are not an administrator of the Jira server.
- Created an application link in Jira, if you possess the privileges as an administrator of the Jira server. See Setting up an application link in the Jira server on page 595.
- 1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

2. Click Active projects > My projects > project_name to open the project that contains the test assets.

The **Overview** page of the project is displayed.

- Click Manage > Integration in the navigation pane.
 The Integration page is displayed.
- 4. Click the CHANGE MANAGEMENT SYSTEM tab.
- 5. Click the **Open action menu** icon , and then click **Configure**.

The Configure Jira server to authorize the application dialog is displayed.

- 6. Perform the following steps:
 - a. Click the URL of the Jira server in the dialog.

The Welcome to Jira page is displayed in a browser.

b. Read the message that is displayed, and then click **Allow** to authorize the Jira server account.

After the authorization is successful, the Access Approved page is displayed with a verification code.

- c. Copy the verification code, and then enter the code in the field on the **Configure Jira server to authorize the application** dialog that is displayed in the **CHANGE MANAGEMENT SYSTEM** tab.
- d. Click Save.

- The Select project in Jira dialog is displayed.
- e. Select the project in Jira from the list under which you want to create defects.

7. Click Update.

Results

You configured Jira as a change management system in HCL OneTest[™] Server.

What to do next

You can perform the following tasks:

- View the following information on the CHANGE MANAGEMENT SYSTEM tab about the Jira configuration:
 - The URL of the Jira server
 - The project that you selected
 - The status of the configuration
- Create defects for the test results that are available in your project in HCL OneTest[™] Server. See Creating Jira issues for tests that ran on page 598.

Creating Jira issues for tests that ran

You can create Jira issues for the tests that ran in . The issues are created in the project in Jira that you configured in .

Before you begin

- •
- Configured the Jira server as a change management system for your project in . See Configuring the Jira server as a change management system on page 596.
- •
- •

About this task

When you want to create a Jira issue in , the issue types that display in the **Create an issue in Jira** dialog depend on the configuration done by the administrator of the Jira server.

The default fields that display on the Create an issue in Jira dialog are as follows:

- Issue Type
- Summary
- Description

If you want to view any additional fields in the **Create an issue in Jira** dialog from , then you must inform your Jira server administrator to configure those additional fields as the required fields in the project on the Jira server. You can then use those fields in the **Create an issue in Jira** dialog when you create a defect from .

You can refer to the Related information section to know more about Jira field configuration.

- 1.
- 2.
- 3.
- 4.

5. Select the step that depends on the role assigned to you in the project on :

- If you are a member with role assigned as *Owner*, go to Step 6 on page 599.
- If you are a member with role assigned as *Tester* and not completed the one-time authorization process, go to Step 7 on page 599.
- If you are a member with role assigned as *Tester* and completed the one-time authorization process, go to Step 8 on page 600.
- 6. Perform the following steps as the project Owner:
 - a. Click the **Jira: Create a Jira issue** icon 📀 that is under the **Actions** column in the row of the test.

Alternatively, you can click the test under the **Test** column to view the results panel, and then click the **Jira: Create a Jira issue** icon **•** that is displayed in the panel.

b. Select the issue type that you want to create in the **Create an issue in Jira** dialog, and then click **Create**.

The issue is created in the project on the Jira server and the link to the issue is displayed in the **Results** panel of the test on .



Note: You can create multiple issues for the same test result, if you want.

You created an issue in Jira. You can go to Results on page 600.

7. Perform the following steps as a member assigned the *Tester* role and if you have not yet completed the onetime authorization process:



Note: You must complete the one-time authorization process if you are not a project owner.

a.

- b. Click the URL of the Jira server in the Configure Jira server to authorize the application dialog that is displayed.
- c. Log in to the Jira server account with your valid credentials.

Note: The **Login** page is displayed only if you are not already logged in to the Jira server.

d. Read the message that is displayed, and then click Allow to authorize the Jira server account.

After the authorization is successful, the Access Approved page is displayed with a verification code.

- e. Copy the verification code, and then enter the verification code in the field on the **Configure Jira server** to authorize the application dialog of .
- f. Click Save.
- g.
- 8. Perform the following steps as a member assigned the *Tester* role and completed the one-time authorization process:
 - a.
 - b.

Results

You have created issues in the Jira project for the test results from .

The Jira issues are created in the Jira project and the links to the issues are displayed in the **Details** panel of the test result on the **Results** page.

What to do next

You can click the test result on the **Results** page to view the Jira issue key link. You can then click the Jira issue key link to open the issue and view the details of the issue in Jira.

Related information Specifying Jira fields

Viewing details of the Jira issues

After you create Jira issues in HCL OneTest[™] Server, you can view and track the details of the Jira issues in Jira.

Before you begin

You must have completed the following tasks:

- Completed a test run and the test results are available on the Results page.
- Created Jira issues against the test results. See Creating Jira issues for tests that ran on page 598.

1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

2. Click Active projects > My projects > project_name to open the project that contains the test assets.

The **Overview** page of the project is displayed.

3. Open the **Results** page by clicking **Analyze > Results**.

The test assets that ran are displayed in the following tabs on the **Results** page:

Tab	Description	
SUITES	Lists all suites, compound tests, JMeter tests, JUnit tests, Postman tests, Rate Sched- ules, or VU Schedules that are in the selected branch of the repository.	
TESTS	Lists all API tests, functional tests, or performance tests that are in the selected branch of the repository.	
ADVANCED	Lists all assets that are displayed when custom filters are applied for assets in the se- lected branch of the repository.	

You can click the relevant Tab to view the tests that you ran.

- 4. Click the test that is listed under the **Test** column.
- 5. Click the Report tab in the Results panel, if it is not already displayed.
- 6. Click the Jira issue link under Defect tracking.

The Jira log-in page is displayed, if you are not already logged into Jira.

- 7. Enter your username and password.
- 8. Click Login.

The issue details are displayed in Jira.

Note: The Description field of the Jira issue in Azure DevOps provides additional details of the test that ran in HCL OneTest[™] Server such as the name of the test, the person who ran the test, the verdict of the test result, the date and time of the test run, the links to the test report that is generated in HCL OneTest[™] Server, and the link to the query that is created.

Results

You have viewed the details in Jira of the Jira issue that you created in HCL OneTest™ Server.

Managing the Jira server configuration

You can manage the Jira server configuration that you set in HCL OneTest[™] Server when you want to modify the project configured in Jira or when you want to delete the existing Jira configuration.

Before you begin

You must have completed the following tasks:

- Ensured that you are assigned a role of a *Project Owner* in the project. See Managing access to server projects on page 734.
- Ensured that you obtained the access and authentication details to Jira from the Jira administrator.
- 1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

2. Click Active projects > My projects > project_name to open the project that contains the test assets.

The Overview page of the project is displayed.

- Click Manage > Integration in the navigation pane.
 The Integration page is displayed.
- 4. Click the CHANGE MANAGEMENT SYSTEM tab.
- 5. Click the **Open action menu** icon [‡] for the Jira server that you want to manage.

The Configure and Delete options are displayed in the list.

- 6. Perform any of the following actions when you want to modify or delete the Jira server configuration:
 - To modify the project in Jira that was set previously in the Jira server configuration. Go to Step 7 on page 602.
 - To delete the Jira server configuration. Go to Step 8 on page 602.
- 7. Perform the following steps to modify the project in Jira:
 - a. Select Configure as the option from the list.

The Select project in Jira dialog is displayed.

- b. Select the project that you want from the list displayed in the Project field.
- c. Click **Update** to save the updated project in the Jira server configuration.
- 8. Perform the following steps to delete the existing Jira server configuration:
 - a. Select **Delete** as the option from the list.
 The **Delete Jira configuration** dialog is displayed.

b. Click Delete.

The Jira server configuration is deleted and a confirmation message is displayed.



Note: The links to the issues that you created for the tests that ran are not deleted from the results panel in HCL OneTest[™] Server even after you delete the Jira server configuration.

Results

You achieved the following results:

- Updated the project in Jira and saved the Jira server configuration.
- Deleted the Jira server configuration.

Configuration of Azure DevOps as a change management system

You can use Azure DevOps as a change management system in HCL OneTest[™] Server to create work items in the Azure DevOps project for the tests that ran in HCL OneTest[™] Server. Links to the Azure DevOps work items are displayed on the **Results** page in HCL OneTest[™] Server, and you can then view and track the work items in the Azure DevOps server.

Prerequisites

Before you configure Azure DevOps as a change management system in HCL OneTest[™] Server, you must have completed the following tasks:

- Ensured that you obtained the access and authentication details to Azure DevOps from the Azure DevOps administrator.
- Ensured that you are assigned a role of a *Project Owner* in the project. See Managing access to server projects on page 734.
- Created a project in your team space in HCL OneTest[™] Server. See Adding a project on page 727.

Supported installations

The following types of Azure DevOps installations are supported that can be configured as a change management system on HCL OneTest[™] Server:

- On-premise Azure DevOps installations.
- On-cloud Azure DevOps installations.

Task flow

You can follow the tasks that are listed in the following table when you want to use Azure DevOps as a change management system in HCL OneTest[™] Server. The table also provides you the links to the information about the tasks.

Task	Go to
Configure Azure DevOps as a change management sys- tem.	Configuring Azure DevOps as a change management system on page 604
Create work items for the test asset.	Creating Azure DevOps work items on page 605
Track and view the details of the created work items.	Viewing work item tracking details on page 609

You can edit the saved configuration, or you can delete the configuration and create a new configuration. For more information, see Editing or deleting the configuration on page 610.

Configuring Azure DevOps as a change management system

You must configure Azure DevOps as a change management system in your project in HCL OneTest[™] Server before you can create work items in the Azure DevOps project for the tests that ran.

Before you begin

You must have completed the following tasks:

- Ensured that you are assigned a role as a *Project Owner* or *Tester* in the project. See Managing access to server projects on page 734.
- Ensured that you obtained the access and authentication details to Azure DevOps from the Azure DevOps administrator.
- 1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

2. Click Active projects > My projects > project_name to open the project that contains the test assets.

The **Overview** page of the project is displayed.

3. Click Manage > Integration in the navigation pane.

The Integration page is displayed.

- 4. Click the CHANGE MANAGEMENT SYSTEM tab.
- 5. Click Add New, and then select the Azure DevOps option from the drop-down list.

The Configure Azure DevOps dialog is displayed.

- 6. You can perform the following actions:
 - a. Enter the URL of Azure DevOps.



Note: You must enter the URL of the Azure DevOps in one of the following formats:

- https://dev.azure.com/{Organization}
- https://{Organization}.visualstudio.com

https://{Hostname}:{Port}/{Collection}

The URL contains information such as the server name (hostname, port, or domain name) and organization name.

- b. Click Next, and then paste the copied personal access token.
 - Note: If you do not have your personal access token, you can click Generate to generate your personal access token to authorize full access or access to the work items.
- c. Click Next, and then select an Azure DevOps project from the drop-down list.
- d. Click Add.

The configuration is added and saved to the CHANGE MANAGEMENT SYSTEM tab.

Results

You configured Azure DevOps as a change management system in HCL OneTest[™] Server.

What to do next

You can create work items for the test results that are available in your project in HCL OneTest[™] Server. See Creating Azure DevOps work items on page 605.

Creating Azure DevOps work items

You can create Azure DevOps work items for the tests that ran in HCL OneTest[™] Server. The issues are created in the project in Azure DevOps that you configured in HCL OneTest[™] Server.

Before you begin

You must have completed the following tasks:

- Ensured that you are assigned a role as a *Project Owner* or *Tester* in the project. See Managing access to server projects on page 734.
- Configured Azure DevOps as a change management system in HCL OneTest[™] Server for your project. See Configuring Azure DevOps as a change management system on page 604.
- Extended the CA list. See Extending the trusted CA list on Linux on page 99 or Extending the trusted CA list on Windows systems on page 100.
- Configured a test run. See Test run configurations on page 327.
- Viewed the results of the completed test runs on the **Results** page. See Test results on page 513.

About this task

When you want to create a Azure DevOps work item on HCL OneTest[™] Server, the fields that display in the **Create a work item** dialog depends on the configuration done by the Azure DevOps administrator.

1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

2. Click Active projects > My projects > project_name to open the project that contains the test assets.

The **Overview** page of the project is displayed.

3. Open the **Results** page by clicking **Analyze > Results**.

The test assets that ran are displayed in the following tabs on the Results page:

Tab	Description	
SUITES	Lists all suites, compound tests, JMeter tests, JUnit tests, Postman tests, Rate Sched- ules, or VU Schedules that are in the selected branch of the repository.	
TESTS	Lists all API tests, functional tests, or performance tests that are in the selected branch of the repository.	
ADVANCED	Lists all assets that are displayed when custom filters are applied for assets in the se- lected branch of the repository.	

You can click the relevant Tab to view the tests that you ran.

- 4. Identify the test asset by performing any of the following actions:
 - Scroll through the list.



Tip: You can hover over the icon in the Type column to know the type of the test asset.

Note: You can also identify the type of the asset from the icon that represents the test type as shown in the following table:

lcon	Represents	Listed in the SUITES tab	Listed in the TESTS tab	Listed in the AD- VANCED tab
-63-	API test		0	0
•	Functional test		0	0
٥	Performance test		0	0
۲	AFT Suite	0		0

Icon	Represents	Listed in the SUITES tab	Listed in the TESTS tab	Listed in the AD- VANCED tab
•	API Suite	0		0
0 00 (J) 00	Compound Test	0		0
0	HCL AppScan CodeSweep	0		0
/JMeter"	JMeter Test	0		0
Ju	JUnit Test	0		0
0	Postman test	0		0
\$ 1	Rate Schedule	0		0
9	VU Schedule	0		0

- Search for the test by entering any text contained in the test asset name in the Search field.
- Select a time within which the test was run. For example, you can select the option *Last 24 hours* to view the tests that ran in the previous 24 hours.
- Select a date range within which the test was run. You can click the calendar icon to select the date in the first image as the start date, and then select the end date in the second image.
- \circ Click the Filter icon $\mathcal V$ in the SUITES or TESTS tab to filter the displayed tests based on the test type.

For example, select **API Suite** in the **SUITES** tab to display all API Suites or select **Functional Test** in the **TESTS** tab to display all functional tests.

- Click the **Filter** icon **W** in the **ADVANCED** tab, and then create a filter query by using the **New filter** option by performing the following steps:
 - a. Click New filter.
 - b. Enter a name for the filter.
 - c. Select an operator, and add a rule, or a group of rules.
 - d. Add or enter the relevant parameters and either select or enter the condition and the criteria for the condition.

You can select a parameter from the following list:

- ID
- Type
- Test
- Version
- Result
- Started on
- Finish on
- Duration
- Status
- Verdict
- Labels
- Locked
- Repository
- Branch
- Text
- e. Save the filter query to save and apply the filter query to filter the tests based on the query.

The tests that match the filter criteria are displayed.

 Retrieve and apply a saved filter query, if you have saved filter queries previously by performing the following steps:

Note: The filter query applied previously is selected and the tests based on that filter query are displayed. To apply a different filter query, you must have created and saved the filter query.

a. Click the **Filter** icon \mathbf{Y} in the **ADVANCED** tab.

The filter queries that you created and saved are displayed.

b. Click the filter that you want to apply.

The tests that match the filter criteria are displayed.

You have identified the test that you want to use.

- 5. Perform the following actions on the test that was run to create a work item:
 - a. Click the **Azure: Create work item** icon **C** that is under the **Actions** column in the row of the test.

Alternatively, you can click the test under the Test column to view the results panel, and then click the

Azure: Create work item icon 💙 that is displayed in the panel.

The Create a work item dialog is displayed.

b. Perform the actions indicated in the following table for each of the fields:

Field	Description	Action
Project	The name of the Azure DevOps project.	Select the Azure DevOps project from the drop-down list.
Work item type	The type of work item.	Select the work item you want to as- sign for the test asset.
Title	A title that identifies the work item.	Specify a title for the work item.
Description	A detailed description of the work item.	Enter a description of the work item.

Note: The other fields selected as **Required** fields on the **Azure DevOps** project are displayed in the **Create a work item** dialog.

c. Enter the information for all the required fields, and then click Create.



Note: You can create multiple work items for the same test result, if required.

Results

You created work items in the Azure DevOps project for the test results from HCL OneTest[™] Server.

The work items are created in the Azure DevOps project and the links to the work items are displayed in the **Details** panel of the test result on the **Results** page.

What to do next

You can click the test result on the **Results** page to view the Azure DevOps work item links. You can then click the work item link to open the work item and view the details of the work item in Azure DevOps.

Viewing work item tracking details

After you create a work item in HCL OneTest[™] Server, you can view and track the details of the work item in **Azure DevOps.**

Before you begin

You must have completed the following tasks:

- Completed a test run and the test results are available on the Results page.
- Created a work item against the test results.
- 1. Open your project.
- 2. Go to Analyze, and then click Results.

- The **Results** page is displayed.
- 3. Click the test asset.
 - The View details report pane is displayed.
- 4. Click the Azure DevOps work item ID to view the work item in Azure DevOps.

Results

You can view and track the work item in Azure DevOps.

Editing or deleting the configuration

You can edit or modify the Azure DevOps configuration that you added and saved to the Change management system tab. If you do not want to use the existing configuration and want to set up a new Change management system configuration, then you can delete the configuration.

Before you begin

You must have completed the following task:

- Been assigned a project Owner role.
- 1. Open the project that you created on HCL OneTest[™] Server.
- 2. Go to **Manage**, and then click **Integration** in the navigation pane. The **Integration** page is displayed.
- 3. Click the CHANGE MANAGEMENT SYSTEM tab.
- 4. Click **Open action menu** icon **•**.

The Edit and Delete options are displayed in the drop-down list.

- 5. Perform any of the following actions:
 - \circ To edit the Azure DevOps configuration. Go to Step 6 on page 610.
 - \circ To delete the Azure DevOps configuration. Go to Step 7 on page 611.
- 6. Follow the step to edit the Azure DevOps configuration:
 - a. Select Edit.

The Configure Azure DevOps dialog is displayed.

- b. Edit the URL by performing the following steps:
 - i. Enter the URL of **Azure DevOps**.
 - ii. Click Next.
 - iii. Paste the copied personal access token or click **Generate** to generate your personal access token.
 - iv. Click Add.

The URL is updated and saved.

c. Edit the project by performing the following steps:

- i. Select an Azure DevOps project from the drop-down list.
- ii. Click Add.

The project is updated and saved.

- 7. Follow these steps to delete the Azure DevOps configuration:
 - a. Select **Delete**.

A confirmation dialog is displayed.

b. Select **Delete**. The Azure DevOps configuration is deleted.

Results

You achieved the following results:

- Edited the Azure DevOps configuration and saved the configuration.
- Deleted the Azure DevOps configuration.

Configuration of HCL® Compass as a change management system

You can use HCL® Compass as a change management system to create HCL® Compass work items after you run tests on HCL OneTest[™] Server. You can then view and track the HCL® Compass work items in HCL® Compass.

Prerequisites

Before you configure HCL® Compass on HCL OneTest[™] Server, you must have completed the following tasks:

- Ensured that you obtained the access and authentication details to HCL® Compass from the HCL® Compass administrator.
- Ensured that you are assigned a role of a *Project Owner* in the project. See Managing access to server projects on page 734.
- Created a project in your team space in HCL OneTest[™] Server. See Adding a project on page 727.

Task flow

You can follow the tasks that are listed in the following table when you want to use HCL® Compass as a change management system on HCL OneTest[™] Server. The table also provides links to the information about the tasks.

	Task	Go to
1	Configure HCL® Compass as a change manage- ment system.	Configuring HCL Compass on page 612
2	Create HCL® Compass work items in HCL® Compass for the tests that ran on HCL	Creating HCL Compass work items on page 613
	OneTest [™] Server.	

	Task	Go to	
3	View and track the details of the created work	Viewing details of the HCL Compass work items	
	items.	on page 618	

You can manage the HCL® Compass settings that you configured in HCL OneTest[™] Server. You can edit the saved configuration or you can delete the configuration. For more information, see Managing the HCL Compass configuration on page 619.

Configuring HCL® Compass

You must configure HCL® Compass as a change management system in your project to create the HCL® Compass work items from HCL OneTest[™] Server.

Before you begin

You must have completed the following tasks:

- Read about the prerequisite tasks in Prerequisites on page 611.
- Ensured that you are assigned a role of a *Project Owner* in the project. See Managing access to server projects on page 734.
- Ensured that you obtained the access and authentication details to HCL® Compass from the HCL® Compass administrator.
- Created a project in your team space in HCL OneTest[™] Server. See Adding a project on page 727.
- 1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

2. Click Active projects > My projects > project_name to open the project that contains the test assets.

The Overview page of the project is displayed.

- Click Manage > Integration in the navigation pane.
 The Integration page is displayed.
- 4. Click the CHANGE MANAGEMENT SYSTEM tab.
- 5. Click Add New, and then select the Compass option from the list.

The Configure Compass application dialog is displayed.

- 6. Configure the HCL® Compass application by performing the following steps:
 - a. Enter the URL of the HCL® Compass server.



Note: You can enter the URL of HCL® Compass in any of the following formats:

- https://IP_address:port/
- https://hostname/

Where Is		ls
_	IP_address	The IP address of the server on which HCL® Compass is installed.
port The port the		The port that is used to communicate with HCL® Compass.
	hostname	The hostname of the computer on which HCL® Compass is in- stalled.

b. Click Next, and then select the application from the Application list.

c. Click Add.

The configuration is added and saved to the **CHANGE MANAGEMENT SYSTEM** tab. You can view the information in the **Configuration status** column to verify if the connection is established.

Results

You have configured HCL® Compass as a change management system in your project on HCL OneTest[™] Server.

What to do next

You can perform any of the following tasks:

- Create HCL® Compass work items for the tests that you ran on HCL OneTest[™] Server. See Creating HCL Compass work items on page 613.
- Modify the configuration that you set for HCL® Compass on HCL OneTest[™] Server. See Managing the HCL Compass configuration on page 619.

Creating HCL® Compass work items

You can create HCL® Compass work items for the tests that ran on HCL OneTest[™] Server. For example, you might want to create a work item in HCL® Compass when the test results differ from the expected results.

Before you begin

You must have completed the following tasks:

- Ensured that you are assigned a role as a *Project Owner* or *Tester* in the project. See Managing access to server projects on page 734.
- Configured HCL® Compass as a change management system in HCL OneTest[™] Server. See Configuring HCL Compass on page 612.
- Configured applications in HCL® Compass.
- Configured a test run. See Test run configurations on page 327.
- Viewed the results of the completed test runs on the Results page. See Test results on page 513.

1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

2. Click Active projects > My projects > project_name to open the project that contains the test assets.

The **Overview** page of the project is displayed.

3. Open the **Results** page by clicking **Analyze > Results**.

The test assets that ran are displayed in the following tabs on the Results page:

Tab	Description
SUITES	Lists all suites, compound tests, JMeter tests, JUnit tests, Postman tests, Rate Sched- ules, or VU Schedules that are in the selected branch of the repository.
TESTS	Lists all API tests, functional tests, or performance tests that are in the selected branch of the repository.
ADVANCED	Lists all assets that are displayed when custom filters are applied for assets in the se- lected branch of the repository.

You can click the relevant Tab to view the tests that you ran.

- 4. Identify the test asset by performing any of the following actions:
 - Scroll through the list.



Tip: You can hover over the icon in the Type column to know the type of the test asset.

Note: You can also identify the type of the asset from the icon that represents the test type as shown in the following table:

lcon	Represents	Listed in the SUITES tab	Listed in the TESTS tab	Listed in the AD- VANCED tab
-63-	API test		0	0
•	Functional test		0	0
٥	Performance test		0	0
	AFT Suite	0		0

Icon	Represents	Listed in the SUITES tab	Listed in the TESTS tab	Listed in the AD- VANCED tab
•	API Suite	0		0
0 00 (1)	Compound Test	0		0
0	HCL AppScan CodeSweep	0		0
/JMeter"	JMeter Test	0		0
Ju	JUnit Test	0		0
0	Postman test	0		0
\$ 1	Rate Schedule	0		0
9	VU Schedule	0		0

- Search for the test by entering any text contained in the test asset name in the Search field.
- Select a time within which the test was run. For example, you can select the option *Last 24 hours* to view the tests that ran in the previous 24 hours.
- Select a date range within which the test was run. You can click the calendar icon to select the date in the first image as the start date, and then select the end date in the second image.
- \circ Click the Filter icon $\mathcal V$ in the SUITES or TESTS tab to filter the displayed tests based on the test type.

For example, select **API Suite** in the **SUITES** tab to display all API Suites or select **Functional Test** in the **TESTS** tab to display all functional tests.

- Click the **Filter** icon **W** in the **ADVANCED** tab, and then create a filter query by using the **New filter** option by performing the following steps:
 - a. Click New filter.
 - b. Enter a name for the filter.
 - c. Select an operator, and add a rule, or a group of rules.
 - d. Add or enter the relevant parameters and either select or enter the condition and the criteria for the condition.

You can select a parameter from the following list:

- ID
- Type
- Test
- Version
- Result
- Started on
- Finish on
- Duration
- Status
- Verdict
- Labels
- Locked
- Repository
- Branch
- Text
- e. Save the filter query to save and apply the filter query to filter the tests based on the query.

The tests that match the filter criteria are displayed.

 Retrieve and apply a saved filter query, if you have saved filter queries previously by performing the following steps:

Note: The filter query applied previously is selected and the tests based on that filter query are displayed. To apply a different filter query, you must have created and saved the filter query.

a. Click the **Filter** icon \mathbf{M} in the **ADVANCED** tab.

The filter queries that you created and saved are displayed.

b. Click the filter that you want to apply.

The tests that match the filter criteria are displayed.

You have identified the test that you want to use.

- 5. Perform the following actions on the identified test to create an HCL® Compass work item in HCL® Compass:
 - a. Click the **Compass: Create a work item** icon ^S that is under the **Actions** column in the row of the test. Alternatively, you can click the test under the **Test** column to view the results panel, and then click the

Compass: Create a work item icon 오 that is displayed in the panel.

The Create a work item in Compass dialog is displayed.

b. Select the application from the list in the Application field.

I Remember: The application that you select must be the application for which you ran the test.

c. Enter the username in the Username field.



Note: The username is authorized to access the HCL® Compass server.

- d. Enter the password in the Password field to authenticate the username.
 - Note: After the credentials that you provided in the Username and Password fields are authorized by the HCL® Compass server, you need not enter these values for subsequent connections to create a work item.
- e. Click Next.

The dialog displays the URL of the HCL® Compass server and the Application that you selected.

- f. Select the work item type as WorkItem.
- g. Click Next.
- h. Select the project from the list in the Project field.
- i. Select the type of the work item from the list in the Type field.
- j. Enter text that is to be used as the title of the work item in the HCL® Compass work item.

You can view the details of the test run in the **Description** field, which is appended to the work item that is created for the test run in HCL® Compass.

A work item is created in HCL® Compass and a link to the work item is created in the **Report** panel of the **Results** page.

Notes:

- You cannot delete the work item that is created in HCL® Compass from HCL OneTest[™] Server.
- $\,\circ\,$ You can create multiple work items for the same test result, if required.

Results

You have created a work item in HCL® Compass from the **Results** page for the test that ran on HCL OneTest[™] Server.

What to do next

You can perform any of the following tasks:

- View details of the HCL® Compass work items that you created in HCL® Compass for the test. See Viewing details of the HCL Compass work items on page 618.
- Modify the configuration that you set for HCL® Compass on HCL OneTest[™] Server. See Managing the HCL Compass configuration on page 619.

Viewing details of the HCL® Compass work items

After you create a work item in HCL® Compass from HCL OneTest[™] Server, you can view and track the details of the work item in HCL® Compass.

Before you begin

You must have completed the following tasks:

- Completed a test run and the test results are available on the Results page.
- Created a work item against the test results. See Creating HCL Compass work items on page 613.
- 1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

2. Click Active projects > My projects > project_name to open the project that contains the test assets.

The **Overview** page of the project is displayed.

3. Open the **Results** page by clicking **Analyze > Results**.

The test assets that ran are displayed in the following tabs on the Results page:

Tab	Description	
SUITES	Lists all suites, compound tests, JMeter tests, JUnit tests, Postman tests, Rate Sched- ules, or VU Schedules that are in the selected branch of the repository.	
TESTS	Lists all API tests, functional tests, or performance tests that are in the selected branch of the repository.	
ADVANCED	Lists all assets that are displayed when custom filters are applied for assets in the se- lected branch of the repository.	

You can click the relevant **Tab** to view the tests that you ran.

4. Click the test that is listed under the Test column.

The **Results** panel for the test is displayed.

- 5. Click the Report tab in the Results panel, if it is not already displayed.
- 6. Click the HCL® Compass work item name under Defect tracking.

The HCL® Compass log-in page is displayed.

7. Enter your username and password.

8. Click Login.

The work item details are displayed in HCL® Compass.

Results

You have viewed the details in HCL® Compass of the work item that you created in HCL OneTest™ Server.

Managing the HCL® Compass configuration

You can manage the HCL® Compass configuration that you set in HCL OneTest[™] Server when you want to edit or modify the configuration or when you want to delete the existing configuration.

Before you begin

You must have completed the following tasks:

- Ensured that you are assigned a role of a *Project Owner* in the project. See Managing access to server projects on page 734.
- Ensured that you obtained the access and authentication details to HCL® Compass from the HCL® Compass administrator.
- 1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

2. Click Active projects > My projects > project_name to open the project that contains the test assets.

The **Overview** page of the project is displayed.

3. Click Manage > Integration in the navigation pane.

The Integration page is displayed.

- 4. Click the CHANGE MANAGEMENT SYSTEM tab.
- 5. Click the **Open action menu** icon for the HCL® Compass server that you want to manage.

The Edit and Delete options are displayed in the list.

- 6. Perform any of the following actions when you want to edit or delete the HCL® Compass configuration:
 - \circ To edit the HCL® Compass configuration. Go to Step 7 on page 619.
 - \circ To delete the HCL® Compass configuration. Go to Step 8 on page 620.
- 7. Perform the following steps to edit the HCL® Compass configuration:
 - a. Select Edit as the option in the list.

The Configure Compass application dialog is displayed.

b. Modify the existing HCL® Compass server URL by entering the URL of the server that you want to use.



Note: You can enter the URL of HCL® Compass in any of the following formats:



https://IP_address:port/

https://hostname/

Where	ls
IP_address	The IP address of the server on which HCL® Compass is installed.
port	The port that is used to communicate with HCL® Compass.
hostname	The hostname of the computer on which HCL® Compass is in- stalled.

- c. Click Next, and then select the application from the Application list.
- d. Click Add.

The configuration is added and saved to the **CHANGE MANAGEMENT SYSTEM** tab. You can view the information in the **Configuration status** column to verify if the connection is established.

- 8. Perform the following steps to delete the existing HCL® Compass configuration:
 - a. Select **Delete** as the option in the list.

The Delete Compass configuration dialog is displayed.

b. Click Delete.

The HCL® Compass configuration is deleted and a confirmation message is displayed.



Note: The links to the records that you created for the tests that you ran are not deleted from the results panel in HCL OneTest[™] Server even after you delete the HCL® Compass configuration.

Results

You achieved the following results:

- Edited and saved the HCL® Compass configuration.
- Deleted the HCL® Compass configuration.

Integrations with other applications

You can integrate certain applications with HCL OneTest[™] Server to run tests, view the test results, and create defects.

Integration plugin compatibility matrix

You can find information about the versions of the integration plugin that are compatible with HCL OneTest™ Server.

The following table lists the versions of the integration plugin that are required to integrate HCL OneTest[™] Server with IBM® Engineering Test Management, HCL Launch, Jenkins, and UrbanCode[™] Deploy.

Note: You must download the required version of the integration plugin from the HCL® License & Delivery portal based on the existing version of HCL OneTest[™] Server. You can then integrate HCL OneTest[™] Server with Engineering Test Management, Jenkins, HCL Launch, and UrbanCode[™] Deploy.

HCL OneTest™ Server	Engineering Test Management plugin	Jenkins plugin	UrbanCode™ Deploy plugin	HCL® Launch plugin
10.1.0	NA	HOT-SERVER-Jenk- ins-2.0	HOT-SERVER-UCD-1.0	NA
10.1.1	NA	HOT-SERVER-Jenk- ins-3.0	HOT-SERVER-UCD-1.0	HOT-SERV- ER-LAUNCH-1.0
10.1.2	NA	HOT-SERVER-Jenk- ins-4.0	HOT-SERVER-UCD-2.0	HOT-SERV- ER-LAUNCH-2.0
10.1.3	NA	HOT-SERVER-Jenk- ins-4.0	HOT-SERVER-UCD-2.0	HOT-SERV- ER-LAUNCH-2.0
10.2.0	NA	HOT-SERVER-Jenk- ins-5.0	HOT-SERVER-UCD-3.0	HOT-SERV- ER-LAUNCH-2.0
10.2.1	HCL_OT_SERVER 1021_ETM	HOT-SERVER-Jenk- ins-5.0	HOT-SERVER-UCD-3.0	HOT-SERV- ER-LAUNCH-3.0
10.2.2	HCL_OT_SERVER 1022_ETM	HOT-SERVER-Jenk- ins-6.0	HOT-SERVER-UCD-3.0	HOT-SERV- ER-LAUNCH-3.0
10.2.3	HCL_OT_SERVER 1023_ETM	HOT-SERVER-Jenk- ins-6.1	HOT-SERVER-UCD-3.2	HOT-SERV- ER-LAUNCH-3.2
10.5.0	HCL_OT_SERVER 1050_ETM	HOT-SERVER-Jenk- ins-6.3	HOT-SERVER-UCD-3.3	HOT-SERV- ER-LAUNCH-3.3

Integration with Azure DevOps

When you use Azure DevOps for continuous integration and continuous development of your application, you can run tests created for your application and available in a project on HCL OneTest[™] Server, in Azure DevOps pipelines by using the *HCL OneTest Studio* extension.

Overview

You can use the HCL OneTest Studio extension to integrate HCL OneTest[™] Server with Azure DevOps.

The *HCL OneTest Studio* extension enables you to select any type of test available for your project in HCL OneTest[™] Server that you can add to your task for the job in the Azure DevOps pipelines.

You can now follow the tasks listed in the task flow table to integrate HCL OneTest[™] Server with Azure DevOps. See Task flow for integrating Azure DevOps on page 622.

Task flow for integrating HCL OneTest[™] Server with Azure DevOps

The table shows the task flow for integrating HCL OneTest[™] Server with Azure DevOps by using the *HCL OneTest* Studio extension. You must perform these tasks in sequence as listed in the following table. The table also provides you the links to the information about the tasks.

	Tasks	More information
1	Install HCL OneTest™ Server.	Installation of the server software on page 36
2	Create tests in the desktop clients for the application that you want to test.	 HCL OneTest[™] Performance documentation HCL OneTest[™] UI documenta- tion HCL OneTest[™] API documen- tation
3	Create a project on HCL OneTest [™] Server and add the test assets that are created in the desktop clients to your project.	Test assets and a server project on page 724
4	Create an organization and a project in Azure DevOps for running jobs in Azure DevOps pipelines.	Creating an organization
5	Access the Visual Studio Marketplace portal and search for the latest version of the <i>HCL OneTest Studio</i> extension.	Visual Studio Marketplace
6	Install the latest version of the <i>HCL OneTest Studio</i> ex- tension.	Installing the <i>HCL OneTest Studio</i> ex- tension on page 623

	Tasks	More information
7	Extend the trust certificate if you have used an internal CA certificate.	Certificate authority: Importing and extending lists on page 97
8	Run tests in an Azure DevOps pipeline.	Running tests in an Azure DevOps Pipeline on page 624

Related information

Integration with Azure DevOps on page 622

Installing the HCL OneTest Studio extension

You must install the latest version of the *HCL OneTest Studio* extension in your Azure DevOps organization before you can use the extension for running your application tests in an Azure DevOps pipeline.

Before you begin

You must have access to the **Visual Studio Marketplace** portal to install the latest version of the *HCL OneTest Studio* extension.

About this task

After you install the latest version of the *HCL OneTest Studio* extension from the **Visual Studio Marketplace** portal in your Azure DevOps organization, you can select the tests that you want to run for your application in an Azure DevOps pipeline by using the *HCL OneTest Studio* extension.

- 1. Log in to the Visual Studio Marketplace portal, if you are not already logged in.
- 2. Click the Azure DevOps tab.
- 3. Search for the HCL OneTest Studio extension.
- 4. Click the HCL OneTest Studio extension.
- 5. Click Get it free.

Result

The Visual Studio Marketplace portal for the HCL OneTest Studio extension is displayed.

- 6. Select the organization where you want to run your test from the Select an Azure DevOps Organization list.
- 7. Click Install.

Result

The installation is completed.

8. Click Proceed to organization.

Result

The **Organization** page in Azure DevOps is displayed.

9. Click Organization settings > Extensions.

Result

The HCL OneTest Studio extension is displayed as an installed extension.

Results

You have installed the HCL OneTest Studio extension in your Azure DevOps organization.

What to do next

You can run tests that are available in HCL OneTest[™] Server as a job in an Azure DevOps pipeline. See Running tests in an Azure DevOps Pipeline on page 624.

Running HCL OneTest[™] Server tests in an Azure DevOps Pipeline

After you install the *HCL OneTest Studio* extension in your organization, you can run tests that are available in HCL OneTest[™] Server as a job in Azure DevOps pipelines.

Before you begin

You must have completed the following tasks:

- Added the tests that you created in the desktop clients for your application to the project on HCL OneTest[™] Server.
- Installed the latest version of the *HCL OneTest Studio* extension in your organization. See Installing the *HCL OneTest Studio* extension on page 623.
- Installed an agent in your pipeline. See Azure Pipelines agents.
- Extended the CA list. See Extending the trusted CA list on Linux on page 99 or Extending the trusted CA list on Windows systems on page 100.
- Generated an offline user token from HCL OneTest[™] Server. See Generating an offline token on page 708.
- Created test cases under test plans if you want to view results of the test runs on the Test Plans dashboard.
- Created encrypted secrets or environment variables for your personal access token (PAT), if you want to use an encrypted PAT.

About this task

After you add the *HCL OneTest Studio* extension in your Azure DevOps organization, you can use an existing pipeline or create a new one to add HCL OneTest[™] Server test tasks. You can install an agent or use the one that you installed in your default agent pool. You can add HCL OneTest[™] Server tests as tasks to your agent job, configure the task, and then run the task in the Azure DevOps pipeline.

If you have created test cases under test plans in a project on Azure DevOps, you must provide the details of the Azure DevOps URL, test plan, test case, and your PAT while you configure the test job in a pipeline so that you can view the results of the test run on your Test Plan dashboard.

- 1. Open your **Organization** page in Azure DevOps and perform the following steps:
 - a. Click the project you want to use.
 - b. Initialize the repository by performing the following steps:
 - i. Click **Repos** from the left pane.
 - ii. Click Initialize from the Initialize with a README or gitignore section.

Note: Select the Add a README checkbox if it is not selected.

- c. Click Pipelines from the left pane.
- d. Click Create Pipeline.
- e. Click Use the classic editor to create a pipeline without YAML.
- f. Verify the project, repository, and branch for manual and scheduled builds, and then click Continue.
- g. Click Empty job.
- 2. Select **Pipeline** and complete the following steps:
 - a. Change the name for the build pipeline if required.
 - b. Select the Agent pool for your build pipeline.

You can use the agent from the default agent pool or use the one you have installed.


- c. Select the Agent Specification for the agent if required.
- 3. Add a task to the agent job by completing the following steps:
 - a. Click the **Add Task** icon + for the agent job.

Result

The Add tasks pane is displayed.

b. Search for the HCL tasks defined in the HCL OneTest Studio extension. Result

The tasks that you can select are displayed.



c. Select the HCL OneTest[™] Server Task, and then click Add to add the task to the agent job. Result

The selected task is added to the agent job and it is displayed with a warning that some settings require attention. You must configure the settings mentioned in step 4 on page 626.

You can also remove the tasks that are not required in your job. Select the tasks in the list that you want to remove. You can then right-click the tasks, and click Remove selected task(s) to remove them.

- 4. Configure the settings by performing the following steps:
 - a. Select the task version from the list if required.
 - b. Follow the action for the task by referring to the following table:

Note: All mandatory fields are marked with an asterisk (*) in the UI.

Field	Description	Action
Display	The default name of the	Enter a name for the task that helps you to identify the task by
name	task. The default name	changing the default name.
	that is displayed is HCL	
	OneTest Server Task.	

Field Description	Action
HCL The details of HCL OneTest™ OneTest™ Server to set	Select the service connection from the drop-down list.
Server up a connection with service Azure DevOps. connec-	If you are selecting the HCL OneTest [™] Server service connec- tion for the first time, you must click New to add the following details to add an HCL OneTest [™] Server service connection, and then save the connection details:
tion	 Server URL - Enter the URL of HCL OneTest[™] Server.

- er. The format of the URL is as follows: https://hostname.
- · Offline Token Enter the offline token that you generated from HCL OneTest[™] Server.
- Service connection name Enter a service connection name.
- Description (optional) Enter the details of the service connection if required.
- Optionally, select the Grant access permission to all pipelines checkbox if required.

You can save the service connection details. The service connection is available for selection from the HCL OneTest™ Server service connection drop-down list.



Note:

You can edit or delete the service connection that you added if required. Click Manage, and then select the service connection from the Service connections list to open the service connection. You can click Edit to edit the service connection details. If you want to delete an existing service connection details, click the Vertical ellipsis icon, and then click Delete to delete the service connection details.

Optionally, you can also create, edit, and delete a service connection from your Azure DevOps project dashboard. Open your project, click Project settings > Service connections, and then perform any of the following tasks:

- Create a new service connection.
- · Edit or delete an existing service connection that you already added.

Field	Description	Action
Team Space	The name of the team space on HCL OneTest [™] Server that contains your project with the test as- sets.	Enter the name of the team space that contains the project.
Name		Note: The license on the team space must be configured and you must be a member of that team space.
Project	The name of the project containing the test as- sets in your team space on HCL OneTest [™] Server.	Enter the name of the project from the available names in the team space.
		Note: The Project drop-down list displays the projects where you are an <i>Owner</i> or a <i>member</i> of HCL OneTest [™] Server. You must be an <i>Owner</i> or a <i>Tester</i> of the project that is available in the team spaces to run the tests from the Jenkins server.
		Azure DevOps pipeline.
Branch	The name of the branch of the repository in your project on HCL OneTest [™] Server that contains the test assets.	Enter the branch where the test assets are stored.
Reposi- tory Link	The URL or link to the repository in your project that contains the test as- sets.	Enter the repository path that is configured for the project that contains the test to run.
File Path	The path of the test in the repository of your project.	Enter the path of the test in HCL OneTest™ Server that you want to run.
API Test Environ- ment		Enter the name of the environment that is configured in the test asset for the test created in HCL OneTest [™] API.

Field	Description	Action
		Note: This field is applicable only if you are running an API suite test.
Variables	The variable name and its value.	Enter the name of the variable and its value if your test requires variables during the test run time.
		You must enter the variables in the following format:
		name_of_the_variable=value_of_the_varibale
	The name with path to the dataset that must be used during the test run.	You can add multiple variables to the test run separated by a semicolon.
		For example, varname1=value1;varname2=value2
Datasets		Enter the path to the dataset if you want to replace the values of the dataset during a test run.
		You must ensure that both original and new datasets are in the same workspace and have the same column names. When you enter a value for the Datasets field, you must also include the path to the dataset. The path must be in the following format:
		/project_name/ds_path/original_d-
		s.csv:/project_name/ds_path/new_ds.csv
		Note: You can override multiple datasets that are saved in a different project by adding multiple paths to the dataset separated by a semicolon.
Labels	The option to add labels to the test results when the test run is complete.	Enter the labels to add to test results when the test run is complete.
		You can add multiple labels to a test result separated by a com- ma.
		For example, label1, label2
		After the test run is complete, then the values provided in the Labels field are displayed on the Results page of HCL OneTest [™] Server.

Field	Description	Action
Secrets Col-	The name of the secrets collection that contains the secrets to be used	Enter the name of the secrets collection that contains the se- crets to be used in the API Suite or test.
lection Name	in certain API Suites or tests.	Note: This field is applicable only if you are running an API suite test.
Azure DevOps Project	The URL of the test project in the organiza- tion on the Azure DevOps	Enter the URL of the test project in the organization on the Azure DevOps server in the following format: https:// <host>/<orgname>/<projectname></projectname></orgname></host>
URL	server. Note: You must enter the details for this option if you have created test cases under test plans in your Azure project and want to view the test results on the Test Plans Dashboard.	You must use this option with the following options: • Azure DevOps PAT • Test Plan Name • Test Case Name
Azure DevOps PAT	The personal access to- ken (PAT) of the Azure server where the test project that contains the test plan is hosted. You can also enter the vari- able for the encrypted PAT that you create in	Enter your personal access token. You must use this option with the following options: • Azure DevOps Project URL • Test Plan Name • Test Case Name

Azure DevOps.

Field	Description	Action	
	Note: The token must have read and write access.		
Test Plan	The name of the test plan	Enter the name of the test plan.	
Name	in your Azure project.	You must use this option with the following options: Azure DevOps Project URL Azure DevOps PAT Test Case Name 	
Test	The name of the test	Enter the name of the test case.	
Case Name	case under the test plan in your Azure project.	You must use this option with the following options: Azure DevOps Project URL Azure DevOps PAT Test Plan Name 	
Export JUnit Re-	The location to store the JUnit report of the test.	Enter the path to store the JUnit report that is generated for the test in the XML format.	
port		You must specify the complete path to the directory including the file name of the report.	
		For example, C:/Users/Documents/Reports/junit_test_report.xml	

- c. Expand Control Options and configure the settings for your task if required.
- d. Expand Output Variables and configure the settings for your task if required.
- 5. Select from the following options:
 - a. Click Save to save the configured settings for the task.
 - **Note:** The task is not queued for a run.

You can save the task to a build pipeline and opt to run the build at a later time.

b. Click **Save & queue** to save the configurations and queue the run in the pipeline. **Result**

The Run pipeline dialog is displayed.

- 6. Complete the following steps:
 - a. Enter a comment for the test in the Save comment field.
 - b. Select the agent that you configured for the test from the Agent pool list.
 - c. Select the agent specification from the Agent Specification list if required.
 - d. Select the branch from the Branch/tag list.
 - e. Add the variables and demands for the task run from the Advanced Options pane if required.
 - f. Select the Enable system diagnostics checkbox for a detailed log view.
 - g. Click Save and run.

Result

The pipeline summary page displays the progress of the job run.

Results

You have run the tests for the application that you are testing in the Azure DevOps pipeline.

What to do next

You can perform any of the following actions in Azure DevOps:

• View the test results on the Task page by clicking the task.

The **Reports information** section on the **Task** page displays the names of the report along with its corresponding URLs. The report URLs are the HCL OneTest[™] Server URLs where the reports are stored. You can access the report URLs to view the test run information at any point of time.

- View the task logs from the **pipeline summary** page for the job you ran.
- View the test results on the Test Plans Dashboard if you created test cases under test plans in your Azure project.

You can perform any of the following actions in HCL OneTest[™] Server:

- View the test results of the test that you ran from Azure DevOps on the Results page.
- View the logs and reports of the test that you ran from Azure DevOps by clicking the result panel of the test asset or resource, and then click the log or the report you want to view.

Integration with HCL® Launch

You can integrate HCL OneTest[™] Server with HCL® Launch to run test assets as a **Process** from HCL® Launch.

When you use HCL® Launch for automating the deployments of your applications to an environment during the development cycle, you can create test assets for your application either in HCL OneTest[™] Server or desktop clients. After you configure the project in HCL OneTest[™] Server, you can then run those tests assets from HCL® Launch.

You must use the HCL OneTest[™] Server Launch plugin to integrate HCL OneTest[™] Server with HCL® Launch. Integrating HCL OneTest[™] Server with HCL® Launch automates the process of test runs. If you have many tests to run at regular intervals, you can use HCL® Launch to initiate test runs automatically.

Tasks	Go to
Create any or all the following types of test assets either in HCL OneTest [™] Server or desktop clients to test your application: • API test assets • Functional test assets • Performance test assets	 HCL OneTest[™] API Documentation HCL OneTest[™] Performance Documentation HCL OneTest[™] UI Documentation Test authoring on page 130 in HCL OneTest[™] Server
Create a project, and then configure the repository in HCL OneTest™ Server.	Working with projects in a team space on page 724
Install HCL® Launch with at least one agent.	HCL® Launch documentation. System Requirements on page 17 for information about specific versions of HCL® Launch requirements.
Install the HCL OneTest™ Server Launch plugin on HCL® Launch.	Installing the plugin on HCL Launch on page 633.
Create a Component in HCL® Launch.	Creating a component in HCL Launch on page 636.
Create a Process for the component in HCL® Launch.	Creating a process in HCL Launch on page 636.
Configure the Process that you created for the compo- nent in HCL® Launch.	Configuring the process on page 637.
Create a Resource in HCL® Launch.	Creating a resource in HCL Launch on page 642.
Configure the Resource in HCL® Launch.	Configuring the resource on page 643.
Create an Application in HCL® Launch.	Creating an application in HCL Launch on page 644.
Configure the Application that you use to run perfor- mance test assets in HCL® Launch.	Configuring the application on page 645.
Run the test assets from HCL® Launch.	Running tests fromHCL Launch on page 647.

The following table lists the tasks that you must perform to run performance test assets from HCL® Launch:

Installing the plugin on HCL® Launch

You must install the HCL OneTest[™] Server Launch plugin to run test assets from HCL® Launch.

Before you begin

- You must be familiar with working with HCL® Launch.
- · You must have performed the following tasks:
 - Installed HCL® Launch. For more information about the installation, refer to the HCL Launch documentation.
 - Been granted access to HCL® Launch.
 - Downloaded the HCL OneTest[™] Server Launch plugin from the HCL® License & Delivery portal.

For more information about specific versions of plugin, see Integration plugin compatibility matrix on page 620.

1. Log in to HCL® Launch, if you are not already logged in.

Result

The HCL® Launch dashboard is displayed.

- 2. Click Settings.
- 3. Click Automation Plugins from the Automation pane.
- 4. Click Load Plugin.
- 5. Click **Choose File** to locate and open the compressed HCL OneTest[™] Server Launch plugin file.

Remember: You must not extract the HCL OneTest[™] Server Launch plugin compressed file contents.

6. Click Submit.

Result

The installed plugin is displayed on the Automation Plugins tab.

Results

You have installed the HCL OneTest[™] Server Launch plugin on HCL® Launch.

What to do next

You must create a Component in HCL® Launch. See Creating a component in HCL Launch on page 636.

Using a custom trust store for HCL® Launch

You can use a custom trust store in the HCL OneTest[™] Server Launch plugin file to establish a trusted and secure connection between the HCL® Launch server and HCL OneTest[™] Server.

Before you begin

You must have completed the following tasks:

You must have completed the following tasks:

• Saved the Certificate Authority (CA) assigned to HCL OneTest[™] Server.

Note: You can contact the administrator of HCL OneTest[™] Server if you do not have a copy of the CA.

• Installed Java on the computer from where you access the HCL OneTest[™] Server UI.

About this task

If the SSL certificate assigned to HCL OneTest[™] Server is signed by an internal Certified Authority (CA), then you must download and import the CA certificate to a custom trust store. You can then use the custom trust store in the HCL OneTest[™] Server test process step to establish a trusted and secure connection between the HCL® Launch server and HCL OneTest[™] Server.



Note: If the internal CA certificate is already imported to the default trust store that is used by the HCL® Launch server, you need not use a custom trust store.

- Locate the default trust store file (cacerts file) from the JRE directory.
 For example: C:\Program Files\Java\jdk-18.0.1.1\lib\security
- 2. Copy the cacerts file to a location of your choice on your computer.
- 3. Place the CA assigned to HCL OneTest[™] Server in the same location where you saved the cacerts file.
- Run the following command from the command-line interface or terminal to import the CA of HCL OneTest[™] Server to custom trust store:

keytool -import -trustcacerts -file {path to the downloaded CA with the file extension} -alias
{label for the certificate} -keystore {path to the trust store cacerts file}

For example,

```
keytool -import -trustcacerts -file C:\Users\Desktop\cert\ca-master-hcl.crt -alias "otsca" -keystore
C:\Users\Desktop\cert\cacerts
```



Note: The default password of the trust store is *changeit*. It remains the same for the custom trust store. If you want to change the password, you can run the following command, and then enter the new password:

keytool -storepasswd -keystore {path to the trust store cacerts file}

For example, keytool -storepasswd -keystore C:\Users\Desktop\cert\cacerts

Results

You have successfully imported the downloaded CA to the custom trust store.

What to do next

You can then run the tests that are available in your HCL OneTest[™] Server project from the HCL® Launch server.

Creating a component in HCL® Launch

You must create a component to include artifacts and processes. The artifacts include runnable files, images, databases, configuration instructions. Whereas the processes define the activities that components can perform.

Before you begin

- You must be familiar with working with HCL® Launch.
- You must have been granted access to HCL® Launch.
- 1. Log in to HCL® Launch, if you are not already logged in.

Result

The HCL® Launch dashboard is displayed.

- 2. Click Components, and then click Create Component.
- 3. Enter a name for the component in the **Name** field.
- 4. Enter the details in the other optional fields based on your requirement, and then click Save.

Result

The component that you created is displayed.

Results

You have created the component in HCL® Launch.

What to do next

You must create a process for the component in HCL® Launch. See Creating a process in HCL Launch on page 636.

Related information

HCL Launch Documentation

Creating a process in HCL® Launch

You must create a process for the component to include step properties for the test that you want to run from HCL® Launch.

Before you begin

- You must be familiar with working with HCL® Launch.
- You must have performed the following tasks:
 - Been granted access to HCL® Launch.
 - Created a component in HCL® Launch. See Creating a component in HCL Launch on page 636.

1. Log in to HCL® Launch, if you are not already logged in.

Result

The HCL® Launch dashboard is displayed.

2. Click Components.

Result

A list of components that are available in HCL® Launch is displayed.

- 3. Select the component from the list for which you want to create a process.
- 4. Click the Processes tab, and then click Create Process.

Result

The Create Process dialog is displayed.

- 5. Enter a name for the process in the Name field.
- 6. Select Operational (No Version Needed) from Process Type drop-down list.
- 7. Verify the Default Working Directory field.

The **Default Working Directory** field defines the location that the agent uses to run the process. The default value is $f_{p:resource/work.dir}/$ \${p:component.name}.

Where $f_{p:resource/work.dir}$ is the default working directory for the agent and $f_{p:component.name}$ is the name of the component.

8. Click Save.

Result

The process that you created is listed in the **Processes** tab and the **Design** tab for the process is displayed.

Results

You have created the process for the component in HCL® Launch.

What to do next

You must configure the process in HCL® Launch. See Configuring the process on page 637.

Related information

HCL Launch Documentation

Configuring the process

You must configure the process that you created for the component to organize the steps in the process, specify the properties of the steps, and connect them.

Before you begin

- You must be familiar with working with HCL® Launch.
- · You must have performed the following tasks:

- Been granted access to HCL® Launch.
- Created a component in HCL® Launch. See Creating a component in HCL Launch on page 636.
- Created a process for the component in HCL® Launch. See Creating a process in HCL Launch on page 636.

About this task

When you open any process to configure, the process is displayed in the process editor. The process editor lists the plugins and steps. The required **Start** and **Finish** steps represent the beginning and the end of the process and steps are automatically placed on the design area.

You must provide the values for certain fields in the properties for the selected test step to run tests from HCL® Launch.

1. Log in to HCL® Launch, if you are not already logged in.

Result

The HCL® Launch dashboard is displayed.

2. Click Components.

Result

A list of components that are available in HCL® Launch is displayed.

- 3. Select the component from the list in which you created the process.
- 4. Click the Processes tab.

Result

A list of processes that are available for the component is displayed.

5. Select the process from the list that you want to configure.

Result

The **Design** tab for the process is displayed.

- 6. Click HCL OneTest Studio, and then HCL OneTest Server from the left menu.
- 7. Drag the Run HCL OneTest[™] Servertest step, and then drop it into the design area.



Note: The selected test must be placed between Start and Finish steps.

- 8. Specify the properties for the selected test by performing the following steps:
 - a. Click the Edit icon.

Result

The Edit Properties for Run an HCL OneTest Server test dialog is displayed.

b. Specify the properties for the selected test step by referring to the following table:

The following table lists the required fields that you must provide to run the test from HCL® Launch:

Fields	Action	
Name	Enter the name for the test step.	
HCL OneTest Server URL	Enter the URL of HCL OneTest [™] Server.	
Offline Token	Enter the offline token that you generated from HCL OneTest™ Server.	
Team Space Name	Enter the name of the team space that contains the project.	
	Note: The license for the team space must be configured and you must be a member of that team space.	
Project Name	Enter the name of the project that are available in the team space.	
Repository Link	Enter the URL of the Git repository that you added to your project in HCL OneTest™ Server.	
File Path	Enter the path of the test assets that you want to run. You can find the path of the test assets from the Execution page	
	in HCL OneTest™ Server	

The following table lists the optional fields that you can provide to run the test from HCL® Launch:

Fields	Description	
Branch Name	Use this field to enter the name of the branch in the Git repository where you stored test assets.	
Custom Trust	Use this field to enter the trust store password if you have modified the password while creating the custom trust store.	

Fields	Description
Store Pass- word	Note: If you have not modified the trust store password, you can retain the Cus- tom Trust Store Password field blank.
Custom Trust Store Path	Use this field to enter the file path of your trust store followed by the file name if HCL OneTest [™] Server uses an internal CA certificate and you have imported the certificate to a custom trust store.
Datasets	Use this field to enter the path to the dataset if you want to replace the values of the dataset during a test run.
	You must ensure that both original and new datasets are in the same workspace and have the same column names. When you enter a value for the Datasets field, you must also include the path to the dataset. The path must be in the following format:
	<pre>/project_name/ds_path/original_ds.csv:/project_name/ds_path/new ds.csv</pre>
	Note : You can override multiple datasets that are saved in a different project by adding multiple paths to the dataset separated by a semicolon.
Environ- ment	Use this field to enter the environment details for the following types of test assets: • APISUITE • APITEST • APISTUB
Labels	Use this field to add labels to test results when the test run is complete.
	You can add multiple labels to a test result separated by a comma. For example, <i>label1, label2</i>
	After the test run is complete, then the values provided in the Labels field are displayed on the Results page of HCL OneTest [™] Server.
Secrets Col- lection	Use this field to enter the name of the Secret if you created secrets collections for your project and to use Secrets at test run time.
Name	This field is mandatory only if you want to run the following types of test assets:

Fields	Description	
	APISUITE	
	APITEST ADISTUB	
	APISTUB	
Show Hidden	Select this checkbox if you want to use an HTTP Proxy to connect to HCL OneTest [™] Serv-	
Proper-	er.	
ties	After you select the Show Hidden Properties checkbox, you can configure the HTTP Proxy by using the following fields:	
	 HTTP Proxy Host: Use this field to enter the hostname of the HTTP proxy that you want to connect to HCL OneTest[™] Server. 	
	HTTP Proxy Port: Use this field to enter the port number where the HTTP proxy is used to listen to both HTTP and HTTPS traffic.	
	 HTTP Proxy User name: Use this field to provide the username for the HTTP proxy. 	
	 HTTP Proxy Password: Use this field to enter a valid password for the user that you specified in the HTTP Proxy User name field. 	
	Note: You can use the Show Hidden Properties field only when you want to run the following types of test assets:	
	APISUITE	
	• APITEST • APISTUB	
Variables	Use this field to enter the name of the variable and its value if your test requires variables	
	during the test run time.	
	You must enter the variables in the following format:	
	name_of_the_variable=value_of_the_varibale	
	You can add multiple variables to the test run separated by a semicolon.	
	For example, varname1=value1;varname2=value2	

Note: In addition to optional fields, you can also use the following fields from HCL® Launch to configure your test run:



- Working Directory
- Precondition
- Post Processing Script
- Use Impersonation
- Auth Token Restriction

You can accept the default values or change the values based on your requirements. For more information about these fields, see the related links.

c. Click **OK** to save the properties for the test.

9. Click **Save** in the design area.

Results

You have configured the process for the component in HCL® Launch.

What to do next

You must create a resource in HCL® Launch. See Creating a resource in HCL Launch on page 642.

Related information

HCL Launch Documentation Process step preconditions Post-processing scripts User impersonation for process steps Restricting authentication tokens

Creating a resource in HCL® Launch

You must create a resource to associate agents with components that you created in HCL® Launch.

Before you begin

- You must be familiar with working with HCL® Launch.
- You must have been granted access to HCL® Launch.
- 1. Log in to HCL® Launch, if you are not already logged in.

Result

The HCL® Launch dashboard is displayed.

2. Click Resources, and then click Create Top-Level Group. Result

The **Create Resource** dialog is displayed.

- 3. Enter a name for the resource in the **Name** field.
- 4. Click Save.

Results

You have created the resource in HCL® Launch.

What to do next

You must configure the resource. See Configuring the resource on page 643.

Related information

HCL Launch Documentation

Configuring the resource

You must configure the resource to add an agent and associate the agent with the component.

Before you begin

- You must be familiar with working with HCL® Launch.
- · You must have performed the following tasks:
 - Been granted access to HCL® Launch.
 - Created a component in HCL® Launch. See Creating a component in HCL Launch on page 636.
 - Created a resource in HCL® Launch. See Creating a resource in HCL Launch on page 642.
- 1. Log in to HCL® Launch, if you are not already logged in.

Result

The HCL® Launch dashboard is displayed.

2. Click Resources.

Result

- A list of resources that are available in HCL® Launch is displayed.
- 3. Perform the following steps to add an agent to the resource:
 - a. Click the resource from the list for which you want to add an agent.
 - b. Click the Actions icon from the last column, and then click Add Agent.
 - c. Select the agent from the drop-down list.



Note: The Name field is auto populated with the name of the agent.

d. Click Save.

Result

The selected agent is added to the resource and you can view the status of the agent in the **Status** column.

- 4. Perform the following steps to add a component to the agent:
 - a. Click the agent from the list for which you want to add a component.
 - b. Click the Actions icon from the last column, and then click Add Component.
 - c. Select the component from the drop-down list.



Note: The Name field is auto populated with the name of the component.

d. Click Save.

Result

The selected component is added to the agent.

Results

You have configured the resource in HCL® Launch.

What to do next

You must create an application. See Creating an application in HCL Launch on page 644.

Related information

HCL Launch Documentation

Creating an application in HCL® Launch

You must create an application to fetch all the components together that you want to deploy.

Before you begin

- You must be familiar with working with HCL® Launch.
- You must have been granted access to HCL® Launch.
- 1. Log in to HCL® Launch, if you are not already logged in.

Result

The HCL® Launch dashboard is displayed.

- 2. Click Applications.
- 3. Click Create Applications, and then New Applications.
- 4. Enter a name for the application in the Name field.

Result

The Environments page for the application that you created is displayed.

Results

You have created the application in HCL® Launch.

What to do next

You must configure the application. See Configuring the application on page 645.

Related information

HCL Launch Documentation

Configuring the application

You must configure the application to associate resources with environments and define processes to run test assets.

Before you begin

- You must be familiar with working with HCL® Launch.
- · You must have performed the following tasks:
 - Created a process for the component in HCL® Launch. See Creating a process in HCL Launch on page 636.
 - Created a component in HCL® Launch. See Creating a component in HCL Launch on page 636.
 - Created a process for the component in HCL® Launch. See Creating a process in HCL Launch on page 636.
 - Configure the process for the component in HCL® Launch. See Configuring the process on page 637.
 - Created a resource in HCL® Launch. See Creating a resource in HCL Launch on page 642.
 - Configured the resource in HCL® Launch. See Configuring the resource on page 643.
 - Created an application in HCL® Launch. See Creating an application in HCL Launch on page 644.
- 1. Log in to HCL® Launch, if you are not already logged in.

Result

The HCL® Launch dashboard is displayed.

2. Click Applications.

Result

A list of applications that are available in HCL® Launch is displayed.

3. Click the application that you want to configure from the Name column.

Result

The Environments page for the selected application is displayed.

- 4. Perform the following steps to create an environment for the application that you selected:
 - a. Click Create Environment.
 - b. Enter a name for the environment in the Name field.
 - c. Click Save.
- 5. Perform the following steps to configure resources to the environment:
 - a. Click the environment that you created.
 - b. Click Add Base Resources.

Result

A list of resources that are available in HCL® Launch is displayed.

- c. Select the checkbox to add resources to the environment.
- d. Click Save.

Result

You can view the corresponding agent and the component that you added for the resource by using the **Expand** icon.

- 6. Perform the following steps to add the component to the application:
 - a. Click **Applications**, and then select your application from the list.
 - b. Click the Components tab, and then Add Components.
 - c. Select the checkbox from the drop-down list to add components to the application.
 - d. Click Save.
- 7. Perform the following steps to create a process for the application:
 - a. Click the Processes tab, and then Create Process.
 - b. Enter a name for the process in the Name field.
 - c. Click Save.

Result

The **Design** tab for the process that you created is displayed.

- 8. Drag the component process listed under the **Component Process Steps** option from the left navigation pane and drop it into the design area.
- 9. Select the component process from the drop-down list in the Operational (No Version Needed) Process field.
- 10. Click Save.
- 11. Click the Edit icon, and then change the name of the properties.
- 12. Click **OK**, and then click **Save**.

Results

You have configured the application to run test assets from HCL® Launch.

What to do next

You can run test assets from HCL® Launch. See Running tests from HCL Launch on page 647.

Related information

HCL Launch Documentation

Running tests fromHCL® Launch

You can run test assets from HCL® Launch as a Process to test your application under test.

Before you begin

- You must be familiar with working with HCL® Launch.
- · You must have performed the following tasks:
 - Been granted access to HCL® Launch.
 - Created a component in HCL® Launch. See Creating a component in HCL Launch on page 636.
 - Created a process for the component in HCL® Launch. See Creating a process in HCL Launch on page 636.
 - Configure the process for the component in HCL® Launch. See Configuring the process on page 637.
 - Created a resource in HCL® Launch. See Creating a resource in HCL Launch on page 642.
 - Configured the resource in HCL® Launch. See Configuring the resource on page 643.
 - Created an application in HCL® Launch. See Creating an application in HCL Launch on page 644.
 - Configured the application in HCL® Launch. See Configuring the application on page 645.
 - Started the HCL® Launch agent. For more information, refer to the HCL Launch documentation.
- 1. Log in to HCL® Launch, if you are not already logged in.

Result

The HCL® Launch dashboard is displayed.

2. Click Applications.

Result

A list of applications that are available in HCL® Launch is displayed.

- 3. Click the application that you configured for the test run.
- 4. Click the Request Process icon.

Result

The Create Deployment page is displayed.

- Select the process that you created for the application which contains the test assets from the Process dropdown list.
- 6. Click Next, and then select the specific version of component, if any.

Note: If you have multiple versions for your component, then only you can choose the required version by clicking the **Add** option.

- 7. Click **Next**, and then verify the properties for the test run.
- Click Next, and then verify that the status of the Run Now option is enabled.
 You can disable the Run Now option, and then use the Date, Time, and Recurrence Pattern fields to run tests as Process at the scheduled time.
- 9. Click **Next**, and then verify the details about the **Process**.
- 10. Click **Submit Deployment** to initiate the test run.

Results

You have run the performance test assets as **Process** from HCL® Launch.

What to do next

You can view the status of the process as follows:

- Success: When the test run is successful
- Failed: When the test run fails

You can view the details of the test run in the **Execution Log** section. The **Reports information** section on the Log file displays the names of the report along with its corresponding URLs.

Integration with IBM® Engineering Test Management

As a *Project Owner*, you can integrate IBM® Engineering Test Management as a quality management solution with HCL OneTest[™] Server. You can run test assets that are available in a project from Engineering Test Management.

The following topics provides more information about the integration of HCL OneTest[™] Server with Engineering Test Management.

Task flow for integration of IBM® Engineering Test Management

You must perform the following tasks in sequence to integrate HCL OneTest[™] Server with IBM® Engineering Test Management. For more information about the tasks, refer to the links provided in the table.

SI. No	Tasks	More information
1	Create a project in HCL OneTest™ Server.	Adding a project on page 727
2	Install the required version of Engineering Test Man- agement on your computer.	Engineering Lifecycle Management Documentation

SI. No	Tasks	More information
3	Download the Engineering Test Management adapter, and then extract the contents of a com- pressed file.	HCL® License & Delivery portal
	For more information about specific versions of plu- gin, see Integration plugin compatibility matrix on page 620.	
4	Add the adapter files that you downloaded to the installation directory of Engineering Test Management.	Adding the adapter files to IBM Engineering Test Management on page 649
5	Configure the details of Engineering Test Manage- ment on HCL OneTest™ Server.	Configuring IBM Engineering Test Management on HCL OneTest Server on page 650
6	Create a test script and a test case on Engineering Test Management to run the test assets.	Preparing test cases in IBM Engineering Test Man- agement on page 652
7	Run the test assets from Engineering Test Manage- ment.	Running tests from IBM Engineering Test Manage- ment on page 653

Adding the adapter files to IBM® Engineering Test Management

You must add the adapter files to the installation directory to run test assets of HCL OneTest[™] Server from IBM® Engineering Test Management.

Before you begin

You must have completed the following tasks:

- Installed the latest version of Engineering Test Management from the Jazz portal on your computer. See System Requirements on page 13.
- Downloaded the adapter (a compressed file) for Engineering Test Management from the HCL® License & Delivery portal.

For more information about specific versions of plugin, see Integration plugin compatibility matrix on page 620.

About this task

You must add the adapter files to the location where you installed Engineering Test Management to run test assets of HCL OneTest[™] Server.

- 1. Extract the compressed file that you downloaded from the HCL® License & Delivery portal.
- $\label{eq:copy-the-etm-adapter-updatesite-folder} 2. \ Copy \ the \ \texttt{etm-adapter-updatesite-folder}.$

- 3. Go to the location where you installed Engineering Test Management on your computer.
- 4. Place the etm-adapter-updatesite folder in the sites folder of the installation directory of Engineering Test Management.

For example, D:\ELM\JazzTeamServer\server\conf\qm\sites.

- 5. Copy the ots-profile.ini file from the provision_profiles folder that is available in the extracted zip file.
- 6. Place the ots-profile.ini file in the provision_profiles folder of the installation directory of Engineering Test Management.

For example, D:\ELM\JazzTeamServer\conf\qm\provision_profiles

Results

You have added the adapter files to Engineering Test Management.

What to do next

You must perform the following tasks:

• You must reset the Engineering Test Management server from the web console by using the **Request Server Reset** option.

If you have administrator privileges, then you can access the **Request Server Reset** option from the following URL:

https://<hostname>:<portnumber>/qm/admin?

internal#action=com.ibm.team.repository.admin.serverReset

Note: You must replace the following values with the actual values in the URL:

- <hostname> with the hostname that you used when you installed Engineering Test Management.
- <portnumber> with the port number that is associated with an IP address of the hostname.
- Restart the Engineering Test Management server.
- Configure the details of Engineering Test Management on HCL OneTest[™] Server to establish a connection between the two products. See Configuring IBM Engineering Test Management on HCL OneTest Server on page 650.

Configuring IBM® Engineering Test Management on HCL OneTest[™] Server

You must configure IBM® Engineering Test Management on HCL OneTest[™] Server to establish a connection between the two products.

Before you begin

You must have completed the following tasks:

- Granted sufficient privileges to access Project area on Engineering Test Management.
- Created a project area in Engineering Test Management.
- Created a project in HCL OneTest[™] Server.

About this task

If you have multiple instances of Engineering Test Management, then you can configure all those instances on HCL OneTest[™] Server. If you have only one instance of Engineering Test Management, you can configure the same instance multiple times. However, you must choose a different **Project area** during the configuration of Engineering Test Management.

- 1. Log in to HCL OneTest[™] Server, if you are not already logged in.
- 2. Open a project from the team space.
- 3. Click Manage > Integration.
- 4. Click the TEST MANAGEMENT tab, and then click Add IBM ETM adapter.
- 5. Enter the following information on the Add IBM ETM adapter dialog:

Fields	Actions	
Server URL	Enter the URL of Engineering Test Management.	
	For example, https:// <hostname>:<portnumber>/qm</portnumber></hostname>	
Authentication Type	Select UserName and Password from the list.	
Username	Enter the username associated with Engineering Test Management.	
Password	Enter the password associated with the username of Engineering Test Management.	

6. Click Validate.

- 7. Select the project name that you created in Engineering Test Management from the **Project area** drop-down list.
- 8. Enter a name for the Engineering Test Management adapter in the Adapter name field.



Note: You cannot provide an adapter name that already exists for the Project area.

9. Click Save.

Results

You have configured the details of Engineering Test Management on HCL OneTest[™] Server.

What to do next

You must create a test script and test case on Engineering Test Management to run the test assets of HCL OneTest[™] Server. See Preparing test cases in IBM Engineering Test Management on page 652.

Preparing test cases in IBM® Engineering Test Management

You must create a test script and a test case on IBM® Engineering Test Management to run the test assets.

Before you begin

You must have completed the following tasks:

- Added the adapter files to the installation directory of Engineering Test Management. See Adding the adapter files to IBM Engineering Test Management on page 649.
- Configured the details of Engineering Test Management on HCL OneTest[™] Server. See Configuring IBM Engineering Test Management on HCL OneTest Server on page 650.
- Generated an offline user token from HCL OneTest[™] Server. See Generating an offline token on page 708.
- Copied the following values to be used during the preparation of a test script and a test case:
 - Branch name of the Git repository
 - Asset ID of the test that you want to run
 - Optional: Name of the environment if you want to run the API test suite.
- 1. Log in to Engineering Test Management, if you are not already logged in.
- 2. Open your project area from where you want to run the test assets.
- 3. Click **Construction**, and then click **Test Script** from the drop-down list.
- 4. Enter a name for the test script in the Test Script field.
- 5. Select HCL OneTest Server from the Type drop-down list.
- 6. Enter the following test information:

Fields	Actions
Offline Token	Enter the offline token that you generated from HCL OneTest [™] Server.
Branch	Enter the name of the branch where your test assets are stored.
Asset ID	Enter an asset ID of the test asset that is available on the Execution page of HCL OneTest [™] Server.
	<i>i</i> Tip: You can hover over the name of the test asset to view and copy the asset ID.
Environment	Enter a name of the API test environment.

Fields	Actions
	Remember: You must use this field only if you want to run the API test suites.

7. Click Save.

- 8. Perform the following steps to add a test script to a test case:
 - a. Click Construction > Test Case.

Result

The **Test Cases** page is displayed.

- b. Enter a name for the test case in the Test Case field.
- c. Click Test Scripts from the left navigation pane.
- d. Click the Plus icon from the Test Scripts panel.

Result

The **Add Test Scripts** dialog is displayed.

- e. Select the checkbox to add the test script that you created to the test case, and then click **Add and Close**.
- f. Click Save.

Results

You have prepared Engineering Test Management.

What to do next

You can run the test assets of HCL OneTest[™] Server from Engineering Test Management. See Running tests from IBM Engineering Test Management on page 653.

Running tests from IBM® Engineering Test Management

After you create a test case in IBM® Engineering Test Management, you can run the test. The test case includes the test scripts that contains test assets of HCL OneTest[™] Server.

Before you begin

You must have performed the following tasks:

- Prepared Engineering Test Management to run test assets of HCL OneTest[™] Server. See Preparing test cases in IBM Engineering Test Management on page 652.
- Configured the details of Engineering Test Management on HCL OneTest[™] Server. See Configuring IBM Engineering Test Management on HCL OneTest Server on page 650.

- 1. Log in to Engineering Test Management.
- 2. Open the test case that you created in Engineering Test Management.
- 3. Click the **Play** icon 5. and then click **Run**.

Result

The Run Test Case dialog is displayed.

- 4. Click the **ChangeMachine** icon rext to the **Machine** field to select the adapter that you configured on HCL OneTest[™] Server.
- 5. Select the required adapter name from the list, and then click OK.
- 6. Click **Finish** to start the test run.

The Engineering Test Management dashboard displays the progress of the test case run.

Results

You have run the test assets of HCL OneTest[™] Server from Engineering Test Management.

What to do next

You can perform the following tasks:

- Click **Show Result** to view information about the test results from Engineering Test Management when the test run is complete.
- Click Link to Result from Results details to view the test results from the Results page of HCL OneTest[™] Server. See Test results and reports on page 514.

Deleting an IBM® Engineering Test Management adapter

You might want to delete an IBM® Engineering Test Management adapter when it is no longer needed.

Before you begin

You must have completed the following tasks:

- Been assigned the role of *Owner* of a project or *Owner* of the project in HCL OneTest[™] Server.
- Configured the details of Engineering Test Management on HCL OneTest[™] Server. See Configuring IBM Engineering Test Management on HCL OneTest Server on page 650.
- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Click Manage > Integration.
- 3. Click the TEST MANAGEMENT tab.

You can view the Engineering Test Management adapters that are configured with the project on HCL OneTest[™] Server.

4. Identify the Engineering Test Management adapter that you want to delete, and then click the Menu icon a

5. Click Delete.



Note: If any of the test runs are in progress on Engineering Test Management, then those runs are aborted.

6. Click Confirm to delete the Engineering Test Management adapter from the project.

Results

You have deleted the Engineering Test Management adapter from the project on HCL OneTest[™] Server.

Integration with Jenkins

You can use the HCL OneTest[™] Server plugin to integrate HCL OneTest[™] Server with Jenkins. After you complete the integration, you can run tests assets that are available in a project of HCL OneTest[™] Server from a Jenkins server.

You must have installed Jenkins on your computer to install the HCL OneTest[™] Server Jenkins plugin. You can run the following command to start the Jenkins server to support UTF-8 character sets:

java -Dfile.encoding=UTF8 -jar jenkins.war

You can use either the Jenkins **Freestyle** project or the **Pipeline** project to run test assets from Jenkins. With **Freestyle** project, you can create build step from the Jenkins UI to run the test assets. Whereas the **Pipeline** project uses a simple text scripts based on the Groovy programming language. You can define pipeline scripts during the configuration of the **Pipeline** project by using any of the following methods:

- **Pipeline script**: In this method, you can directly enter a script in the field provided within the Jenkins UI or you can select a sample **Pipeline script** from the drop-down list.
- **Pipeline script from SCM**: In this method, you can create a script with a Groovy editor and then commit the script file into the Git repository.

For more information about the Jenkins Pipeline, refer to the Jenkins documentation.

Refer to the following topics to learn more about integrating Jenkins with HCL OneTest[™] Server.

Task flows for running test assets from Jenkins

You can perform certain tasks to run test assets from the Jenkins Freestyle project or the Pipeline project.

The following table lists the task flows for running test assets from the Jenkins Freestyle project:

Tasks	Go to
Install the HCL OneTest™ Server Jenkins plugin.	Installing the HCL OneTest Server Jenkins Plugin on page 656
Import the CA certificate to your custom trust store.	Using a custom trust store on page 657

Tasks	Go to
Configure the Freestyle project.	Configuring the Freestyle project on page 659
Run HCL OneTest™ Server test assets on Jenkins.	Running tests from Jenkins on page 669

You can perform the following tasks to run test assets from the Jenkins Pipeline project by using the sample script:

Tasks	Go to
Install the HCL OneTest™ Server Jenkins plugin.	Installing the HCL OneTest Server Jenkins Plugin on page 656
Import the CA certificate to your custom trust store.	Using a custom trust store on page 657
Create a pipeline script from the Jenkins UI.	Creating a pipeline script from Jenkins on page 663
Configure the Pipeline project.	Configuring the Pipeline project by using the sample script on page 667
Run HCL OneTest™ Server test assets on Jenkins.	Running tests from Jenkins on page 669

You can perform the following tasks to run test assets from the Jenkins **Pipeline** project by using the script from Source Code Management (SCM):

Tasks	Go to
Install the HCL OneTest™ Server Jenkins plugin.	Installing the HCL OneTest Server Jenkins Plugin on page 656
Import the CA certificate to your custom trust store.	Using a custom trust store on page 657
Create a pipeline script and commit the script to the Git repository.	For more information, refer to the Jenkins documenta- tion.
Configure the Pipeline project.	Configuring the Pipeline project by using the script from SCM on page 668
Run HCL OneTest™ Server test assets on Jenkins.	Running tests from Jenkins on page 669

Installing the HCL OneTest[™] Server Jenkins Plugin

You must install the HCL OneTest[™] Server Jenkins plugin on the Jenkins server before you can use the plugin for running tests that are available in your HCL OneTest[™] Server project on the Jenkins server.

Before you begin

You must have completed the following tasks:

- Installed Jenkins on your computer. For more information about installing Jenkins, refer to the Jenkins documentation.
- Downloaded the HCL OneTest[™] Server Jenkins plugin from the HCL License and Delivery portal.

For more information about specific versions of plugin, see Integration plugin compatibility matrix on page 620.

1. Log in to the Jenkins server.

Result

The Jenkins dashboard is displayed.

- 2. Click Manage Jenkins > Manage Plugins.
- 3. Click the Advanced tab.
- 4. Click Choose File from the Upload Plugin section to locate and Open the HCL OneTest[™] Server Jenkins plugin.
- 5. Click Upload.

Result

The HCL OneTest[™] Server Jenkins plugin is displayed in the **Installed** tab.

Results

You have installed the HCL OneTest[™] Server Jenkins plugin on the Jenkins server.

What to do next

You must import the CA certificate to your custom trust store to establish a trusted and secure connection between the Jenkins server and HCL OneTest[™] Server. See Using a custom trust store on page 657.

Using a custom trust store

You must use a custom trust store in the Jenkins build to establish a trusted and secure connection between the Jenkins server and HCL OneTest[™] Server.

Before you begin

You must have completed the following tasks:

• Saved the Certificate Authority (CA) assigned to HCL OneTest[™] Server.



Note: You can contact the administrator of HCL OneTest[™] Server if you do not have a copy of the CA.

• Installed Java on the computer from where you access the HCL OneTest[™] Server UI.

About this task

If the SSL certificate assigned to HCL OneTest[™] Server is signed by an internal CA, then you must download and import the CA to a custom trust store. You can then use the custom trust store in the Jenkins build step to establish a trusted and secure connection between the Jenkins server and HCL OneTest[™] Server.

Note: If the internal CA is already imported to the default trust store that is used by the Jenkins server, you need not use a custom trust store.

Restriction:

When you use Red Hat Enterprise Linux (RHEL) operating systems for Jenkins, you must run the Jenkins service with a user who has access to the custom trust store path to utilize the custom trust store feature. To change the Jenkins user, you must open the /etc/sysconfig/jenkins file and set the JENKINS_USER to the user who has access to the custom trust store path.

You can then run the following commands to set JENKINS_USER to another user who has access to the path of the custom trust store:

\$JENKINS_USER= <username>

For example, \$JENKINS_USER= <user1>



Note: You must ensure that the user account is available in the /etc/passwd file.

You can then run the following commands to change the ownership of the Jenkins folder:

chown -R username:username	/var/lib/jenkins
----------------------------	------------------

chown -R username:username /var/cache/jenkins

chown -R username:username /var/log/jenkins

For example,

chown -R user1:user1 /var/lib/jenkins

chown -R user1:user1 /var/cache/jenkins

chown -R userl:userl /var/log/jenkins

After the change of ownership is complete, you can run the following command to restart the Jenkins server:

/etc/init.d/jenkins restart

1. Locate the default trust store file (cacerts file) from the JRE directory.

For example: C:\Program Files\Java\jdk-18.0.1.1\lib\security

- $\ensuremath{\text{2. Copy the cacerts file to a location of your choice on your computer.}\xspace$
- 3. Place the CA assigned to HCL OneTest[™] Server in the same location where you saved the cacerts file.

 Run the following command from the command-line interface or terminal to import the CA of HCL OneTest[™] Server to custom trust store:

keytool -import -trustcacerts -file {path to the downloaded CA with the file extension} -alias
{label for the certificate} -keystore {path to the trust store cacerts file}

For example,

```
keytool -import -trustcacerts -file C:\Users\Desktop\cert\ca-master-hcl.crt -alias "otsca" -keystore
C:\Users\Desktop\cert\cacerts
```

Note: The default password of the trust store is *changeit*. It remains the same for the custom trust store. If you want to change the password, you can run the following command, and then enter the new password:

keytool -storepasswd -keystore {path to the trust store cacerts file}

For example, keytool -storepasswd -keystore C:\Users\Desktop\cert\cacerts

Results

You have successfully imported the downloaded CA to the custom trust store.

What to do next

You can run test assets either from Freestyle or Pipeline project from the Jenkins server.

Configuring the Freestyle project

You must configure a **Freestyle** project to add a build step, and then run tests that are available in your HCL OneTest[™] Server project from Jenkins.

Before you begin

You must have completed the following tasks:

- Installed the HCL OneTest[™] Server Jenkins plugin on the Jenkins server. See Installing the HCL OneTest Server Jenkins Plugin on page 656.
- Created a Jenkins Freestyle project.
- Generated an offline user token from HCL OneTest[™] Server. See Managing access to HCL OneTest Server on page 708.
- 1. Open your Jenkins Freestyle project from the list, and then click Configure.
- 2. Click the Build tab, and then click Add build step.
- 3. Select the Run HCL OneTest Server test option from the drop-down list.
- 4. Provide the details about the test run for the fields in the following table:

The following table lists the required fields that you must provide to run the test from Jenkins:

Fields	Action
Name	Enter a name for the Jenkins build step.
Server URL	Enter the URL of HCL OneTest [™] Server. The format of the URL is as follows: <i>https://hostname</i> .
Offline Token	Enter the offline user token that you generated from HCL OneTest [™] Server.

The following table lists the optional fields that you can provide to run the test from Jenkins:

Fields	Descriptions
Asset Type	Use this field to select the test asset type that you want to run from the Asset Type drop-down list.
Branch	Use this field to select the branch of the Git repository from the drop-down list. The Branch drop-down list displays the branches that are available in the corresponding project of HCL OneTest [™] Server.
	Note: After you select the branch from the Branch drop-down list, if you want to change the URL of HCL OneTest [™] Server, offline user token, or the project in the Build step, then you must close the build step. Then you must click Add build step , select Run HCL OneTest Server test , and then enter the details.
Datasets	Use this field to enter the path to the dataset if you want to replace the values of the dataset during a test run.
	You must ensure that both original and new datasets are in the same workspace and have the same column names. When you enter a value for the Datasets field, you must also include the path to the dataset. The path must be in the following format:
	/project_name/ds_path/original_ds.csv:/project_name/ds_path/new_ds.csv
	Note: You can override multiple datasets that are saved in a different project by adding multiple paths to the dataset separated by a semicolon.
Labels	Use this field to add labels to test results when the test run is complete.

Fields	Descriptions
	You can add multiple labels to a test result separated by a comma.
	For example, <i>label1, label2</i>
	After the test run is complete, then the values provided in the Labels field are displayed on the Results page of HCL OneTest [™] Server.
Project	Use this field to select a project from the drop-down list.
	The Project drop-down list displays the projects that are available in the corresponding team space of HCL OneTest [™] Server.
	Note: The Project drop-down list displays the projects where you are an Owner or a member of HCL OneTest [™] Server. You must be an Owner or a Tester of the project that is available in the team spaces to run the tests from the Jenkins server.
Secrets Collection	Use this field to select the Secret from the Secrets Collection drop-down list if you created se- crets collections for your project to use Secrets at test run time.
	The Secrets collection field is mandatory only if you select one of the following options in the Asset Type field: • APISUITE • APITEST • APISTUB • POSTMAN
	The following message is displayed when you select any other asset type than preceding list: You can select Secrets collection only if you are running tests of type APISUITE, APITEST, APISTUB, or POSTMAN.
Team Space	Use this field to select the name of the team space from the drop-down list.
	The Team Space drop-down list displays the names of the team spaces if you are an <i>Owner</i> or a <i>member</i> of the team space.
Test	Use this field to select the required test that you want to run from the drop-down list.
	The Tests drop-down list displays the available test assets from the corresponding branch in the following format:

Fields	Descriptions
	Project_name [Path: the path of the test assets] [Repo: URL of the Git repository that the test belongs to]
	Note: After you select the test details from the Tests drop-down list if you want to change the URL of HCL OneTest [™] Server, offline user token, or the project in the Jenkins Build step , then you must delete the build step and add a new build step.
Test Envi- ronment	Use this field to select an environment from the drop-down list.
	The Test Environment field displays the available test environments from HCL OneTest [™] Server.
	The Test Environment field is mandatory only if you select one of the following options in the Asset Type field:
	 APISUITE APITEST
	∘ POSTMAN
	The following message is displayed when you select any other asset type than preceding list:
	You can select Test Environment only if you are running tests of type APISUITE, APITEST, APISTUB, or POSTMAN.
Use Cus- tom Trust Store	Select this checkbox if you used an internal CA certificate and imported the certificate to the custom trust store. You can then enter the file path of your trust store followed by the file name in the Custom Trust Store Path field.
	Select the Use Custom Password for the Trust Store checkbox if you modified the trust store password, and then enter the new password in the Custom Trust Store Password field.
	Note: If you did not modify the trust store password, you must clear the Use Custom Password for the Trust Store checkbox.
Variables	Use this field to enter the name of the variable and its value if your test requires variables during the test run time.
	You must enter the variables in the following format:
	name_of_the_variable=value_of_the_varibale
	You can add multiple variables to the test run separated by a semicolon.

Fields	Descriptions
	For example, varname1=value1;varname2=value2

Note: You can run multiple tests sequentially in the same job by adding multiple build steps and providing details for the tests that you want to run.

5. Click **Save** to save the build step.

Results

You have configured the Freestyle project by adding the build step.

What to do next

You can run test assets from the Jenkins server. See Running tests from Jenkins on page 669.

Creating a pipeline script from Jenkins

You must create a pipeline script to run test assets that are available in the HCL OneTest[™] Server project from the Jenkins **Pipeline** project.

Before you begin

You must have completed the following tasks:

- Installed the HCL OneTest[™] Server Jenkins plugin on the Jenkins server. See Installing the HCL OneTest Server Jenkins Plugin on page 656.
- Generated an offline user token from HCL OneTest[™] Server. See Managing access to HCL OneTest Server on page 708.
- Created a Jenkins **Pipeline** project.
- 1. Open your Jenkins Pipeline project from the list.
- 2. Click Configure, and then select the Pipeline tab.
- 3. Click Pipeline Syntax to generate a pipeline script.
- 4. Select the step: General Build Step option from the drop-down list in the Sample Step field.
- 5. Select the Run HCL OneTest Server test option from the drop-down list in the Build Step field.
- 6. Provide the details about the test run for the fields in the following table:

The following table lists the required fields that you must provide to run the test from Jenkins:

Fields	Action
Name	Enter a name for the Jenkins build step.

Fields	Action
Server URL	Enter the URL of HCL OneTest [™] Server. The format of the URL is as follows: <i>https://hostname</i> .
Offline To- ken	Enter the offline user token that you generated from HCL OneTest™ Server.

Field	Description	
Asset Type	Use this field to select the test asset type that you want to run from the Asset Type drop-down list.	
Branch	Select the branch from the drop-down list.	
	The Branch drop-down list displays the branches that are available in the corresponding project of HCL OneTest [™] Server.	
Datasets	Use this field to enter the path to the dataset if you want to replace the values of the dataset during a test run.	
	You must ensure that both original and new datasets are in the same workspace and have the same column names. When you enter a value for the Datasets field, you must also include the path to the dataset. The path must be in the following format:	
	/project_name/ds_path/original_ds.csv:/project_name/ds_path/new_ds.csv	
	Note: You can override multiple datasets that are saved in a different project by adding multiple paths to the dataset separated by a semicolon.	
Labels	Use this field to add labels to test results when the test run is complete.	
	You can add multiple labels to a test result separated by a comma.	
	For example, <i>label1, label2</i>	
	After the test run is complete, then the values provided in the Labels field are displayed on the Results page of HCL OneTest [™] Server.	
Project	Use this field to select a project from the drop-down list.	

Field	Description
	The Project drop-down list displays the projects that are available in the corresponding team
	space of HCL OneTest™ Server.
	Note: The Project drop-down list displays the projects where you are an Owner or a
	member of HCL OneTest [™] Server. You must be an <i>Owner</i> or a <i>Tester</i> of the project that
	is available in the team spaces to run the tests from the Jenkins server.
Secrets	Use this field to select the Secret from the Secrets Collection drop-down list if you created se-
Collection	
	crets collections for your project to use Secrets at test run time.
	The Secrets collection field is mandatory only if you select one of the following options in the
	Asset Type field:
	• APISUITE
	• APITEST
	○ APISTUB
	• POSTMAN
	The following message is displayed when you select any other asset type than preceding list:
	You can select Secrets collection only if you are running tests of type APISUITE, APITEST,
	APISTUB, or POSTMAN.
Team Space	Use this field to select the name of the team space from the drop-down list.
	The Team Space drop-down list displays the names of the team spaces if you are an <i>Owner</i> or a <i>member</i> of the team space.
Test	Use this field to select the required test that you want to run from the drop-down list.
	The Tests drop-down list displays the available test assets from the corresponding branch in
	the following format:
	Project_name [Path: the path of the test assets] [Repo: URL of the Git repository that the
	test belongs to]
	Note: After you select the test details from the Tests drop-down list if you want to
	change the URL of HCL OneTest™ Server, offline user token, or the project in the Jenkins
	Build step, then you must delete the build step and add a new build step.
Test Envi-	Use this field to select an environment from the drop-down list.
ronment	

Field	Description
	The Test Environment field displays the available test environments from HCL OneTest [™] Server.
	The Test Environment field is mandatory only if you select one of the following options in the
	Asset Type field:
	∘ APISUITE ∘ APITEST
	• APISTUB
	• POSTMAN
	The following message is displayed when you select any other asset type than preceding list:
	You can select Test Environment only if you are running tests of type APISUITE, APITEST, APISTUB, or POSTMAN.
Use Cus- tom Trust Store	Select this checkbox if you used an internal CA certificate and imported the certificate to the custom trust store. You can then enter the file path of your trust store followed by the file name in the Custom Trust Store Path field.
	Select the Use Custom Password for the Trust Store checkbox if you modified the trust store password, and then enter the new password in the Custom Trust Store Password field.
	Note: If you did not modify the trust store password, you must clear the Use Custom Password for the Trust Store checkbox.
Variables	Use this field to enter the name of the variable and its value if your test requires variables during the test run time.
	You must enter the variables in the following format:
	name_of_the_variable=value_of_the_varibale
	You can add multiple variables to the test run separated by a semicolon.
	For example, varname1=value1;varname2=value2

7. Click **Generate Pipeline Script** and copy the script that you created for the build step to use it in the sample script.

Results

You have created the pipeline script.

What to do next

You can configure the **Pipeline** project by using the **Pipeline script** option. See Configuring the Pipeline project by using the sample script on page 667.

Configuring the Pipeline project by using the sample script

You can configure a **Pipeline** project directly from the Jenkins UI by using the sample pipeline scripts to run test assets from Jenkins.

Before you begin

You must have completed the following tasks:

- Installed the HCL OneTest[™] Server Jenkins plugin on the Jenkins server. See Installing the HCL OneTest Server Jenkins Plugin on page 656.
- Created a pipeline script. See Creating a pipeline script from Jenkins on page 663.
- 1. Open your Jenkins Pipeline project from the list.
- 2. Click **Configure**, and then select the **Pipeline** tab.
- 3. Select the Pipeline script option in the Definition field.
- 4. Select the sample script from the drop-down list.

For example, if you select Hello Word from the drop-down list, then the sample script is displayed as follows:



5. Specify the script that you created in place of "echo 'Hello Word'".

1	pipeline s	script	~
ł	Script		0
	1 * 2 3 4 * 5 5 * 6 * 7 7 8 9 9 10 11 12		try sample Pipeline 🗸
1			



Note: You can provide a different name for the stage in the script.

Results

You have configured the Pipeline project by using the Pipeline script option.

What to do next

You can run test assets from the Jenkins server. See Running tests from Jenkins on page 669.

Configuring the Pipeline project by using the script from SCM

You can configure the **Pipeline** project to use the pipeline script from the Source Code Management (SCM), and then run test assets that are available in the HCL OneTest[™] Server project from the Jenkins **Pipeline** project.

Before you begin

You must have completed the following tasks:

- Installed the HCL OneTest[™] Server Jenkins plugin on the Jenkins server. See Installing the HCL OneTest Server Jenkins Plugin on page 656.
- Created a pipeline script and committed the script to the Git repository. For more information, refer to the Jenkins documentation.
- Been granted administrator permission of the Jenkins server to add credentials into Jenkins.
- Added your GitHub credentials into Jenkins. For more information about adding global credentials, refer to the Jenkins documentation.
- Created a Jenkins Pipeline project.

About this task

If your pipeline scripts are complex, you can then write the script outside of Jenkins UI. You must commit that script file into your Git repository. During the **Pipeline** build process, Jenkins checks out the script file from the Git repository and runs your **Pipeline** project.

- 1. Open your Jenkins **Pipeline** project from the list.
- 2. Click **Configure**, and then select the **Pipeline** tab.
- 3. Select the Pipeline script from SCM option in the Definition field.
- 4. Select the Git option from the drop-down list in the SCM field.
- 5. Enter the URL of the Git repository in the Repository URL field where you stored your pipeline script.
- 6. Select the credentials of the Git repository from the drop-down list.
- 7. **Optional:** Enter the branch name of the Git repository in the **Branch Specifier** field.
- 8. Enter the path of the script that you stored in the Git repository in the Script path field.
- 9. Click Save.

Results

You have configured the Pipeline project by using the Pipeline script from the SCM option.

What to do next

You can run test assets from the Jenkins server. See Running tests from Jenkins on page 669.

Running tests from Jenkins

You can run test assets either from the Jenkins **Freestyle** or the **Pipeline** project on the Jenkins server to test an application under test.

Before you begin

You must have completed the following tasks:

- Configured the **Freestyle** project, if you want to run test assets from the **Freestyle** project. See Configuring the Freestyle project on page 659.
- Configured the **Pipeline** project either by using the **Pipeline script** or **Pipeline script from SCM**, if you want to run test assets from the **Pipeline script** project. See Configuring the Pipeline project by using the sample script on page 667 or Configuring the Pipeline project by using the script from SCM on page 668.
- Downloaded the latest **Test Results Analyzer** plugin from the Jenkinsci repository. For more information about the **Test Results Analyzer** plugin, refer to the Jenkins documentation.
- Installed the **Test Results Analyzer** plugin on the Jenkins server. For more information about installing the plugin, refer to the Jenkins documentation.

About this task

After the test run is complete, you can view the test results in a tabular format when you use the Jenkins **Test Results Analyzer** plugin. With a TRA-based report, you can filter the results based on the status of the build. The status of the builds can be PASSED, FAILED, and SKIPPED. You can also identify the failed build from the TRA-based report and take the required action to resolve the build errors. The TRA report also represents the build information in **Line**, **Bar**, and **Pie** graphs so that you can easily read the data. 1. Log in to the Jenkins server.

Result

The Jenkins dashboard is displayed.

- 2. Open your Jenkins Freestyle or Pipeline project from the list.
- 3. Click **Build Now** to run the test assets from Jenkins.

Results

You have run the test from the Jenkins server.

What to do next

You can view the build logs by clicking the build number from the **Build History** pane, and then selecting the **Console Output** option. You can also view the history of test results in a tabular format by clicking the **Test Results Analyzer** option.

You can access the report URLs to view the test run information at any point in time. You can also view the test reports and logs of the test that was run on the Jenkins server from the **Results** page on HCL OneTest[™] Server. See Test results and reports on page 514.

Integration with UrbanCode[™] Deploy

You can integrate HCL OneTest[™] Server with IBM® UrbanCode[™] Deploy to run test assets as a **Process** from UrbanCode[™] Deploy.

When you use UrbanCode[™] Deploy for automating the deployments of your applications to an environment during the development cycle, you can create test assets for your application either in HCL OneTest[™] Server or desktop clients. After you configure the project in HCL OneTest[™] Server, you can then run those tests assets from UrbanCode[™] Deploy.

You must use the HCL OneTest[™] Server UCD plugin to integrate HCL OneTest[™] Server with UrbanCode[™] Deploy. Integrating HCL OneTest[™] Server with UrbanCode[™] Deploy automates the process of test runs. If you have many tests to run at regular intervals, you can use UrbanCode[™] Deploy to initiate test runs automatically.

The following table lists the tasks that you must perform to run performance test assets from UrbanCode[™] Deploy:

Tasks	Go to
Create any or all the following types of test assets either in HCL OneTest [™] Server or desktop clients to test your application: • API test assets • Functional test assets • Performance test assets	 HCL OneTest[™] API Documentation HCL OneTest[™] Performance Documentation HCL OneTest[™] UI Documentation Test authoring on page 130 in HCL OneTest[™] Server

Tasks	Go to
Create a project, and then configure the repository in HCL OneTest™ Server.	Working with projects in a team space on page 724
Install UrbanCode™ Deploy with at least one agent.	IBM UrbanCode [™] Deploy documentation.
	System Requirements on page 17 for information about specific versions of UrbanCode™ Deploy requirements.
Install the HCL OneTest [™] Server UCD plugin on Urban- Code [™] Deploy.	Installing the plugin on UrbanCode Deploy on page 671.
Create a Component in UrbanCode [™] Deploy.	Creating a component in UrbanCode Deploy on page 673.
Create a Process for the component in UrbanCode [™] Deploy.	Creating a process in UrbanCode Deploy on page 674.
Configure the Process that you created for the compo- nent in UrbanCode [™] Deploy.	Configuring the process on page 675.
Create a Resource in UrbanCode™ Deploy.	Creating a resource in UrbanCode Deploy on page 680.
Configure the Resource .	Configuring the resource on page 681.
Create an Application in UrbanCode [™] Deploy.	Creating an application in UrbanCode Deploy on page 682.
Configure the Application that you want to use to run test assets from UrbanCode™ Deploy.	Configuring the application on page 683.
Run the test assets from UrbanCode™ Deploy.	Running tests from UrbanCode Deploy on page 685.

Installing the plugin on UrbanCode[™] Deploy

You must install the HCL OneTest[™] Server UCD plugin to run test assets from UrbanCode[™] Deploy.

Before you begin

- You must be familiar with working with UrbanCode[™] Deploy.
- You must have performed the following tasks:
 - Installed UrbanCode[™] Deploy. For more information about the installation, refer to the IBM Urban Code documentation.
 - ∘ Been granted access to UrbanCode[™] Deploy.

• Downloaded the HCL OneTest[™] Server UCD plugin from the HCL® License & Delivery portal.

For more information about specific versions of plugin, see Integration plugin compatibility matrix on page 620.

1. Log in to UrbanCode[™] Deploy, if you are not already logged in.

Result

The UrbanCode[™] Deploy dashboard is displayed.

- 2. Click Settings.
- 3. Click Automation Plugins from the Automation pane.
- 4. Click Load Plugin.
- 5. Click Choose File to locate and open the compressed HCL OneTest[™] Server UCD plugin file.

Remember: You must not extract the HCL OneTest[™] Server UCD plugin compressed file contents.

6. Click Submit.

Result

The installed plugin is displayed on the Automation Plugins tab.

Results

You have installed the HCL OneTest[™] Server UCD plugin on UrbanCode[™] Deploy.

What to do next

You must create a **Component** in UrbanCode[™] Deploy. See Creating a component in UrbanCode Deploy on page 673.

Using a custom trust store

You can use a custom trust store in the HCL OneTest[™] Server UCD plugin file to establish a trusted and secure connection between the UCD server and HCL OneTest[™] Server.

Before you begin

You must have completed the following tasks:

• Saved the Certificate Authority (CA) assigned to HCL OneTest[™] Server.



Note: You can contact the administrator of HCL OneTest[™] Server if you do not have a copy of the CA.

• Installed Java on the computer from where you access the HCL OneTest[™] Server UI.

About this task

If the SSL certificate assigned to HCL OneTest[™] Server is signed by an internal Certified Authority (CA), then you must download and import the CA certificate to a custom trust store. You can then use the custom trust store in the **HCL OneTest[™] Server test** process step to establish a trusted and secure connection between the UCD server and HCL OneTest[™] Server.

Note: If the internal CA certificate is already imported to the default trust store that is used by the UCD server, you need not use a custom trust store.

- Locate the default trust store file (cacerts file) from the JRE directory.
 For example: C:\Program Files\Java\jdk-18.0.1.1\lib\security
- 2. Copy the cacerts file to a location of your choice on your computer.
- 3. Place the CA assigned to HCL OneTest[™] Server in the same location where you saved the cacerts file.
- 4. Run the following command from the command-line interface or terminal to import the CA of HCL OneTest[™] Server to custom trust store:

keytool -import -trustcacerts -file {path to the downloaded CA with the file extension} -alias
{label for the certificate} -keystore {path to the trust store cacerts file}

For example,

keytool -import -trustcacerts -file C:\Users\Desktop\cert\ca-master-hcl.crt -alias "otsca" -keystore C:\Users\Desktop\cert\cacerts



Note: The default password of the trust store is *changeit*. It remains the same for the custom trust store. If you want to change the password, you can run the following command, and then enter the new password:

keytool -storepasswd -keystore {path to the trust store cacerts file}

For example, keytool -storepasswd -keystore C:\Users\Desktop\cert\cacerts

Results

You have successfully imported the downloaded CA to the custom trust store.

What to do next

You can then run the tests that are available in your HCL OneTest™ Server project from the UCD server.

Creating a component in UrbanCode[™] Deploy

You must create a component to include artifacts and processes. The artifacts include runnable files, images, databases, configuration instructions. Whereas the processes define the activities that components can perform.

Before you begin

- You must be familiar with working with UrbanCode[™] Deploy.
- You must have been granted access to UrbanCode[™] Deploy.
- 1. Log in to UrbanCode[™] Deploy, if you are not already logged in.

Result

The UrbanCode[™] Deploy dashboard is displayed.

- 2. Click Components, and then click Create Component.
- 3. Enter a name for the component in the Name field.
- 4. Enter the details in the other optional fields based on your requirement, and then click Save.

Result

The component that you created is displayed.

Results

You have created the component in UrbanCode[™] Deploy.

What to do next

You must create a process for the component in UrbanCode[™] Deploy. See Creating a process in UrbanCode Deploy on page 674.

Related information

IBM UrbanCode Deploy Documentation

Creating a process in UrbanCode[™] Deploy

You must create a process for the component to include step properties for the test that you want to run from UrbanCode[™] Deploy.

Before you begin

- You must be familiar with working with UrbanCode[™] Deploy.
- You must have performed the following tasks:
 - Been granted access to UrbanCode[™] Deploy.
 - Created a component in UrbanCode[™] Deploy. See Creating a component in UrbanCode Deploy on page 673.
- 1. Log in to UrbanCode[™] Deploy, if you are not already logged in.

Result

The UrbanCode[™] Deploy dashboard is displayed.

2. Click Components.

Result

A list of components that are available in UrbanCode[™] Deploy is displayed.

- 3. Select the component from the list for which you want to create a process.
- 4. Click the Processes tab, and then click Create Process.

Result

The Create Process dialog is displayed.

- 5. Enter a name for the process in the Name field.
- 6. Select Operational (No Version Needed) from Process Type drop-down list.
- 7. Verify the Default Working Directory field.

The **Default Working Directory** field defines the location that the agent uses to run the process. The default value is $f_{p:resource/work.dir}/$ \${p:component.name}.

Where $f_{p:resource/work.dir}$ is the default working directory for the agent and $f_{p:component.name}$ is the name of the component.

8. Click Save.

Result

The process that you created is listed in the **Processes** tab and the **Design** tab for the process is displayed.

Results

You have created the process for the component in UrbanCode[™] Deploy.

What to do next

You must configure the process in UrbanCode[™] Deploy. See Configuring the process on page 675.

Related information

IBM UrbanCode Deploy Documentation

Configuring the process

You must configure the process that you created for the component to organize the steps in the process, specify the properties of the steps, and connect them.

Before you begin

- You must be familiar with working with UrbanCode™ Deploy.
- · You must have performed the following tasks:
 - Been granted access to UrbanCode[™] Deploy.
 - Created a component in UrbanCode[™] Deploy. See Creating a component in UrbanCode Deploy on page 673.
 - Created a process for the component in UrbanCode[™] Deploy. See Creating a process in UrbanCode Deploy on page 674.

- Generated an offline user token from HCL OneTest[™] Server. See Generating an offline token on page 708.
- ∘ Added the tests assets to the project on HCL OneTest[™] Server.

About this task

When you open any process to configure, the process is displayed in the process editor. The process editor lists the plugins and steps. The required **Start** and **Finish** steps represent the beginning and the end of the process and steps are automatically placed on the design area.

1. Log in to UrbanCode[™] Deploy, if you are not already logged in.

Result

The UrbanCode[™] Deploy dashboard is displayed.

2. Click Components.

Result

A list of components that are available in UrbanCode™ Deploy is displayed.

- 3. Select the component from the list in which you created the process.
- 4. Click the Processes tab.

Result

A list of processes that are available for the component is displayed.

5. Select the process from the list that you want to configure.

Result

The **Design** tab for the process is displayed.

- 6. Click HCL OneTest Studio, and then HCL OneTest Server from the left menu.
- 7. Drag the **Run HCL OneTest[™] Servertest** step, and then drop it into the design area.



Note: The selected test must be placed between Start and Finish steps.

- 8. Specify the properties for the selected test by performing the following steps:
 - a. Click the **Edit** icon.
 - Result

The Edit Properties for Run HCL OneTest Server test dialog is displayed.

b. Specify the properties for the selected test step by referring to the following tables:

The following table lists the required fields that you must provide to run the test from UrbanCode[™] Deploy:

Fields	Action
Name	Enter the name for the test step.

Fields	Action
HCL OneTest Server URL	Enter the URL of HCL OneTest™ Server.
Offline Token	Enter the offline token that you generated from HCL OneTest™ Server.
Team Space Name	Enter the name of the team space that contains the project.
	Note: The license for the team space must be configured and you must be a member of that team space.
Project Name	Enter the name of the project that are available in the team space.
Repository Link	Enter the URL of the Git repository that you added to your project in HCL OneTest™ Server.
File Path	Enter the path of the test assets that you want to run.
	You can find the path of the test assets from the Execution page in HCL OneTest [™] Server

The following table lists the optional fields that you can provide to run the test from UrbanCode[™] Deploy:

Fields	Description
Branch Name	Use this field to enter the name of the branch in the Git repository where you stored test assets.
Custom Trust	Use this field to enter the trust store password if you have modified the password while creating the custom trust store.

Fields	Description
Store Pass- word	Note: If you have not modified the trust store password, you can retain the Cus- tom Trust Store Password field blank.
Custom Trust Store Path	Use this field to enter the file path of your trust store followed by the file name if HCL OneTest [™] Server uses an internal CA certificate and you have imported the certificate to a custom trust store.
Datasets	Use this field to enter the path to the dataset if you want to replace the values of the dataset during a test run.
	You must ensure that both original and new datasets are in the same workspace and have the same column names. When you enter a value for the Datasets field, you must also include the path to the dataset. The path must be in the following format:
	<pre>/project_name/ds_path/original_ds.csv:/project_name/ds_path/new ds.csv</pre>
	Note : You can override multiple datasets that are saved in a different project by adding multiple paths to the dataset separated by a semicolon.
Environ- ment	Use this field to enter the environment details for the following types of test assets: • APISUITE • APITEST • APISTUB
Labels	Use this field to add labels to test results when the test run is complete.
	You can add multiple labels to a test result separated by a comma. For example, <i>label1, label2</i>
	After the test run is complete, then the values provided in the Labels field are displayed on the Results page of HCL OneTest [™] Server.
Secrets Col- lection	Use this field to enter the name of the Secret if you created secrets collections for your project and to use Secrets at test run time.
Name	This field is mandatory only if you want to run the following types of test assets:

Fields	Description
	APISUITE APITEST APISTUB
Show Hidden Proper-	Select this checkbox if you want to use an HTTP Proxy to connect to HCL OneTest™ Serv- er.
ties	After you select the Show Hidden Properties checkbox, you can configure the HTTP Proxy by using the following fields:
	• HTTP Proxy Host: Use this field to enter the hostname of the HTTP proxy that you want to connect to HCL OneTest [™] Server.
	 HTTP Proxy Port: Use this field to enter the port number where the HTTP proxy is used to listen to both HTTP and HTTPS traffic.
	 HTTP Proxy User name: Use this field to provide the username for the HTTP proxy.
	 HTTP Proxy Password: Use this field to enter a valid password for the user that you specified in the HTTP Proxy User name field.
	 Note: You can use the Show Hidden Properties field only when you want to run the following types of test assets: APISUITE APITEST
	• APISTUB
Variables	Use this field to enter the name of the variable and its value if your test requires variables during the test run time.
	You must enter the variables in the following format:
	name_of_the_variable=value_of_the_varibale
	You can add multiple variables to the test run separated by a semicolon.
	For example, varname1=value1;varname2=value2

Note: In addition to optional fields, you can also use the following fields from UrbanCode[™] Deploy to configure your test run:



- Working Directory
- Precondition
- Post Processing Script
- Use Impersonation
- Auth Token Restriction

You can accept the default values or change the values based on your requirements. For more information about these fields, see the related links.

c. Click **OK** to save the properties for the test.

9. Click **Save** in the design area.

Results

You have configured the process for the component in UrbanCode[™] Deploy.

What to do next

You must create a resource in UrbanCode[™] Deploy. See Creating a resource in UrbanCode Deploy on page 680.

Related information

IBM UrbanCode Deploy Documentation Process step preconditions Post-processing scripts User impersonation for process steps Restricting authentication tokens

Creating a resource in UrbanCode[™] Deploy

You must create a resource to associate agents with components that you created in UrbanCode™ Deploy.

Before you begin

- You must be familiar with working with UrbanCode[™] Deploy.
- You must have been granted access to UrbanCode[™] Deploy.
- 1. Log in to UrbanCode[™] Deploy, if you are not already logged in.

Result

The UrbanCode[™] Deploy dashboard is displayed.

2. Click Resources, and then click Create Top-Level Group. Result

The Create Resource dialog is displayed.

- 3. Enter a name for the resource in the **Name** field.
- 4. Click Save.

Results

You have created the resource in UrbanCode[™] Deploy.

What to do next

You must configure the resource. See Configuring the resource on page 681.

Related information

IBM UrbanCode Deploy Documentation

Configuring the resource

You must configure the resource to add an agent and associate the agent with the component.

Before you begin

- You must be familiar with working with UrbanCode[™] Deploy.
- You must have performed the following tasks:
 - Been granted access to UrbanCode[™] Deploy.
 - Created a component in UrbanCode[™] Deploy. See Creating a component in UrbanCode Deploy on page 673.
 - Created a resource in UrbanCode[™] Deploy. See Creating a resource in UrbanCode Deploy on page 680.
- 1. Log in to UrbanCode[™] Deploy, if you are not already logged in.

Result

The UrbanCode[™] Deploy dashboard is displayed.

2. Click Resources.

Result

A list of resources that are available in UrbanCode[™] Deploy is displayed.

- 3. Perform the following steps to add an agent to the resource:
 - a. Click the resource from the list for which you want to add an agent.
 - b. Click the Actions icon from the last column, and then click Add Agent.
 - c. Select the agent from the drop-down list.

Note: The Name field is auto populated with the name of the agent.

d. Click Save.

Result

The selected agent is added to the resource and you can view the status of the agent in the **Status** column.

- 4. Perform the following steps to add a component to the agent:
 - a. Click the agent from the list for which you want to add a component.
 - b. Click the Actions icon from the last column, and then click Add Component.
 - c. Select the component from the drop-down list.

Note: The Name field is auto populated with the name of the component.

d. Click Save.

Result

The selected component is added to the agent.

Results

You have configured the resource in UrbanCode[™] Deploy.

What to do next

You must create an application. See Creating an application in UrbanCode Deploy on page 682.

Related information

IBM UrbanCode Deploy Documentation

Creating an application in UrbanCode[™] Deploy

You must create an application to fetch all the components together that you want to deploy.

Before you begin

- You must be familiar with working with UrbanCode[™] Deploy.
- You must have been granted access to UrbanCode[™] Deploy.
- 1. Log in to UrbanCode[™] Deploy, if you are not already logged in.

Result

The UrbanCode[™] Deploy dashboard is displayed.

2. Click Applications.

- 3. Click Create Applications, and then New Applications.
- 4. Enter a name for the application in the Name field.

Result

The Environments page for the application that you created is displayed.

Results

You have created the application in UrbanCode[™] Deploy.

What to do next

You must configure the application. See Configuring the application on page 683.

Related information

IBM UrbanCode Deploy Documentation

Configuring the application

You must configure the application to associate resources with environments and define processes to run test assets.

Before you begin

- You must be familiar with working with UrbanCode[™] Deploy.
- You must have performed the following tasks:
 - Been granted access to UrbanCode[™] Deploy.
 - Created a component in UrbanCode[™] Deploy. See Creating a component in UrbanCode Deploy on page 673.
 - Created a process for the component in UrbanCode[™] Deploy. See Creating a process in UrbanCode Deploy on page 674.
 - Configure the process for the component in UrbanCode[™] Deploy. See Configuring the process on page 675.
 - Created a resource in UrbanCode[™] Deploy. See Creating a resource in UrbanCode Deploy on page 680.
 - ∘ Configured the resource in UrbanCode[™] Deploy. See Configuring the resource on page 681.
 - Created an application in UrbanCode[™] Deploy. See Creating an application in UrbanCode Deploy on page 682.
- Log in to UrbanCode[™] Deploy, if you are not already logged in. Result

The UrbanCode[™] Deploy dashboard is displayed.

2. Click Applications.

Result

A list of applications that are available in UrbanCode[™] Deploy is displayed.

3. Click the application that you want to configure from the Name column.

Result

The **Environments** page for the selected application is displayed.

- 4. Perform the following steps to create an environment for the application that you selected:
 - a. Click Create Environment.
 - b. Enter a name for the environment in the Name field.
 - c. Click Save.
- 5. Perform the following steps to configure resources to the environment:
 - a. Click the environment that you created.
 - b. Click Add Base Resources.

Result

A list of resources that are available in UrbanCode[™] Deploy is displayed.

c. Select the checkbox to add resources to the environment.

d. Click Save.

Result

You can view the corresponding agent and the component that you added for the resource by using the **Expand** icon.

- 6. Perform the following steps to add the component to the application:
 - a. Click Applications, and then select your application from the list.
 - b. Click the Components tab, and then Add Components.
 - c. Select the checkbox from the drop-down list to add components to the application.
 - d. Click Save.
- 7. Perform the following steps to create a process for the application:
 - a. Click the Processes tab, and then Create Process.
 - b. Enter a name for the process in the Name field.
 - c. Click Save.

Result

The **Design** tab for the process that you created is displayed.

- 8. Drag the component process listed under the **Component Process Steps** option from the left navigation pane and drop it into the design area.
- 9. Select the component process from the drop-down list in the Operational (No Version Needed) Process field.
- 10. Click Save.

- 11. Click the Edit icon, and then change the name of the properties.
- 12. Click OK, and then click Save.

Results

You have configured the application to run test assets from UrbanCode™ Deploy.

What to do next

You can run test assets from UrbanCode[™] Deploy. See Running tests from UrbanCode Deploy on page 685.

Related information

IBM UrbanCode Deploy Documentation

Running tests from UrbanCode[™] Deploy

You can run test assets from UrbanCode™ Deploy as a Process to test your application under test.

Before you begin

- You must be familiar with working with UrbanCode[™] Deploy.
- · You must have performed the following tasks:
 - Been granted access to UrbanCode[™] Deploy.
 - Created a component in UrbanCode[™] Deploy. See Creating a component in UrbanCode Deploy on page 673.
 - Created a process for the component in UrbanCode[™] Deploy. See Creating a process in UrbanCode Deploy on page 674.
 - Configure the process for the component in UrbanCode[™] Deploy. See Configuring the process on page 675.
 - Created a resource in UrbanCode[™] Deploy. See Creating a resource in UrbanCode Deploy on page 680.
 - ∘ Configured the resource in UrbanCode[™] Deploy. See Configuring the resource on page 681.
 - Created an application in UrbanCode[™] Deploy. See Creating an application in UrbanCode Deploy on page 682.
 - ∘ Configured the application in UrbanCode[™] Deploy. See Configuring the application on page 683.
 - Started the UrbanCode[™] Deploy agent. For more information, refer to the IBM UrbanCode Deployment documentation.

1. Log in to UrbanCode[™] Deploy, if you are not already logged in.

Result

The UrbanCode[™] Deploy dashboard is displayed.

2. Click Applications.

Result

A list of applications that are available in UrbanCode[™] Deploy is displayed.

- 3. Click the application that you configured for the test run.
- 4. Click the Request Process icon.

Result

The Run Application Process page is displayed.

- Select the process that you created for the application which contains the test assets from the Process dropdown list.
- 6. Click Submit.

Result

The UrbanCode[™] Deploy dashboard shows the progress of the process request.

Results

You have run the performance test assets as **Process** from UrbanCode[™] Deploy.

What to do next

After the process completes, you can view the status of the process displayed as follows:

- Success: When the test run is successful
- Failed: When the test run is failed

You can view the details of the test run in the **Execution Log** section. The **Reports information** section on the Log file displays the names of the report along with its corresponding URLs.

Integration with other applications

You can integrate certain applications with HCL® OneTest[™] Data to generate the test data.

You can find instructions to integrate other applications with HCL® OneTest[™] Data.

Generating the test data by using Jenkins


When you perform a test during the continuous integration and continuous deployment process on Jenkins, you might want to generate the test data. You can generate random test data to test your application by integrating Jenkins with HCL® OneTest[™] Data by using the **HCL OneTest Data Jenkins Plugin**.

Before you begin

You must have completed the following tasks:

- Installed the latest version of Jenkins.
- You must have an account in the Jenkins application.

- Downloaded the latest version of HCL OneTest Data Jenkins Plugin from the HCL License & Delivery portal.
- Installed HCL OneTest Data Jenkins Plugin in Jenkins.



- Logged in to HCL OneTest[™] Server.
- Created a project and a schema in HCL® OneTest[™] Data.
- Established a connection between HCL® OneTest™ Data and a supported database. See
 - Establishing a JDBC connection with HCL OneTest Data on page 197
 - Establishing a MongoDB connection with HCL OneTest Data on page 209

About this task

You can write the test data generated by integrating Jenkins with HCL® OneTest[™] Data into a file or any supported database. After integration with Jenkins, **HCL OneTest Data Jenkins Plugin** supports the insertion of the generated test data in both JDBC supported database and MongoDB. To write the generated test data in the database, you must establish a connection between HCL® OneTest[™] Data and the supported database.

- 1. Log in to the Jenkins application.
- 2. Create a Jenkins free-style software project.

For more details about how to create a project in Jenkins, refer to the related link.

The project dashboard is displayed.

- 3. From the project dashboard, perform the following steps:
 - a. Click the Add build step list under Build and select Run an HCL OneTest Data Generation.
 - b. Set the properties for the **HCL OneTest Data Jenkins Plugin** for HCL OneTest Data by referring to the following table:

Field	Action	Required/Optional
Name	Enter the name of the build.	Required
Use Custom Trust Store	 Select the checkbox if the SSL certificate is available in the custom trust store. Note: If you do not find details of the custom trust store in the application plugin, then the application navigates to the default trust store to access the certificate. 	Optional

Field	Action	Required/Optional
	The default trust store is at the following loca- tion: \$JAVA_HOME/jre/lib/security/cac- erts	
Custom Trust Store Path	Enter the path of the custom trust store where the certificate is stored.	Required, if Use Custom Trust Store is selected.
Use Custom Pass- word for the Trust Store	Select the checkbox if the default password for the cus- tom trust store is changed when you place the certificate in the custom trust store. Note: The default password to access the cus- tom trust store is changeit.	Optional
Custom Trust Store Password	Enter the password to access the custom trust store.	Required, if Use Custom Password for the Trust Store is selected.
Server URL	Enter the URL of HCL OneTest [™] Server. The format for the URL is as follows: https:// <fully-quali- fied-dns-name>/</fully-quali- 	Required
Offline Token	Enter the offline token that is generated in HCL OneTest™ Server.	Required
Project	Select the name of the project from the list of your projects.	Required
Schema	Select the name of the schema from the list of schemas associated with the project you selected.	Required
Root Element	Specify the root path of the element for which you want to generate the test data. For example, Root:NewType1	Required
Number of Records	Enter the number of records you want to generate. This field accepts only numbers.	Required

Field	Action	Required/Optional
Numeric Seed Val- ue	Enter the seed value that acts as an instance of random data when you generate the test data.	Optional
	This field accepts both positive and negative numbers.	
Output Data Stor- age	Select the data storage type. The data storage is a loca- tion where you want the generated test data to be writ- ten.	Required
	You can select FILE, JDBC, or MONGODB as a data storage type.	
	FILE: The generated test data is written into a file and you can download it in your local file system.	
	JDBC: The generated test data is written in the selected JDBC supported database.	
	MONGODB: The generated test data is written into Mongo- DB.	
Connection Names	Note: This field is enabled only when you select JDBC as the data storage type.	Required
	Select the connection name from the populated list of connection names.	
Output Format	Select the output file format of the generated test data from the populated list of the output formats. The output file format is based on the schema you selected.	Required
Data File Location	Specify the location of the output file. If the specified lo- cation is invalid, by default, the output file is saved in the HCL® OneTest™ Data server.	Optional
	Notes:	

Field	Action	Required/Optional
	• You can find the output file in the HCL® OneTest [™] Data pod at the following loca- tion:	
	/opt/hcl/hip-rest/output/ <ac- countId>/<userid>/<project- Id>/<schemaid>/<genmappath></genmappath></schemaid></project- </userid></ac- 	
	• This field is not applicable if you select the data storage type as JDBC.	

c. Click Save.

4. From the Jenkins dashboard, select the project and click **Build Now**.

Results

You have successfully generated the test data by using the HCL OneTest Data Jenkins Plugin.

Note: If the test data generation request fails, you can view the test data generation logs. See Viewing the test data generation logs on page 690.

What to do next

After the build completes, you can perform the following tasks:

- If you selected FILE as a data storage type, the generated test data is downloaded in the local file system at the specified location.
- If you selected JDBC as the data storage type, then you can use the generated test data from the database.
- If you selected MONGODB as the data storage type, then you can use the generated test data from the database.

Related information

Building a software project

Viewing the test data generation logs

After the Jenkins build generates the test data, you can view the details of the test data generation from the logs.

- 1. Click the build number from Build History.
- 2. Click **Console Output** to open the console for the project.

Exemple

The following sample shows the logs of the generated test data when you select FILE as the data storage type:

```
Started by user
Running as SYSTEM
Building in workspace C:\Program Files (x86)\Jenkins\workspace\HelloWorld
----- START Build Step -----
Master/Slave details
System Information : LP1-AP-51837142/10.115.94.185
Windows OS
Data Generation information:
Server URL: https://otd-build.nonprod.hclpnp.com/
Project: testing
Schema: schema
Data Location:
Seed Value: 10
Root Element: Root:NewType1
Include Header: true
No Of Records: 10
Data Storage: FILE
Output Format: Excel
Status: Starting the data generation..
Data Generation Response is
 {"code":200,"project_id":"4400","schema_id":"5ebd2915612cae00fe8e48dd","connectionURL":null,"
dbSchemaName":null,"message":"Data generation
 succeeded.","data_location":"5ebd2906612cae00fe8e48db_e584d146-db2e-4b5b-bb15-495b1a53a18a_GL
zXjhMqlX_1","timestamp":"2020-05-14T13:14:52.623Z","tableName":null}
Status: Test data generation completed successfully
Status: Downloading the Generated Test Data
Not able to save the file as the location was invalid/blank
File is available
 in /
opt/hcl/hip-rest/output/5ebbc065612cae002d82b141/5ebd2906612cae00fe8e48db/4400/5ebd2915612cae0
0fe8e48dd/e584d146-db2e-4b5b-bb15-495b1a53a18a/GLzXjhMqlX.xlsx location of OTD Server
----- END Build Step ------
Finished: SUCCESS
```

The following sample shows the logs of the generated test data when you select JDBC as the data storage type:

```
Started by user1
Running as SYSTEM
Building in workspace C:\Program Files (x86)\Jenkins\workspace\HelloWorld6
------
Master/Slave details
System Information : LP1-AP-51837142/10.115.94.185
Windows OS
```

```
Test data generation information:
Server URL: https://otd-build.nonprod.hclpnp.com/
Project: otdproject
Schema: anonymous_schema
Data Location:
Seed Value: 10
Root Element: DB:Table:Row
Include Header: false
No Of Records: 10
Data Storage: JDBC
Connection Name: SampleJDBC
Output Format: Native
Status: Starting the test data generation..
Test data generation response:
 ["code":200,"project_id":"1050","schema_id":"5e830314e4332f0192e3487e","connectionURL":"jdbc:
mysql:\/\/10.134.198.10:8081","dbSchemaName":"sampleSchema","message":"Data generation
 succeeded.","data_location":null,"timestamp":"2020-03-31T09:06:48.005Z","table name":"tasks"]
Status: Test data generation completed successfully
Data is written into the database
Connection URL: jdbc:mysgl://10.134.198.10:8081
Database schema name: sampleSchema
Table name: tasks
```

The following sample shows the logs of the generated test data when you select MONGODB as the data storage type:

```
Started by user
Running as SYSTEM
Building in workspace C:\Program Files (x86)\Jenkins\workspace\HCLOneTestData Integration
----- START Build Step -----
Master/Slave details
System Information : LP1-AP-51837142/10.115.94.185
Windows OS
Data Generation information:
Server URL: https://otd-fvt1.nonprod.hclpnp.com/
Project: testproject
Schema: EmployeeDetails
Data Location:
Seed Value: 1
Root Element: Root: Employee
Include Header: false
No Of Records: 1
Data Storage: MONGODB
Connection Name: TestMongo
Output Format: Json
```

Generating the test data by using HCL® OneTest[™] Data

When you perform a test while you deploy an application on UrbanCode[™] Deploy, you might want to generate test data. You can generate a random test data to test your application by integrating HCL® OneTest[™] Data UCD Plugin with HCL® OneTest[™] Data.

Before you begin

You must have completed the following tasks:

- Installed the latest version of the UrbanCode[™] Deploy server and agent on the target system.
- Configured the agent and verified that the agent is running on the target system. For information about how to configure the agent, refer to Configure the agent and target system.
- Downloaded the latest version of HCL® OneTest[™] Data UCD Plugin from the HCL License & Delivery portal.
- Installed HCL® OneTest[™] Data UCD Plugin on the UrbanCode[™] Deploy server. See Installing the HCL OneTest Data UCD Plugin on page 696.
- Created an account on the UrbanCode[™] Deploy server.
- Logged in to HCL OneTest[™] Server.
- Created a project and a schema in HCL® OneTest[™] Data.
- Established a connection between HCL® OneTest[™] Data and a supported database. See
 - Establishing a JDBC connection with HCL OneTest Data on page 197
 - Establishing a MongoDB connection with HCL OneTest Data on page 209

About this task

You can write the test data generated by integrating HCL® OneTest[™] Data UCD Plugin with HCL® OneTest[™] Data into a file or any supported database. After integration with HCL® OneTest[™] Data UCD Plugin, HCL® OneTest[™] Data supports the insertion of the generated test data in both JDBC supported database and MongoDB. To write

the generated test data in the database, you must establish a connection between HCL® OneTest[™] Data and the supported database.

Procedure

- 1. Log in to the HCL UrbanCode Deploy server.
- 2. Create a component.
- 3. Create a component process, and then set the properties for the component by referring to the following table:

Field	Action	Required/Optional
Name	Enter a name for the HCL UrbanCode Deploy application process.	Required
Server URL	Enter the URL of HCL OneTest [™] Server.	Required
	The format for the URL is as follows: https:// <fully-quali- fied-dns-name>/</fully-quali- 	
Offline Token	Enter the offline token that is generated in HCL OneTest™ Server.	Required
Project	Enter the name of your project.	Required
Schema	Enter the name of the schema associated with the project you selected.	Required
Root Element	Specify the root path of the element for which you want to generate the test data.	Required
	For example, Root:NewType1	
Number of Records	Enter the number of records you want to generate.	Required
Numeric Seed Value	Enter the seed value that acts as an instance of random data when you generate the test data.	Optional
Data Storage	Select the data storage type. The data storage is a loca- tion where you want the generated test data to be written.	Required
	You can select FILE, JDBC, or MONGODB as a data storage type.	
	FILE: The generated test data is written into a file and you can download it in your local file system.	
	$_{\rm JDBC}$: The generated test data is written in the selected JDBC supported database.	

Field	Action	Required/Optional
	MONGODE: The generated test data is written into MongoDB.	
Connection Name	Note: This field is applicable only when you select JDBC OF MONGODE as the data storage type. Enter the name of the JDBC OF MONGODE connection.	Required
Output Format	Specify the file format of the generated test data.	Required
Data File Location	Specify the location for the output file. If the specified location is invalid, by default, the output file is saved in the HCL® OneTest [™] Data server. Notes: You can find the output file in the HCL® OneTest[™] Data pod at the following location: /opt/hcl/hip-rest/output/<accountid>/<project-id>/<project-id>/<project-id>/<project-id>/<project-id>/<project-id>/<project< p=""> This field is not applicable if you select the data storage type as JDBC OT MONGODB. </project<></project-id></project-id></project-id></project-id></project-id></project-id></accountid>	Optional

Note: You can ignore the following property fields while you set up the integration of HCL UrbanCode Deploy with HCL® OneTest[™] Data:

- Working Directory
- Post Processing Script
- Precondition
- Use Impersonation
- 4. Create a resource and select the agent.
- 5. Add the component that you created to the agent.
- 6. Create an application.
- 7. Create an environment from the **Applications** dashboard.
- 8. Add the resource and the component that you created to the environment.
- 9. Create a process for the application by clicking the **Processes** tab from the **Applications** dashboard.

The page of the application process is displayed.

- 10. Click the component process that you created in step 3 from the **Component Process Steps** on the left navigation pane and drag it into the design area.
- 11. Click Save.
- 12. Go to the **Applications** dashboard, and then click **Request Process** for the environment of the application process that you want to execute.

The Run Process on environment name dialog is displayed.

13. Select the application process that you want to execute and click Submit.

The HCL UrbanCode Deploy dashboard shows the progress of the application process request to generate the test data.

Result

You have successfully generated the test data by using the HCL® OneTest[™] Data UCD Plugin for HCL® OneTest[™] Data.

You can view the completed request process with the status displayed as Success or Failed.



If the test data generation request fails, you can view the logs of the process. See Viewing the UrbanCode Deploy logs on page 697

What to do next

After the successful completion of process, you can perform the following tasks:

- If you selected FILE as a data storage type, the generated test data is downloaded in the local file system at the specified location.
- If you selected JDBC as the data storage type, then you can use the generated test data from the database.
- If you selected MONGODB as the data storage type, then you can use the generated test data from the database.

Installing the HCL OneTest Data UCD Plugin

When you want to generate the test data by using the HCL® OneTest[™] Data UCD Plugin for HCL® OneTest[™] Data, you must install the HCL® OneTest[™] Data UCD Plugin on the UrbanCode[™] Deploy server.

- 1. From Settings, click Automation Plugins.
- 2. Click Load Plugin.
- 3. Enter the path of the compressed plug-in file, and then click **Submit**.

Results

The plug-in is listed on the **Automation Plugins** pane.

What to do next

After you successfully installed the HCL® OneTest[™] Data UCD Plugin on the server, you must configure the HCL® OneTest[™] Data UCD Plugin and generate the test data. See Generating test data by using HCL UrbanCode Deploy on page 693.

Viewing the UrbanCode[™] Deploy logs

After completion of the generation of test data, you can view the details of the process in the UrbanCode[™] Deploy console log.

You can click the Output Log icon from the console log of the UrbanCode Deploy dashboard to view the output log.

The following sample shows the logs of the generated test data when you select FILE as the data storage type:

```
______
plugin: HCL OneTest Data UCD Plugin, id: com.urbancode.air.plugin.otd, version: 1
plugin command: 'cmd' '/C' '"D:\UCD_Agent\opt\groovy-1.8.8\bin\groovy.bat -cp
 "D:
\UCD_Agent\var\plugins\com.urbancode.air.plugin.otd_1_200b8a9ae7959125d32be1cde7aa20472d2b47c4
de3754dbd7627bd6778d33d0\classes;D:\UCD_Agent\var\plugins\com.urbancode.air.plugin.otd_1_200b8
a9ae7959125d32be1cde7aa20472d2b47c4de3754dbd7627bd6778d33d0\lib\commons-codec-1.10.jar;D:\UCD_
Agent\var\plugins\com.urbancode.air.plugin.otd_1_200b8a9ae7959125d32be1cde7aa20472d2b47c4de375
4dbd7627bd6778d33d0\lib\commons-logging-1.2.jar;D:\UCD_Agent\var\plugins\com.urbancode.air.plu
gin.otd_1_200b8a9ae7959125d32be1cde7aa20472d2b47c4de3754dbd7627bd6778d33d0\lib\groovy-all-1.8.
4.jar;D:\UCD_Agent\var\plugins\com.urbancode.air.plugin.otd_1_200b8a9ae7959125d32be1cde7aa2047
2d2b47c4de3754dbd7627bd6778d33d0\lib\groovy-plugin-utils-1.2.jar;D:\UCD_Agent\var\plugins\com.
urbancode.air.plugin.otd_1_200b8a9ae7959125d32be1cde7aa20472d2b47c4de3754dbd7627bd6778d33d0\
lib\gson-2.8.6.jar;D:\UCD_Agent\var\plugins\com.urbancode.air.plugin.otd_1_200b8a9ae7959125d32
be1cde7aa20472d2b47c4de3754dbd7627bd6778d33d0\lib\hamcrest-core-1.1.jar;D:\UCD_Agent\var\plug
ins\com.urbancode.air.plugin.otd_1_200b8a9ae7959125d32be1cde7aa20472d2b47c4de3754dbd7627bd6778
d33d0\lib\httpclient-4.5.6.jar;D:\UCD_Agent\var\plugins\com.urbancode.air.plugin.otd_1_200b8a9
ae7959125d32be1cde7aa20472d2b47c4de3754dbd7627bd6778d33d0\lib\httpcore-4.4.10.jar;D:\UCD_Ag
ent \ var \ plugins \ com. urbancode.air.plugin.otd \ 1_{200b8a9ae7959125d32be1cde7aa20472d2b47c4de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de3754de37576da3754de3754de3754de3754de3754de3754de3754de3754de37576da3754da3754da7576da3754da3754da3754da3754da3754da3758da37576
bd7627bd6778d33d0\lib\json-simple-1.1.1.jar;D:\UCD_Agent\var\plugins\com.urbancode.air.plugin.
otd_1_200b8a9ae7959125d32be1cde7aa20472d2b47c4de3754dbd7627bd6778d33d0\lib\jsoup-1.11.3.jar
;D:\UCD_Agent\var\plugins\com.urbancode.air.plugin.otd_1_200b8a9ae7959125d32be1cde7aa20472d2b4
7c4de3754dbd7627bd6778d33d0\lib\junit-4.10.jar"
 D:
\UCD_Agent\var\plugins\com.urbancode.air.plugin.otd_1_200b8a9ae7959125d32be1cde7aa20472d2b47c4
de3754dbd7627bd6778d33d0\OneTestDataGenerationUCD.groovy
 D:\UCD_Agent\var\temp\logs-63ec6300-a796-49c2-b3ad-794d0e28b1be\input.props
 D:\UCD_Agent\var\temp\logs-63ec6300-a796-49c2-b3ad-794d0e28b1be\output.props"'
working directory: D:\UCD_Agent\var\work\UCDComponent
properties:
 PLUGIN_INPUT_PROPS=D:\UCD_Agent\var\temp\logs-63ec6300-a796-49c2-b3ad-794d0e28b1be\input.pr
ops
```

PLUGIN_OUTPUT_PROPS=D:\UCD_Agent\var\temp\logs-63ec6300-a796-49c2-b3ad-794d0e28b1be\output.pr ops

connectionName=

```
dataFileLocation=C:\Users\user\Downloads
 dataStorage=FILE
 offlineToken=****
 outputFormat=CSV
 project=testing
 records=10
 rootElement=Root:NewType1
 schema=schema
 seedValue=10
 serverUrl=https://otd-build.nonprod.hclpnp.com/
environment:
 AGENT_HOME=D:\UCD_Agent
 AH_AUTH_TOKEN=****
 AH_WEB_URL=https://LP1-AP-51837142.PROD.HCLPNP.COM:8443
 AUTH_TOKEN=****
 DS_AUTH_TOKEN=****
 DS_SYSTEM_ENCODING=Cp1252
 JAVA_OPTS=-Dfile.encoding=Cp1252 -Dconsole.encoding=Cp1252
PLUGIN_HOME=D:\UCD_Agent\var\plugins\com.urbancode.air.plugin.otd_1_200b8a9ae7959125d32be1cde
7aa20472d2b47c4de3754dbd7627bd6778d33d0
 UD_DIALOGUE_ID=63ec6300-a796-49c2-b3ad-794d0e28b1be
 WE_ACTIVITY_ID=172134c9-a5ec-22cd-3c8f-4d3d9789c96d
_____
Data Generation information:
Server URL: https://otd-build.nonprod.hclpnp.com/
Project: testing
schema: schema
Root Element: Root:NewType1
Output Format: CSV
Data Location: C:\Users\user\Downloads
Seed Value: 10
Data Storage: FILE
Connection Name:
Include Header: true
No Of Records 10
Validating: server URL , offlineToken
Successfully validated server URL and offlineToken
Status: Test Data Generation Started...
Data Generation Response is [code:200, project_id:4400, schema_id:5ebd2915612cae00fe8e48dd,
connectionURL:null, dbSchemaName:null, message:Data generation succeeded.,
data_location:5ebd2906612cae00fe8e48db_4876c2b6-1424-442f-a1f1-5c3cad77576e_biWSum9yW8_1,
timestamp:2020-05-14T13:08:15.840Z, tableName:null]
Status: Test data generation completed successfully
Status: Downloading the Generated Test Data
File saved to
C:
\Users\user\Downloads\5ebd2906612cae00fe8e48db_4876c2b6-1424-442f-a1f1-5c3cad77576e_biWSum9yW8
_1.csv location
Status: Completed the download of Generated Test Data
```

The following sample shows the logs of the generated test data when you select MONGODB as the data storage type:

```
plugin: HCL OneTest Data UCD Plugin, id: com.urbancode.air.plugin.otd, version: 1
plugin command: 'cmd' '/C' '"D:\UCD_Agent\opt\groovy-1.8.8\bin\groovy.bat -cp
"D:
```

\UCD Agent\var\plugins\com.urbancode.air.plugin.otd 1 73a2c474971db8d52bfdb80c0335e047f8f6cc65 6e1784133370b8d253310f6a\classes;D:\UCD_Agent\var\plugins\com.urbancode.air.plugin.otd_1_73a2c 474971db8d52bfdb80c0335e047f8f6cc656e1784133370b8d253310f6a\lib\commons-codec-1.10.jar;D:\UCD_ Agent\var\plugins\com.urbancode.air.plugin.otd_1_73a2c474971db8d52bfdb80c0335e047f8f6cc656e178 4133370b8d253310f6a\lib\commons-logging-1.2.jar;D:\UCD_Agent\var\plugins\com.urbancode.air.plu gin.otd_1_73a2c474971db8d52bfdb80c0335e047f8f6cc656e1784133370b8d253310f6a\lib\groovy-all-1.8. 4.jar;D:\UCD_Agent\var\plugins\com.urbancode.air.plugin.otd_1_73a2c474971db8d52bfdb80c0335e047 f8f6cc656e1784133370b8d253310f6a\lib\groovy-plugin-utils-1.2.jar;D:\UCD_Agent\var\plugins\com. urbancode.air.plugin.otd_1_73a2c474971db8d52bfdb80c0335e047f8f6cc656e1784133370b8d253310f6a\ lib\gson-2.8.6.jar;D:\UCD_Agent\var\plugins\com.urbancode.air.plugin.otd_1_73a2c474971db8d52bf db80c0335e047f8f6cc656e1784133370b8d253310f6a\lib\hamcrest-core-1.1.jar;D:\UCD_Agent\var\plug ins\com.urbancode.air.plugin.otd_1_73a2c474971db8d52bfdb80c0335e047f8f6cc656e1784133370b8d2533 10f6a\lib\httpclient-4.5.6.jar;D:\UCD_Agent\var\plugins\com.urbancode.air.plugin.otd_1_73a2c47 4971db8d52bfdb80c0335e047f8f6cc656e1784133370b8d253310f6a\lib\httpcore-4.4.10.jar;D:\UCD_Ag ent\var\plugins\com.urbancode.air.plugin.otd_1_73a2c474971db8d52bfdb80c0335e047f8f6cc656e17841 33370b8d253310f6a\lib\json-simple-1.1.1.jar;D:\UCD_Agent\var\plugins\com.urbancode.air.plugin. otd_1_73a2c474971db8d52bfdb80c0335e047f8f6cc656e1784133370b8d253310f6a\lib\jsoup-1.11.3.jar ;D:\UCD_Agent\var\plugins\com.urbancode.air.plugin.otd_1_73a2c474971db8d52bfdb80c0335e047f8f6c c656e1784133370b8d253310f6a\lib\junit-4.10.jar"

```
D:
```

\UCD_Agent\var\plugins\com.urbancode.air.plugin.otd_1_73a2c474971db8d52bfdb80c0335e047f8f6cc65 6e1784133370b8d253310f6a\OneTestDataGenerationUCD.groovy

D:\UCD_Agent\var\temp\logs-48a47aee-3889-4a3b-ba91-298cbc33a99e\input.props

D:\UCD_Agent\var\temp\logs-48a47aee-3889-4a3b-ba91-298cbc33a99e\output.props"'

working directory: D:\UCD_Agent\var\work\OTDComponent

properties:

```
PLUGIN_INPUT_PROPS=D:\UCD_Agent\var\temp\logs-48a47aee-3889-4a3b-ba91-298cbc33a99e\input.pr
ops
```

PLUGIN_OUTPUT_PROPS=D:\UCD_Agent\var\temp\logs-48a47aee-3889-4a3b-ba91-298cbc33a99e\output.pr ops

connectionName=TestMongo dataFileLocation= dataStorage=MONGODB offlineToken=**** outputFormat=JSON project=testproject records=1 rootElement=Root:Employee schema=EmployeeDetails seedValue=1 serverUrl=https://otd-fvt1.nonprod.hclpnp.com/ environment: AGENT_HOME=D:\UCD_Agent AH_AUTH_TOKEN=**** AH_WEB_URL=https://LP1-AP-51837142.PROD.HCLPNP.COM:8443

```
AUTH_TOKEN=****
 DS_AUTH_TOKEN=****
 DS_SYSTEM_ENCODING=Cp1252
 JAVA_OPTS=-Dfile.encoding=Cp1252 -Dconsole.encoding=Cp1252
 PLUGIN_HOME=D:\UCD_Agent\var\plugins\com.urbancode.air.plugin.otd_1_73a2c474971db8d52bfdb80c0
335e047f8f6cc656e1784133370b8d253310f6a
 UD_DIALOGUE_ID=48a47aee-3889-4a3b-ba91-298cbc33a99e
 WE_ACTIVITY_ID=1731397b-b82e-1d8a-dc50-153fd3010ce0
Data Generation information:
Server URL: https://otd-fvt1.nonprod.hclpnp.com/
Project: testproject
schema: EmployeeDetails
Root Element: Root:Employee
Output Format: JSON
Data Location:
Seed Value: 1
Data Storage: MONGODB
Connection Name: TestMongo
Include Header: false
No Of Records 1
Validating: server URL , offlineToken
Successfully validated server URL and offlineToken
Status: Test Data Generation Started...
Data Generation Response is [code:200, databaseName:oneTestDataDB, project_id:2850,
schema_id:5efedcb33d358500a1662993, connectionURL:{my-ots}-mongodb:27017, dbSchemaName:null,
message:Data generation succeeded., data_location:null, timestamp:2020-07-03T07:33:11.497Z,
tableName:null, collectionName:employee]
Status: Test data generation completed successfully
Data is written into Mongo database
Connection URL: {my-ots}-mongodb:27017
Database Name: oneTestDataDB
Collection name: employee
```

Generating the test data by using HCL Launch

When you perform a test while you deploy an application on HCL Launch, you might want to generate test data. You can generate a random test data to test your application by integrating HCL OneTest Data Launch Plugin with HCL® OneTest[™] Data.

Before you begin

You must have completed the following tasks:

- Installed the latest version of the HCL Launch server and agent on the target system.
- Configured the agent and verified that the agent is running on the target system. For information about how to configure the agent, refer to Configure the agent and target system.
- Downloaded the latest version of HCL OneTest Data Launch Plugin from the HCL License & Delivery portal.

- Installed HCL OneTest Data Launch Plugin on the HCL Launch server. See Installing the HCL OneTest Data Launch Plugin on page 704.
- Created an account on the HCL Launch server.
- Logged in to HCL OneTest[™] Server.
- Created a project and a schema in HCL® OneTest[™] Data.
- Established a connection between HCL® OneTest™ Data and a supported database. See
 - Establishing a JDBC connection with HCL OneTest Data on page 197
 - Establishing a MongoDB connection with HCL OneTest Data on page 209

About this task

You can write the test data generated by integrating HCL OneTest Data Launch Plugin with HCL® OneTest[™] Data into a file or any supported database. After integration with HCL OneTest Data Launch Plugin, HCL® OneTest[™] Data supports the insertion of the generated test data in both JDBC supported database and MongoDB. To write the generated test data in the database, you must establish a connection between HCL® OneTest[™] Data and the supported database.

Procedure

- 1. Log in to the HCL Launch server.
- 2. Create a component.
- 3. Create a component process, and then set the properties for the component by referring to the following table:

Field	Action	Required/Optional
Name	Enter a name for the HCL Launch application process.	Required
Server URL	Enter the URL of HCL OneTest [™] Server. The format for the URL is as follows: https:// <fully-quali- fied-dns-name>/</fully-quali- 	Required
Custom Trust Store Path	Enter the path of the custom trust store where the certificate is stored.	Optional
	Note: If you do not find details of the custom trust store in the application plugin, then the application navigates to the default trust store to access the certificate.	

Field	Action	Required/Optional
	The default trust store is at the following location:	
	\$JAVA_HOME/jre/lib/security/cacerts	
Custom Trust Store Password	Enter the password to access the custom trust store.	Optional
Offline Token	Enter the offline token that is generated in HCL OneTest™ Server.	Required
Project	Enter the name of your project.	Required
Schema	Enter the name of the schema associated with the project you selected.	Required
Root Element	Specify the root path of the element for which you want to generate the test data.	Required
	For example, Root:NewType1	
Number of Records	Enter the number of records you want to generate.	Required
Numeric Seed Value	Enter the seed value that acts as an instance of random data when you generate the test data.	Optional
Data Storage	Select the data storage type. The data storage is a loca- tion where you want the generated test data to be written. You can select FILE, JDBC, or MONGODE as a data storage type.	Required
	FILE: The generated test data is written into a file and you can download it in your local file system. JDBC: The generated test data is written in the selected JDBC supported database.	
Connection Name	MONGODE: The generated test data is written into MongoDB. Note: This field is applicable only when you select JDBC OF MONGODE as the data storage type. Enter the name of the JDBC OF MONGODE connection.	Required
Output Format	Specify the file format of the generated test data.	Required
	l.	·

Field	Action	Required/Optional
Data File Location	Specify the location for the output file. If the specified lo- cation is invalid, by default, the output file is saved in the HCL® OneTest [™] Data server. Notes: • You can find the output file in the HCL® OneTest [™] Data pod at the following loca- tion:	Optional
	<pre>tion: /opt/hcl/hip-rest/output/<ac- countid="">/<userid>/<project- id="">/<schemaid>/<genmappath> o This field is not applicable if you select the data storage type as JDBC OF MongoDB.</genmappath></schemaid></project-></userid></ac-></pre>	

Note: You can ignore the following property fields while you set up the integration of HCL Launch with HCL® OneTest[™] Data:

- Working Directory
- Post Processing Script
- Precondition
- Use Impersonation
- 4. Create a resource and select the agent.
- 5. Add the component that you created to the agent.
- 6. Create an application.
- 7. Create an environment from the Applications dashboard.
- 8. Add the resource and the component that you created to the environment.
- 9. Create a process for the application by clicking the **Processes** tab from the **Applications** dashboard.

The page of the application process is displayed.

- 10. Click the component process that you created in step 3 from the **Component Process Steps** on the left navigation pane and drag it into the design area.
- 11. Click Save.
- 12. Go to the **Applications** dashboard, and then click **Request Process** for the environment of the application process that you want to execute.
- 13. Select the name of the application, environment, and process from the drop-down list, and then click Next.
- 14. Verify that the default settings of the component versions are retained, and then click Next.
- 15. Toggle the Run Now switch to the on position to set the Schedule Deployment, and then click Next.
- 16. Check the deployment details, and then click Submit Deployment.

Result

You have successfully generated the test data by using the HCL OneTest Data Launch Plugin for HCL® OneTest™ Data.

You can view the completed request process with the status displayed as Success or Failed.



If the test data generation request fails, you can view the logs of the process. See Viewing the HCL Launch logs on page 704.

What to do next

After the successful completion of the process, you can perform the following tasks:

- If you selected FILE as a data storage type, then you can download the generated test data in the local file system at the specified location.
- If you selected JDBC as the data storage type, then you can use the generated test data from the database.
- If you selected MONGODB as the data storage type, then you can use the generated test data from the database.

Installing the HCL OneTest Data Launch Plugin

When you want to generate the test data by using the HCL® OneTest[™] Data for HCL® OneTest[™] Data, you must install the HCL® OneTest[™] Data on the HCL Launch server.

- 1. From Settings, click Automation Plugins.
- 2. Click Load Plugin.
- 3. Enter the path of the compressed plug-in file, and then click Submit.

Results

The plug-in is listed on the Automation Plugins pane.

What to do next

After you successfully installed the HCL® OneTest[™] Data on the server, you must configure the HCL® OneTest[™] Data and generate the test data. See Generating the test data by using HCL Launch on page 700.

Viewing the HCL Launch logs

After completion of the generation of test data, you can view the details of the process in the HCL Launch console log.

You can click the Output Log icon from the console log of the HCL Launch dashboard to view the output log.

The following sample shows the logs of the generated test data when you select FILE as the data storage type:

```
plugin: HCL OneTest Data Launch Plugin, id: com.hcllaunch.air.plugin.otd, version: 2
plugin command: 'cmd' '/C' '""D:\HCL Launch\LaunchAgent\opt\groovy-2.4.15\bin\groovy.bat" -cp
"D:\HCL
Launch\LaunchAgent\var\plugins\com.hcllaunch.air.plugin.otd_2_ebae55c6a5da97650f3890760d07778
5e4fa877523edeadf3cfda916b293b4a1\classes;D:\HCL
Launch/LaunchAgent/var/plugins/com.hcllaunch.air.plugin.otd_2_ebae55c6a5da97650f3890760d07778
5e4fa877523edeadf3cfda916b293b4a1\lib\commons-codec-1.10.jar;D:\HCL
Launch/LaunchAgent/var/plugins/com.hcllaunch.air.plugin.otd_2_ebae55c6a5da97650f3890760d07778
5e4fa877523edeadf3cfda916b293b4a1\lib\commons-logging-1.2.jar;D:\HCL
Launch\LaunchAgent\var\plugins\com.hcllaunch.air.plugin.otd_2_ebae55c6a5da97650f3890760d07778
5e4fa877523edeadf3cfda916b293b4a1\lib\groovy-all-1.8.4.jar;D:\HCL
Launch\LaunchAgent\var\plugins\com.hcllaunch.air.plugin.otd_2_ebae55c6a5da97650f3890760d07778
5e4fa877523edeadf3cfda916b293b4a1\lib\groovy-plugin-utils-1.2.jar;D:\HCL
Launch\LaunchAgent\var\plugins\com.hcllaunch.air.plugin.otd_2_ebae55c6a5da97650f3890760d07778
5e4fa877523edeadf3cfda916b293b4a1\lib\gson-2.8.6.jar;D:\HCL
Launch/LaunchAgent/var/plugins/com.hcllaunch.air.plugin.otd_2_ebae55c6a5da97650f3890760d07778
5e4fa877523edeadf3cfda916b293b4a1\lib\hamcrest-core-1.1.jar;D:\HCL
Launch/LaunchAgent/var/plugins/com.hcllaunch.air.plugin.otd_2_ebae55c6a5da97650f3890760d07778
5e4fa877523edeadf3cfda916b293b4a1\lib\httpclient-4.5.6.jar;D:\HCL
Launch\LaunchAgent\var\plugins\com.hcllaunch.air.plugin.otd_2_ebae55c6a5da97650f3890760d07778
5e4fa877523edeadf3cfda916b293b4a1\lib\httpcore-4.4.10.jar;D:\HCL
Launch\LaunchAgent\var\plugins\com.hcllaunch.air.plugin.otd_2_ebae55c6a5da97650f3890760d07778
5e4fa877523edeadf3cfda916b293b4a1\lib\json-simple-1.1.1.jar;D:\HCL
Launch\LaunchAgent\var\plugins\com.hcllaunch.air.plugin.otd_2_ebae55c6a5da97650f3890760d07778
5e4fa877523edeadf3cfda916b293b4a1\lib\jsoup-1.11.3.jar;D:\HCL
Launch/LaunchAgent/var/plugins/com.hcllaunch.air.plugin.otd_2_ebae55c6a5da97650f3890760d07778
5e4fa877523edeadf3cfda916b293b4a1\lib\junit-4.10.jar" "D:\HCL
Launch/LaunchAgent/var/plugins/com.hcllaunch.air.plugin.otd_2_ebae55c6a5da97650f3890760d07778
5e4fa877523edeadf3cfda916b293b4a1\OneTestDataGenerationHCLLaunch.groovy" "D:\HCL
Launch\LaunchAgent\var\temp\logs-89c29385-395a-4c98-b695-de7eb9dbdee5\input.props" "D:\HCL
Launch\LaunchAgent\var\temp\logs-89c29385-395a-4c98-b695-de7eb9dbdee5\output.props""
working directory: D:\HCL Launch\LaunchAgent\var\work\OTDComponent1
properties:
 PLUGIN_INPUT_PROPS=D:\HCL
Launch\LaunchAgent\var\temp\logs-89c29385-395a-4c98-b695-de7eb9dbdee5\input.props
 PLUGIN_OUTPUT_PROPS=D:\HCL
Launch\LaunchAgent\var\temp\logs-89c29385-395a-4c98-b695-de7eb9dbdee5\output.props
 connectionName=
 dataFileLocation=C:\Users\user1\Downloads
 dataStorage=FILE
 offlineToken=****
 outputFormat=CSV
 project=otdproject
 records=10
 rootElement=Root:NewType1
 schema=otdschema
 seedValue=10
 serverUrl=https://otd-fvt2.nonprod.hclpnp.com/
environment:
 AGENT_HOME=D:\HCL Launch\LaunchAgent
 AH_AUTH_TOKEN=****
```

```
AH_WEB_URL=https://LP1-AP-51837142.PROD.HCLPNP.COM:8443
 AUTH TOKEN=****
 DS_AUTH_TOKEN=****
 DS_SYSTEM_ENCODING=Cp1252
 JAVA_OPTS=-Dfile.encoding=Cp1252 -Dconsole.encoding=Cp1252
 PLUGIN_HOME=D:\HCL
 Launch\LaunchAgent\var\plugins\com.hcllaunch.air.plugin.otd_2_ebae55c6a5da97650f3890760d07778
5e4fa877523edeadf3cfda916b293b4a1
 UD_DIALOGUE_ID=89c29385-395a-4c98-b695-de7eb9dbdee5
 WE_ACTIVITY_ID=17443a96-551a-d05a-6041-0d9b77073106
Data Generation information:
Server URL: https://otd-fvt2.nonprod.hclpnp.com/
Project: otdproject
schema: otdschema
Root Element: Root:NewType1
Output Format: CSV
Data Location: C:\Users\user1\Downloads
Seed Value: 10
Data Storage: FILE
Connection Name:
Include Header: true
No Of Records 10
Validating: server URL, offlineToken
Successfully validated server URL and offlineToken
Status: Test Data Generation Started...
Data Generation Response is [code:200, databaseName:null,
 project_id:3200, schema_id:5f48ad2b1491d2009db126fd, connectionURL:null,
 dbSchemaName:null, message:Data generation succeeded.,
 data_location:5f48ad1c1491d2009db126fb_077ae85b-5527-4aba-a64f-5b58d15df899_6dH9eZZfoq_1,
 timestamp:2020-08-31T08:36:56.526Z, tableName:null, collectionName:null]
Status: Test data generation completed successfully
Status: Downloading the Generated Test Data
File saved to
C:
\Users\user1\Downloads\5f48ad1c1491d2009db126fb_077ae85b-5527-4aba-a64f-5b58d15df899_6dH9eZZfo
q_1.csv location
Status: Completed the download of Generated Test Data
```

The following sample shows the logs of the generated test data when you select MONGODE as the data storage type:

plugin: HCL OneTest Data Launch Plugin, id: com.hcllaunch.air.plugin.otd, version: 2
plugin command: 'cmd' '/C' '""D:\HCL Launch\LaunchAgent\opt\groovy-2.4.15\bin\groovy.bat" -cp
"D:\HCL
Launch\LaunchAgent\var\plugins\com.hcllaunch.air.plugin.otd_2_fcffff6fc25d3aad57596e97b05f621
f6a850ad06d6b0495e2954cbf5e1be0e0\classes;D:\HCL
Launch\LaunchAgent\var\plugins\com.hcllaunch.air.plugin.otd_2_fcffff6fc25d3aad57596e97b05f621
f6a850ad06d6b0495e2954cbf5e1be0e0\lib\commons-codec-1.10.jar;D:\HCL
Launch\LaunchAgent\var\plugins\com.hcllaunch.air.plugin.otd_2_fcffff6fc25d3aad57596e97b05f621
f6a850ad06d6b0495e2954cbf5e1be0e0\lib\commons-codec-1.10.jar;D:\HCL
Launch\LaunchAgent\var\plugins\com.hcllaunch.air.plugin.otd_2_fcffff6fc25d3aad57596e97b05f621
f6a850ad06d6b0495e2954cbf5e1be0e0\lib\commons-codec-1.10.jar;D:\HCL
Launch\LaunchAgent\var\plugins\com.hcllaunch.air.plugin.otd_2_fcffff6fc25d3aad57596e97b05f621
f6a850ad06d6b0495e2954cbf5e1be0e0\lib\commons-logging-1.2.jar;D:\HCL
Launch\LaunchAgent\var\plugins\com.hcllaunch.air.plugin.otd_2_fcffff6fc25d3aad57596e97b05f621
f6a850ad06d6b0495e2954cbf5e1be0e0\lib\commons-logging-1.2.jar;D:\HCL

Launch\LaunchAgent\var\plugins\com.hcllaunch.air.plugin.otd_2_fcffff6fc25d3aad57596e97b05f621 f6a850ad06d6b0495e2954cbf5e1be0e0\lib\groovy-all-1.8.4.jar;D:\HCL

```
Launch\LaunchAgent\var\plugins\com.hcllaunch.air.plugin.otd_2_fcffff6fc25d3aad57596e97b05f621
f6a850ad06d6b0495e2954cbf5e1be0e0\lib\groovy-plugin-utils-1.2.jar;D:\HCL
Launch\LaunchAgent\var\plugins\com.hcllaunch.air.plugin.otd_2_fcffff6fc25d3aad57596e97b05f621
f6a850ad06d6b0495e2954cbf5e1be0e0\lib\gson-2.8.6.jar;D:\HCL
Launch/LaunchAgent/var/plugins/com.hcllaunch.air.plugin.otd_2_fcffff6fc25d3aad57596e97b05f621
f6a850ad06d6b0495e2954cbf5e1be0e0\lib\hamcrest-core-1.1.jar;D:\HCL
Launch\LaunchAgent\var\plugins\com.hcllaunch.air.plugin.otd_2_fcffff6fc25d3aad57596e97b05f621
f6a850ad06d6b0495e2954cbf5e1be0e0\lib\httpclient-4.5.6.jar;D:\HCL
Launch\LaunchAgent\var\plugins\com.hcllaunch.air.plugin.otd_2_fcffff6fc25d3aad57596e97b05f621
f6a850ad06d6b0495e2954cbf5e1be0e0\lib\httpcore-4.4.10.jar;D:\HCL
Launch\LaunchAgent\var\plugins\com.hcllaunch.air.plugin.otd_2_fcffff6fc25d3aad57596e97b05f621
f6a850ad06d6b0495e2954cbf5e1be0e0\lib\json-simple-1.1.1.jar;D:\HCL
Launch/LaunchAgent/var/plugins/com.hcllaunch.air.plugin.otd_2_fcffff6fc25d3aad57596e97b05f621
f6a850ad06d6b0495e2954cbf5e1be0e0\lib\jsoup-1.11.3.jar;D:\HCL
Launch\LaunchAgent\var\plugins\com.hcllaunch.air.plugin.otd_2_fcffff6fc25d3aad57596e97b05f621
f6a850ad06d6b0495e2954cbf5e1be0e0\lib\junit-4.10.jar" "D:\HCL
Launch\LaunchAgent\var\plugins\com.hcllaunch.air.plugin.otd_2_fcffff6fc25d3aad57596e97b05f621
f6a850ad06d6b0495e2954cbf5e1be0e0\OneTestDataGenerationHCLLaunch.groovy" "D:\HCL
Launch\LaunchAgent\var\temp\logs-49ec0c81-7f25-4494-accd-4bf9bd384d93\input.props" "D:\HCL
Launch\LaunchAgent\var\temp\logs-49ec0c81-7f25-4494-accd-4bf9bd384d93\output.props""
working directory: D:\HCL Launch\LaunchAgent\var\work\OTDComponent1
properties:
 PLUGIN_INPUT_PROPS=D:\HCL
Launch\LaunchAgent\var\temp\logs-49ec0c81-7f25-4494-accd-4bf9bd384d93\input.props
 PLUGIN_OUTPUT_PROPS=D:\HCL
Launch\LaunchAgent\var\temp\logs-49ec0c81-7f25-4494-accd-4bf9bd384d93\output.props
 connectionName=MongoConnection
 dataFileLocation=
 dataStorage=MONGODB
 offlineToken=****
 outputFormat=JSON
 project=otdproject
 records=1
 rootElement=Root:NewType1
 schema=otdschema
 seedValue=
 serverUrl=https://otd-fvt1.nonprod.hclpnp.com/
environment:
 AGENT_HOME=D:\HCL Launch\LaunchAgent
 AH_AUTH_TOKEN=****
 AH_WEB_URL=https://LP1-AP-51837142.PROD.HCLPNP.COM:8443
 AUTH_TOKEN=****
 DS_AUTH_TOKEN=****
 DS_SYSTEM_ENCODING=Cp1252
 JAVA_OPTS=-Dfile.encoding=Cp1252 -Dconsole.encoding=Cp1252
 PLUGIN_HOME=D:\HCL
Launch\LaunchAgent\var\plugins\com.hcllaunch.air.plugin.otd_2_fcffff6fc25d3aad57596e97b05f621
f6a850ad06d6b0495e2954cbf5e1be0e0
 UD_DIALOGUE_ID=49ec0c81-7f25-4494-accd-4bf9bd384d93
 WE_ACTIVITY_ID=174d8e29-f157-0a93-07a4-5a90df84fb41
Data Generation information:
```

Server URL: https://otd-fvt1.nonprod.hclpnp.com/ Project: otdproject schema: otdschema Root Element: Root:NewType1 Output Format: JSON Data Location: Seed Value: Data Storage: MONGODB Connection Name: MongoConnection Include Header: false No Of Records 1 Validating: server URL , offlineToken Successfully validated server URL and offlineToken Status: Test Data Generation Started... Data Generation Response is [code:200, databaseName:mdb, project_id:1150, schema_id:5f72c22171ff1a00a009ae50, connectionURL:{my-ots}-mongodb:27017, message:Data generation succeeded., timestamp:2020-09-29T08:02:59.141Z, collectionName:users] Status: Test data generation completed successfully Data is written into Mongo database Connection URL: {my-ots}-mongodb:27017 Database Name: mdb Collection name: users

Managing access to HCL OneTest[™] Server

Desktop clients and third-party integrations use offline user tokens to connect to HCL OneTest[™] Server.

You can configure the desktop clients and third-party integrations to access HCL OneTest[™] Server by using the offline user tokens created from the server.

Offline user tokens are used in the following cases:

- To retrieve secrets configured on the server to be used in certain tests in HCL OneTest[™] API.
- To enable publishing of test results and reports from desktop clients to HCL OneTest[™] Server.
- To enable the Resource Monitoring Service in HCL OneTest[™] Performance to monitor a data source during a run on HCL OneTest[™] Server.
- To enable agents to connect with HCL OneTest[™] Server.
- To enable HTTP proxies to connect with HCL OneTest[™] Server.
- To enable third-party integrations.

About this task

From HCL OneTest[™] Server, you can create an offline user token, copy it, and then use that token to enable connections to be authenticated by HCL OneTest[™] Server.

You can also delete all the tokens, when you no longer need access or you want to prevent access to the server.

Creating a token

- · Follow these steps:
 - 1. Click the **User** icon **C** from the menu bar, and then select **Create Token**.

The Create Offline User Token dialog is displayed.



Note: This token is not accessible after you copy it as the dialog box closes.

2. Copy the token and paste it into a private location for ongoing reference.

The dialog closes.

3. Paste the token into the desktop client UI or in the application where this token is required.

See the following table for a list of where you can use the tokens and where you can find more information.

Table 16. Using the offline user tokens to access HCL OneTest $^{\scriptscriptstyle \mathrm{M}}$ Server		
Use the offline user token in the following places	More information	
HCL OneTest™ API	See HCL OneTest [™] API and HCL OneTest [™] Server.	
HCL OneTest [™] Performance	See Publishing test results to the server.	
	See Enabling Enablement of Resource Monitoring services for a schedule.	
HCL OneTest™ UI	See Publishing test results to the server.	
Third-party integrations	See Integrations with other applications on page 620.	

Deleting tokens

- · Follow these steps:
 - 1. Click the **User** icon from the menu bar and select **Delete Tokens**.

The Delete All Offline User Tokens dialog is displayed.

2. Inform the desktop client users that the tokens were deleted. Fix any test automation scripts that used tokens.

Working with HCL OneTest[™] Server REST services

When you want to use the HCL OneTest[™] Server REST APIs in your test automation scripts, you can view the REST APIs that are exposed by HCL OneTest[™] Server. You can also run the APIs from within your project in HCL OneTest[™] Server.

All REST services are accessible from the base URL of HCL OneTest[™] Server and are defined by using Swagger. A navigable user interface lists the available set of APIs at <server_URL>/#/initial/Admin/docs. This Swagger file describes the individual APIs along with details of the parameters and response bodies.

You must be assigned the role of an administrator to be able to view or run the REST APIs.

After you log into HCL OneTest[™] Server with your credentials that has administrator privileges, you must go to the following URL: <server_URL>/#/initial/Admin/docs

The Swagger docs that are available can be viewed from the drop down list.

You can select the Swagger doc for the REST APIs that you want to view or use. For example, you can select the / **jobservicev2/pi-docs** to view the APIs for the execution micro-service.

You can perform the following steps to view or run the API:

- 1. Expand the section to view the APIs that are available.
- 2. Expand each of the APIs to view the details such as the description, examples, parameters, and responses.
- 3. Run the API by clicking the Try it out option and then enter the required values for the parameters.
- 4. Click Execute to start the API.

You can view the response after the API runs.

Chapter 7. Test Manager Guide

This guide describes how to manage and track your overall test effort. This guide is intended for test managers.

Related information Managing access to server projects on page 734

Team space management

You might want to become a team space member, add members to your team space, change a user role in a team space, modify the team space, or delete a team space.

Each team space is associated with at least one *Team Space Owner*. You can assign multiple owners to your team space. Any user who becomes a member of a team space and is assigned the role of a *Member*, *Project Creator*, *Architect*, or *Team Space Owner* of a team space, can access the team space.

As an owner of a team space, after you create a team space, you must configure the team space license. You can then add members to the team space and can assign different roles to each member of the team space. You can update or delete a team space. You can also add a repository to a team space to store a system model and edit the repository settings. Apart from adding a repository, you can add, update, or delete the Resource Monitoring agent if no longer required.

As an Architect of a team space, you can manage a team space repository and design a system model.

As a Project Creator of a team space, you can create a project in the team space.

As a licensed user who is assigned with a *Member, Project Creator, Architect,* or *Team Space Owner* role of a team space, you can add a Docker host to your team space. You can view the configured Docker, agents, or intercepts of your team space. You can edit only those Docker hosts that you created.

Viewing team spaces

After you log in to HCL OneTest[™] Server, you can view all the existing team spaces on the **Team Space Dashboard** page.

About this task

As a member of a team space, you can view your team spaces under **My Team Spaces**. You can also view the team spaces that are created by other users as the public team space and the Permissive team spaces under **Other Team Spaces**.

If the initial team space does not exist, then you can view the Team Space Dashboard without any navigation pane.

You as a member of a team space, when you want to use that team space immediately after you log in to HCL OneTest[™] Server, you can suffix the alias in the application URL.

For example, if the alias of the team space is first, then you must use the following HCL OneTest[™] Server URL in the address bar:

<server url>/#/first

1. Log in to HCL OneTest[™] Server.

Result

The Projects page of the initial team space is displayed.

2. Click the **Settings** icon ⁽²⁾ from the left navigation pane, and then click **Join another team space**.

Result

The Team Space Dashboard is displayed.

You can view the team spaces in the following panels:

- **My Team Spaces**: You can view all the team spaces that you created. You can also view the team spaces in which you are a member.
- Other Team Spaces: You can view all the team spaces that are created by others.



Note: You cannot view the Restrictive private type team spaces.

Results

You have viewed the team spaces that are created by you and other users on the Team Space Dashboard.

What to do next

You can select a team space and can send a request to become a member of that team space. See Becoming a team space member on page 719.

Adding members to a team space

When you create a team space to manage projects, you must add users to your team space so that they can create and access the projects.

Before you begin

- As an administrator, you are assigned the default role of a *Team Space Owner*. If you log in to HCL OneTest[™] Server as another user, then you must have been assigned the role of a *Team Space Owner*.
- As an owner of a team space, you must have completed the following tasks:
 - Created a team space. See Creating a team space on page 111.
 - Configured a license for the team space. See Configuring licenses for team spaces on page 121.

You must have been assigned a role as a *Team Space Owner*. If you are a server administrator, then you are assigned with the default role of a *Team Space Owner*.

About this task

As an owner of a team space, you can add multiple users to your Permissive or Restrictive team space.

1. Log in to HCL OneTest[™] Server.

Result

The Projects page of the initial team space is displayed.

2. Click the **Settings** icon 🔯 from the left navigation pane.



Note: If the initial team space does not exist, then you can view the **Team Space Dashboard** page without any navigation pane.

3. Identify the team space for which you want to add a member.

You can either use the same team space where you choose to work or switch to any other team space.

4. Click Add member to add members in the initial team space.

Alternatively, you can select the team space, and then click **Settings > Add member**.

Result

The Add Member page is displayed.

5. Enter a user name in the **Add People** field to add users.

Alternatively, you can find the user name by using type search.

Result

The list of users is displayed.

- 6. Select the user.
- 7. Assign a role to the selected user.



Note: All members are assigned the default roles of a Project Creator and Architect.

You can choose the role for the user based on its associated actions:

Roles	Responsibilities
Team Space Owner	 Create a team space.
	 Update and delete a team space.
	 Add members to a team space.
	 Remove members from the team space.
	 Assign the roles to the members.
	 Modify the roles of the members.
	 Create and modify a project.
	 Add or update the system model.
	 Add a repository to store a system model.
	 Update and delete a repository in a team space.
	 Add, update, or delete Docker.

Roles	Responsibilities
	 Configure or update agent and intercepts. Register, update, delete, and list Resource Monitoring sources in a team space.
Project Creator	 Create, update, and view a project Add, update, or delete Docker. Configure or update agent and intercepts.
Architect	 Create, update, delete, and view a repository in a team space. Create, update, and delete components in the system model. Add, update, or delete Docker. Configure or update agent and intercepts.
Member	 View the list of team spaces in the Team Space Dashboard. View the configuration of the team space. Add, update, or delete Docker. Configure or update agent and intercepts. View the registered Dockers, agents, or intercepts. View the Resource Monitoring agents in a team space. View the registered Resource Monitoring agents. View the registered Resource Monitoring agents. View components in the system model.

Notes:

• The members with the assigned role of a *Team Space Owner*, *Project Creator*, *Architect*, or *Member* of a team space can be assigned with any of the following project roles:

- Project Owner
- Tester
- Viewer

• You can add or remove the role of a member by using the **Menu** icon * next to each user in the **Members** list.

8. Repeat the applicable steps to add another user.

Results

You have added members with assigned roles to your team space. You can view the list of all added users on the **Team Space Configuration** page.

What to do next

You can reassign or remove the roles of users to one or more team spaces that you own. See Managing members and their roles in a team space on page 720.

All users can request to be a member of another team space. See Becoming a team space member on page 719.

Users added as members to the team space can view the team space in My Team Spaces.

Modifying the configuration of a team space

After you create a team space, if you want to modify the details of the team space, add a repository to your team space, add or remove members of a team space or delete a team space, then you can perform these tasks on the **Team Space Configuration** page.

Before you begin

You must have been assigned the role of a Team Space Owner.

About this task

The Team Space Configuration page displays details of the team space.

As an owner of a team space, you can modify details of the team space, add members to your team space, and assign roles to the members of the team space on the **Team Space Configuration** page.

The Team Space Owner and Architect can add or remove a repository from the team space.

If the team space is no longer required, then the Team Space Owner can also delete that team space.

As a *Member*, *Project Creator*, or *Architect*, you can only view the configuration details of a team space on the **Details** tab of the **Team Space Configuration** page.

As a *Member*, and *Project Creator* you can only view the configuration details of a team space on the **Repository** tab of the **Team Space Configuration** page.

1. Log in to HCL OneTest[™] Server.

Result

The Projects page of the initial team space is displayed.

- 2. Click the **Settings** icon 🥺 from the left navigation pane.
- 3. Identify the team space for which you want to modify the configuration.

You can either use the same team space where you are working or switch to any other team space.

4. Click Manage team space.

Result

The **Details** page is displayed.

5. Perform the modifications on the following details of the **Details** tabs of the team space:

Fields	More information	
Name	Displays the name of the team space.	

Fields	More information
URL alias	Displays an alias of the team space. You must suffix this alias in the application URL to access a specific team space after you log in to the application.
Available at	Displays the application URL by using an alias. You can copy this URL and use it when you want to ac- cess the team space immediately after you log in to the application. Note: You cannot modify the URL.
Member Access	 Displays the type of team space that defines the permissions to access the team space. A team space can be of the following types: • Permissive: All licensed users can access this team space without the approvals of a <i>Team Space Owner</i>. • Restrictive: All licensed users must get approvals from the <i>Team Space Owner</i> to access this team space.
Visibility	 The visibility mode of a team space can be of the following types: Public: The team spaces are visible to all licensed users in the Other Team Spaces panel. Private: The team spaces are not visible to all the licensed users in the Other Team Spaces panel. Note: The visibility mode is available only when the Restrictive type of team space is selected.
Description	Brief description of the team space. This is an op- tional field.
Add People	List of members in a team space.

6. Click the **Repository** tab to modify the details of the repository of the team space.

Results

You have modified the configuration details of the selected team space.

What to do next

You can add members and assign roles to each member of your team space.

Related information

Adding members to a team space on page 712 Managing members and their roles in a team space on page 720 Adding repositories to a server project on page 728

Viewing the configuration of a team space

You can view the configuration of a team space as a member of any team space. You can view the configuration details on the **Team Space Configuration** page.

Before you begin

You must be a member of a team space.

About this task

The Team Space Configuration page displays the configuration details of the team space.

As a member of a team space, if you want to access your team space immediately after logging into HCL OneTest[™] Server, then you must suffix the alias in the application URL. You can find details of the alias on the **Team Space Configuration** page. You can also view the list of members and their roles in that team space on the **Team Space Configuration** page.

- 1. Log in to HCL OneTest[™] Server.
- 2. Click the **Settings** icon 👰 from the left navigation pane.
- 3. Identify the team space for which you want to view the configuration.

You can either use the same team space where you are working or switch to any other team space.

4. Click Manage team space.

Result

The **Details** page is displayed.

You can view the following details about the team space:

Fields	Tabs	More information
Name	Details	Displays the name of the team space.
URL alias	Details	Displays an alias of the team space. You must suffix this alias

Fields	Tabs	More information
		in the application URL to access a specific team space after you log in to the application.
Available at	Details	Displays the application URL by us ing an alias. You can copy this URI and use it when you want to ac- cess the team space immediately after you log in to the application.
Member Access	Details	Displays the type of team space that defines the permissions to access the team space. A team space can be of the following types: • Permissive : All licensed users can access this team space without the ap provals of a <i>Team Space</i> <i>Owner</i> . • Restrictive : All licensed users must get approvals from the <i>Team Space Own-</i> <i>er</i> to access this team space.
Visibility	Details	The visibility mode of a team space can be of the following types: • Public: The team spaces are visible to all licensed users in the Other Team Spaces panel. • Private: The team spaces are not visible to all the li- censed users in the Other Team Spaces panel. Note: The visibility mode is available only when the

Fields	Tabs	More information
		Restrictive type of team space is selected.
Members	Details	Displays a list of members of the team space.
Repository	Repository	Displays the repository details that host the system model.

Results

You have viewed the configuration details of the selected team space.

Becoming a team space member

After logging into HCL OneTest[™] Server, the licensed users must be a member of any team space to perform test activities in a project. As a licensed user, if you are not assigned the role of a member in any team space, then you can request the *Team Space Owner* become a member of any existing team space.

Before you begin

You must be a licensed user.

About this task

If you want to become a member of a **Restrictive** team space, then only the owner of that team space can grant you the role of a member of a team space. If you request to become a member of a **Permissive** team space, then you automatically become a member of that team space.



Note: The server administrator can join any team space automatically without any approval and is assigned with a default role of *Team Space Owner*.

1. Log in to HCL OneTest[™] Server.

Result

The Projects page of the initial team space is displayed.

2. Click the **Settings** icon 0 from the left navigation pane, and then **Join another team space**.

Result

The Team Space Dashboard is displayed.

You can view the team spaces in the following panels:

- **My Team Spaces**: You can view all the team spaces that you created. You can also view the team spaces in which you are a member.
- Other Team Spaces: You can view all the team spaces that are created by others.

Note:

You can view only the public type of **Restrictive** team spaces and the **Permissive** team spaces. You cannot view the **Restrictive** private type team spaces.

- 3. Select the team space that you want to join from the list of other team spaces in the Team Space Dashboard.
- Click the Key icon P of the selected team space.
- 5. Confirm your request when prompted.

If you agree, then the Team Space Owner sees a notification about the request.

After opening the notification, the *Team Space Owner* can view the user who is requesting the access and can accept or decline the request. If the *Team Space Owner* accepts your request, you are added and assigned a *Member* role.



- You can become a member of any team space only when the license of the selected team space is configured.
- If you are a server administrator, then the Team Space Owner role is the default role assigned.
- If you are a licensed user, then the Member role is the default role assigned and is restricted to specific actions.

You can then see the team space under My Team Spaces on the Team Space Dashboard page.

You might want to follow up with the Team Space Owner if your request is pending for some time.

Results

You have become a member of another team space.

What to do next

You can view the actions that you can perform based on your assigned role. See Adding members to a team space on page 712.

Managing members and their roles in a team space

After you assign roles to the members of a team space, as a *Team Space Owner*, you might want to remove a member from the team space or reassign the role to the existing members of your team space.

Before you begin

You must have been assigned the role of a Team Space Owner.

About this task

As a licensed user, you are assigned a role of a *Member* in any team space after the approval of the *Team Space Owner*.

As an owner of a team space, you can remove or reassign any member of your team space with the roles of a *Team Space Owner, Project Creator,* or *Architect.* You can also remove any member from the list of members of the team space.

1. Log in to HCL OneTest[™] Server.

Result

The Projects page of the initial team space is displayed.

- 2. Click the **Settings** icon ⁽²⁾ from the left navigation pane.
- 3. Identify the team space for which you want to reassign the roles of the members or remove a member from the list of members.

You can either use the same team space where you are working or switch to any other team space.

4. Click **Add member** if you want to reassign the roles of the members or remove a member from the list of members of the initial team space.

Alternatively, you can select the team space, and then click Settings > Add member.

Result

The Add member page is displayed.

- 5. Identify the member from the list of **Members**.
- 6. Click the Menu icon an ext to the selected member.
- 7. Perform any one of the following operations to the identified member of the team space:

Choose from:

- Click Remove Member to remove the identified member from the team space.
- Select the role that you want to assign or remove the assigned role for the identified member.

You can choose multiple roles for the members based on the associated actions:

Roles	Actions
Team Space Owner	 Create a team space.
	 Update and delete a team space.
	 Add members to a team space.
	 Remove members from the team space.
	 Assign the roles to the members.
	 Modify the roles of the members.
	 Create and modify a project.
	 Add or update the system model.
	• Add a repository to store a system model.
	 Update and delete a repository in a team
	space.
	 Add, update, or delete Docker.

Roles	Actions
	 Configure or update agent and intercepts. Register, update, delete, and list Resource Monitoring sources in a team space.
Project Creator	 Create, update, and view a project. Add, update, or delete Docker. Configure or update agent and intercepts.
Architect	 Create, update, delete, and view a repository in a team space. Create, update, and delete components in the system model. Add, update, or delete Docker. Configure or update agent and intercepts.
Member	 View the list of team spaces in the Team Space Dashboard. View the configuration of the team space. Add, update, or delete Docker. Configure or update agent and intercepts. View the registered Dockers, agents, or intercepts. View the Resource Monitoring agents in a team space. View the registered Resource Monitoring agents. View components in the system model.

Note: The *Team Space Owner*, *Project Creator*, *Architect*, or *Member* of a team space can be assigned with any of the following project roles:

- Project Owner
- Tester
- Viewer

Similarly, you can remove the assigned role of any member of your team space.

Results

You have completed any of the following tasks in your team space:

- Reassigned the role of the members.
- Removed the assigned role of the members.
- Removed the members.

Related information

Adding members to a team space on page 712

Deleting a team space

You might want to delete a team space when it is no longer needed.

Before you begin

You must have been assigned the role of a *Team Space Owner* of HCL OneTest[™] Server.

About this task

As a *Team Space Owner*, you can delete a team space that you do not need. When you delete a team space, it is a permanent deletion. You cannot undo the delete action on a team space.

If you delete the initial team space, then you can only view the **Team Space Dashboard** page without any navigation pane.

After you delete the team space, you can use the name of the team space again.

1. Log in to HCL OneTest[™] Server.

Result

The Projects page of the initial team space is displayed.

- 2. Click the **Settings** icon 🥺 from the left navigation pane.
- 3. Identify the team space that you want to delete.

You can either use the same team space where you are working or switch to any other team space.

4. Click Manage team space.

Result

The **Details** page is displayed.

- 5. Click Delete Team Space.
- 6. Confirm that you want to delete the team space when prompted.

If you proceed, the team space is deleted including all of its projects and members.

Results

You have deleted the selected team space.

What to do next

You can view the available team spaces on the **Team Space Dashboard** page. See Viewing team spaces on page 711.

After you delete a team space, the license that is used for that team space is released and is available to configure the other team spaces, if required. See Configuring licenses for team spaces on page 121.

Test assets and a server project

HCL OneTest[™] Server projects manage access to your test assets, which are stored in a Git repository. Projects are maintained in a team space. Projects are either public by default or private. Private projects are not discoverable by other users. You can either add your own project or you can request to be a member of another public project.

All the licensed users are assigned with a default role of a *Project Creator*. As a *Project Creator*, when you create a project immediately after logging in the application, the project is created in the initial team space. If you want to create a project in any specific team space, then you must become a member of that team space. When you add your own project, you can configure it now or later. Configuring the project includes adding details about the project, adding one or more Git repositories, optionally adding secrets, classifying encrypted datasets, and adding a change management system. To run test assets that are associated with an encrypted dataset, you must categorize the encrypted datasets by creating a classification. You can also add users to your project to access your test assets only if the users are the members of that team space. To use Jira to create defects for the tests available in your project, you must configure the Jira server for your project on HCL OneTest[™] Server.

Related information

Team space overview on page 108 Becoming a team space member on page 719 Becoming a project member on page 733 Managing access to server projects on page 734 Managing repositories on page 739 Protecting API test assets by using secrets on page 747 Managing an encrypted dataset on page 754 Default user administration on page 85 Configuring the Jira server as a change management system on page 596

Working with projects in a team space

After you log in to HCL OneTest[™] Server, you must have a project to perform the test activities. To work with projects, you must create and configure projects.

Before you begin

You must have logged into HCL OneTest[™] Server.

About this task

You must be assigned with the role of an Owner, Tester, or Viewer of a project.

- 1. Go to the Projects page from the Initial Team Space Home page. See Viewing active projects on page 732.
- 2. Add a project. See Adding a project on page 727.

- 3. Add a repository. See Adding repositories to a server project on page 728.
- 4. Add secrets in secrets collections. See Secrets configuration on page 731.
- 5. Encrypt the data set resources. See Data security.
- 6. Configure a change management system. See Configuration of a change management system on page 592.
- 7. Add members to a project and configure their roles. See Adding users to a project on page 731.
- Select a global branch in a project to view the test assets or resources maintained in the repositories. See Selecting the global branch in a project on page 745
- 9. Perform the following tasks based on the type of test assets or resources that you want to run:
 - a. Add agents to your project, if you are using remote agents as a location to run certain tests. See Adding a performance agent to a project on page 291.
 - b. Add remote Dockers, if you are using a remote Docker host as a location to run tests. See Adding a remote Docker host to the project for running tests on page 306.
 - c. Read the considerations that you must take into account before you configure a run or start a virtual service. See Prerequisites for running virtual services on page 468.
 - d. Read the considerations that you must take into account before you configure a test run. See Prerequisites to running tests on page 277.
- 10. Configure a run of the test asset or resource. See Test run configurations on page 327.
- 11. View the progress of a test run. See Viewing the progress of running test assets on page 457.
- 12. Manage a running test. See Management of running tests on page 453.
- 13. View the results of a test run after the run is completed. See Test results on page 513.
- 14. Review the test results and create defects for test runs from the Results page. See Creating Jira issues for tests that ran on page 598.

Results

You have performed all the tasks with the projects.

Repository considerations for a server project

To collaborate with other project stakeholders, you can open test assets from a local clone of the Git repository, pull project test assets from a Git repository, and push changes made to your local test assets to a Git repository. Before you add a project and add a repository to that project, you must consider some information about repositories.

Consider the following sections about using Git repositories with HCL OneTest[™] Server. For more information about installing, setting up, and using Git, see the <u>Git documentation</u>.

Git

You must install Git or upgrade to the supported version if you already have installed Git. See System Requirements on page 13.

Repositories and user identities

After you install Git, you must set up your Git repository and set up access for members. You must ensure that the repository contains your test assets.

Optionally, you can use a command line utility or Git tool to access the repository, upload your test assets, fetch or pull from the repository, push to the repository, clone the repository, and other operations you want to perform in Git.

Local and shared repositories

After you create a remote or shared repository in Git, you can create a local version of the repository by cloning the remote repository. You must ensure that your test assets are available in the remote repository and are also cloned to the local repository.

Alternatively, if your test assets are on your local system, you can set up a Git repository in the bare mode, add the project files to the local repository, and then commit and push from the local repository to the remote repository in Git by using your preferred method.



Note: While copying the test assets from your local system to the repository, you must ensure that you copy the entire project that contains the test assets.

User authentication for the Git repository

The administrator can set up different types of authentication for accessing the Git repository. HCL OneTest[™] Server supports the following authentication types:

- HTTP with user name and password
- HTTP without user name and password
- HTTPS with user name and password
- HTTPS without user name and password
- SSH with SSH key and passphrase
- SSH with SSH key and without a passphrase

Based on the authentication type that is set for a repository, you must provide the same authentication values in HCL OneTest[™] Server when you add a repository.

Test assets

You must complete the following tasks in the desktop client where you are authoring your test before you check in and commit the test assets to the Git repository.

Test type	Task	More information
API suite in HCL OneTest™ API	Change the local stub to a remote stub.	See Test run considerations for API Suites or API tests on page 279.
	Add the library files.	

Adding a project

The first step is to add a project and provide some details about it.

Before you begin

To add one or more projects to manage access to your test assets, you must log in to HCL OneTest[™] Server by providing the application URL in a browser.

If you are a new user, and LDAP and Active Directory are not configured, then you must first sign up by completing a form that specifies user information such as an email, user name, and password. You can then log in by using that information.

You must be a member of any licensed team space.

About this task

As a licensed user, you are by default assigned as both *Project Creator* and *Architect* role for the initial team space. You must select a team space to create a project.

You can view all the team spaces in the **Team Space Dashboard**. To create a project in any team space, you must be a member of that team space and assigned a *Team Space Owner* or *Project Creator* role in that team space.

After you select a team space from the **Team Space Dashboard**, you can add a project and give it a name and description.

1. Log in to HCL OneTest[™] Server.

Result

The Projects page of the initial team space is displayed.

2. Click **New project** or icon from the navigation pane to create a project in the team space where you are working.

Alternatively, if you want to create a project in any other team space, then switch to another team space from

the **Settings** icon 😳 in the navigation pane, and then create a project.

Result

The Details page is displayed.

Results

You have successfully created a project.

What to do next

You can modify your project configuration. You can also add a repository to your project.

Related information

Default user administration on page 85 Changing the visibility configuration of a project on page 733 Adding repositories to a server project on page 728

Adding repositories to a server project

You can add a single repository individually or multiple repositories simultaneously to a server project to access assets and resources that are available in the repositories.

Before you begin

You must have completed the following tasks:

- Added a project on HCL OneTest[™] Server.
- Been granted permission and you must have set up your credentials to access the remote repositories in a repository domain.

About this task

As a project owner or a tester, you can add a single repository or multiple repositories to your project. You can use the information in the following table to decide the method for adding repositories to your project:

When	Action
 You want to add any of the following repositories: A single repository owned by you. A single repository owned by other people. The repositories that are in different domains. 	You can add individual repositories one at a time. You must then provide the complete URL of the repository along with the required credentials to authenticate the connection to the repository from HCL OneTest [™] Server. For example, the URL to a single repository can be as https://github.com/ <user>/<reposito- ry>.git. You must provide the user name and pass- word to access this repository.</reposito- </user>
 You want to add any of the following repositories: Multiple repositories that are owned by you and are contained in the same domain. Multiple repositories that are owned by others and are contained in the same domain. 	You can add all the repositories simultaneously that are in the same domain. You must then provide the URL of the repository domain along with the required credentials to authenticate the connection to the repository from HCL OneTest [™] Server.

When	Action
	For example, the URL of the repository domain can be as
	https://github.com. You must select the platform
	and provide your personal access token to access the
	repositories.

1. Log in to HCL OneTest[™] Server and open the team space that contains your project.

2. Open your project either from the navigation pane or from the My Projects page.

The **Overview** page of the project is displayed.

- 3. Click **Manage > Configuration** from the navigation pane.
- 4. Click the REPOSITORIES tab.
- 5. Click Add repository.

The Add repository dialog is displayed.

You can either choose to add a single repository individually or multiple repositories simultaneously from a single domain.

- 6. Perform either of the following actions:
 - To add a single repository, go to Step 7 on page 729.
 - To add multiple repositories from a domain, go to Step 8 on page 730.
- 7. Perform the following steps to add individual repositories at a time:
 - a. Enter the complete URL of the repository in the Git URL field.

For example, the URL to a single repository can be as ${\tt https://}$

github.com/<user>/<repository>.git.

The required authentication fields are displayed that depend on the protocol you specified in the URL.

If	Then
The repository URL contains <i>http</i> or <i>https</i>	The following fields for authentication are dis- played: • Username • Password
The repository URL contains git@	The following fields for authentication are dis- played: • SSH/Deploy Key • Passphrase

- Note: If you use SSH to connect to a remote repository and HCL OneTest[™] Server displays an Auth Fail error, you can resolve this error by regenerating your SSH keys by using the -**m PEM** option.
- b. Enter the credentials to authenticate the connection to the repository.
- c. Click Add to add the repository to your project.

You can add other individual repositories by specifying the URL and performing the actions in Step 7 on page 729.

- Perform the following steps to add multiple repositories simultaneously that are contained in the same domain:
 - a. Enter the URL of the repository domain in the Git URL field.

For example, the URL of the repository domain can be as https://github.com.

- b. Select the platform from the list under Platform where your repositories reside.
- c. Enter your personal access token to authenticate your connection to the repository domain.



Note: If you do not have your *personal access token*, you can click **Generate** to generate your *personal access token* and use the token to authenticate your connection.

d. Click Next.

The connection to the repository domain is established and all the repositories that you own are listed. The time when the repository was last updated is displayed in the **Last updated** column.

- e. Select the repositories that you want to add to your project.
- f. Click Add.
- Note: Depending on the size of the repository that you are adding, it can take a few to several minutes to add the repository to your project on the server.

All the repositories that you selected are added to your project and are listed on the Repositories page.

Results

You have added individual repositories or multiple repositories to your project on the server.

What to do next

You can perform the following actions on the repository that you added:

- Update the authentication credentials if they are changed in the Git repository configuration. See Updating the authentication credentials of the repository on page 743.
- Delete a repository if it is no longer required. See Deleting a repository on page 743.
- Refresh a repository to fetch and synchronize changes from the remote repository. See Refreshing repositories manually on page 744.
- Configure a webhook to notify you when there is a push event in the remote repository. See Creating webhooks on page 746.

Secrets configuration

If you are working with an API suite and the project test asset contains environment variables that are required for the test runs, you must configure the environment variables as secrets in a secrets collection by using the **Secrets** tab. Configuring secrets enable the API suite to run correctly on HCL OneTest[™] Server.

Related information

Protecting API test assets by using secrets on page 747

Adding users to a project

You can add users to your server project so they can access your test assets.

Before you begin

- · You own a project.
- The users you want to add to your project must be the members of the team space of that project.

About this task

As a project owner, you can add other users to your public or private project. For example, if you have a large number of test assets that must be run, you might want your test team to help run them, and see the results.

1. Log in to HCL OneTest[™] Server.

Result

The Projects page of the Initial Team Space is displayed.

- 2. Select the project for which you want to add the users.
- 3. Click the **Settings** icon 🔯 on the Project card.
- 4. Add users by entering the user name of the user you want to add. You can add a partial name and then press the **Enter** key to see the user that you want to add.
- 5. Select that user and then assign a role.
- 6. Click Viewer, Tester, or Owner. When you add a user, the default role is Viewer.

The added user after logging in can see the owner's project in their list of **My Projects**.

7. Repeat the applicable steps to add another user.

Results

You have successfully added users to your project.

What to do next

You can add or remove roles to one or more projects that you own. All users can request to be a member of another public project.

Related information

Becoming a project member on page 733

Managing access to server projects on page 734

Viewing active projects

After you log in to HCL OneTest[™] Server, you can view both active and archived projects in the **Initial team space**.

About this task

As a project owner, you can view your projects under the **My Projects** panel, and the projects that are created by other users as public projects are displayed under the **Other Projects** panel. You can view a list of all active projects that you created under **My Projects**. You can view a list of all archived projects under **Archived Projects**.

Log in to HCL OneTest[™] Server.

The Projects page is displayed.

You can view the following projects:

- The active projects that you created or added to as a member with either the *Tester* or *Viewer* role are displayed under the **My Projects** panel.
- The active projects that are created by others as public projects are displayed under the Other Projects panel.

Results

You have viewed the active projects that are created by you and other users in the team space.

What to do next

You can perform any of the following tasks:

- Create a project. See Adding details to a server project on page 727.
- Request to become a member of a project that is displayed under the **Other Projects** panel. See Becoming a project member on page 733.
- View the other pages in the team space and perform tasks on those pages. See Tasks in a team space on page 113.

Related information

Archiving or unarchiving server projects on page 736

Changing the visibility configuration of a project

After you create a project, you might want to change the visibility configuration of the project from the public, which is the default, to private.

Before you begin

You must have created a project.

1. Log in to HCL OneTest[™] Server.

Result

The **Projects** page of the initial team space is displayed.

2. Select the project from the left navigation pane.

Result

The project page is displayed.

3. Click Manage > Configuration > .

Alternatively, select a project, and then click the **Configure project** icon 🧐 on the project card.

Result

The **Details** page is displayed.

- 4. Select **Private** as the visibility mode of the project.
- 5. Click Save.

Results

You have successfully changed the visibility configuration of a project.

What to do next

You can add a repository to your project.

Related information

Default user administration on page 85

Becoming a project member

You might want to request to be a member of another project. New users without any projects might also want to be a member of an existing project.

About this task

As a project owner, you can add users to your public or private projects. All users can request to become a member of a public project.

My Projects

- Note: You can add a licensed user as a member of your project only if that user is the member of your team space.
 - 1. Request to be a member of another project. Search for the project that you want to join in the list of other projects from the project Home page. Click that Project card or the **Key** icon \mathscr{P} . Only public projects are visible in the list of projects.
 - 2. Confirm your request when prompted. If you agree, the project owner is notified. The project owner sees a pending request **Notification** icon on their Project card.

🚢 тургој		٢
No description. Owner: user55	20	•
Created: a month a Branch: master Test Suites: 59		40
Last Run Time: Nov	7 4, 2020 8:59 AM	
1	0/59	1/59
In Progress	Fail	Success

After opening the notification, the owner can see the user that is requesting access and can accept or decline it.

If the project owner accepts your request, you are added as a member of the project with a Viewer role. A Viewer role is the default role assigned and is restricted to specific actions.

You then see the project under My Projects on the Home page.

If the project owner declines your request, follow up with the project owner.

Results

You have successfully sent a request to become a member of another project.

Managing access to server projects

You might want to add or remove a project member role from your project.

About this task

As a project owner, you can assign access by specifying a role when you add a user to your project. You can also assign more access or remove access for a user. Roles enable users to perform tasks on project resources such as running tests and viewing test results.

Option	Description
Owner of a project	 All Tester's actions
	 Update, archive, list, and view a project
	 Assign, update, delete, and list user roles for
	project
	 Accept new member requests
	 Create, update, and delete a dataset classifi-
	cation in a project
	 Add, update, and remove an encrypted
	dataset from a classification
	 Update current row for a listed dataset in a
	project
	\circ Delete, list and view a report
	\circ Update, delete, and list a repository in a
	project
	\circ Get the test assets from a repository in a
	project
	\circ Create, update, delete and list secrets in a
	project
	\circ Create, update, delete, and list resource mor
	toring sources in a project
	\circ Get the content of a resource monitoring
	source in a project
	 Register, update, delete, and list resource
	monitoring agents
	\circ Create, configure, and delete the Jira change
	management system
	 Create and update defects in the Jira chang
	management system
	 Create and update components in the system
	model
Tester of a project	 All Viewer's actions
	 List repositories in a project
	 Run a test and create a report
	 Stop a test while running

1. Choose the role in a project based on its associated actions.

Option	Description
	 Get the test assets from a repository in a project Get a list of datasets in a project Get the content of a dataset Update the current row for a listed dataset in a project Add, update, and remove an encrypted dataset from a classification Delete a report if you created the report Create and update defects in the Jira change management system Create and update components in the system model
Viewer of a project	 List your own roles on a project List running tests List and view a report List resource monitoring sources in a project Get the content of a resource monitoring source in a project List the resource monitoring agents View components in the system model View defects in the Jira change management system
Non-member of a project	 Request to be a member of a project

2. Open the project that you own.

From the project details, you can see a list of project members for your project and then add or remove a members role.

3. Add or remove the member access by using the **Menu** icon next to each user in the member list.

Archiving or unarchiving server projects

You can archive a project when that project is no longer needed but you want to retain it for future reference. If you do want to use an archived project, you can unarchive it.

About this task

As a project owner, you can archive inactive projects. Archived projects are not visible to users or project members, but owners can show or hide their archived projects. You can view the list of all archived projects from the navigation pane. Archived projects can be unarchived.

Note:

• To archive a project:

- 1. Log in to HCL OneTest[™] Server.
- 2. Select your project from the Projects page.
- Click the Configure project icon O on the project card.
 Result
 The Details page is displayed.
- 4. Click Archive Project.
- 5. Confirm that you want to archive the project when prompted.

If you proceed, the project is archived and is hidden from My Projects.

• To view an archived project:

- 1. Log in to HCL OneTest[™] Server.
- 2. Select your team space.

3. Click Archived Projects.

Result

A list of all archived projects that are associated with you is displayed under **My Projects** and the archived projects that are associated with others are displayed under **Other Projects**.

• To unarchive a project:

- 1. Log in to HCL OneTest[™] Server.
- 2. Click Archived Projects.
- 3. Select your archived project, and then click the **Configure project** icon 🗐 on the project card.

Result

The **Details** page is displayed.

- 4. Click Unarchive Project.
- Confirm that you want to unarchive the project when prompted.
 If you proceed, the project is unarchived and is shown under My Projects.

Deleting server projects

You might want to delete a project when the project is no longer needed, and you want to free up disk space.

About this task

As a project owner, you can delete a project that you no longer want. When you delete a project it is permanent. You cannot undo the delete project action.

After you delete the project, you can use the project name again.

- 1. Open the project that you want to delete.
- 2. From the project details, delete the project.
- 3. Confirm that you want to delete the project when prompted. If you proceed, the project is deleted including all of its test assets, results, and members.



Note: The repository that you used for the project is not deleted.

An overview of test assets, modifications, and scheduled runs

After you configure a project with one or more Git repositories and run some test assets, you can view statistics about those test assets.

From the **Overview** page, several cards display charts, sliders, and tables of the statistics of the test assets in your server project. You can click some of the charts, sliders, or tables to see more information, such as the progress of a scheduled run or the results of a run. You can also review some statistics by date and see more details such as the proportion of test assets by type.

You can view a server project, which might contain multiple repositories and multiple branches, by selecting the name of the branch from the **Branch** drop-down list. For more information about selecting branches, see Selecting the global branch in a project on page 745.

The **Members** area displays the total number of users who have access to the project. You can click the number to view the details of all the members. The **Owner** area displays the username of the project owner.

Test suites

This card displays a slider of the percentage of test suites by type. A test suite is a collection of tests, including schedules, compound tests, API Suites, and AFT Suites. You can hover over the slider and see the proportion of test suites by test suite type. The number of suites shown are relative to the selected branch.

Individual tests

This card displays a slider of the percentage of individual tests by type. You might have performances tests, API tests, or UI tests according to the desktop clients that you used to create the tests. You can hover over the slider and see the proportion of individual tests by type. The number of tests shown are relative to the selected branch.

Execution results

This card displays a chart of the proportion of test suites that were run by status and by date. If no date is selected, the card displays all the run results associated with the project since it was created. You can

see the run results by clicking a test or Suite status. You can also hover over the chart and see the test or Suite status and the proportion of test assets. You can view statistics by tests or Suites that ran.



- The results shown are generated from tests or Suites run.
- The statistics exclude canceled runs of tests or Suites.
- The number of Suites and individual tests that are associated with your project are shown on the **Home** page along with a verdict summary. You can see the run results by clicking a verdict. You can also see the last date and time when you ran one or more test assets.
- The number of suites shown are relative to the selected branch.

Last run

This card displays a table of the last three runs by date and time. You can see the run results by clicking each last run.

New or modified

This card displays a chart of new and modified test assets that were made in your Git repository for a week or for the last seven days based on a selected date range. You can hover your mouse over each bar in the chart and see the proportion of test assets by type. The data shown is relative to the selected branch.

Scheduled runs

This card displays a table of the next three scheduled runs by date and time. You can see the progress of a scheduled run by clicking each scheduled run.

Related information

Test assets and a server project on page 724

Managing repositories

After you create a project in HCL OneTest[™] Server, you can add repositories that contain test assets and resources to the project. You can also change the repository details, update the user credentials of a repository, delete a repository, create a webhook for the configured repository.

Tasks in a repository

To add a repository in your project and work on the repository, you can perform the tasks listed in the following table:

Task	More information
Adding a repository	Adding repositories to a server project on page 728
Updating the repository credentials	Updating the authentication credentials of the repository on page 743
Refreshing a repository	Refreshing repositories manually on page 744
Creating a webhook for the repository	Creating webhooks on page 746
Selecting the global branch	Selecting the global branch in a project on page 745
Deleting a repository	Deleting a repository on page 743

Adding repositories to a server project

You can add a single repository individually or multiple repositories simultaneously to a server project to access assets and resources that are available in the repositories.

Before you begin

You must have completed the following tasks:

- Added a project on HCL OneTest[™] Server.
- Been granted permission and you must have set up your credentials to access the remote repositories in a repository domain.

About this task

As a project owner or a tester, you can add a single repository or multiple repositories to your project. You can use the information in the following table to decide the method for adding repositories to your project:

When	Action
You want to add any of the following repositories:	You can add individual repositories one at a time.
 A single repository owned by you. A single repository owned by other people. The repositories that are in different domains. 	You must then provide the complete URL of the reposito- ry along with the required credentials to authenticate the connection to the repository from HCL OneTest [™] Server.
	For example, the URL to a single repository can be as https://github.com/ <user>/<reposito- ry>.git. You must provide the user name and pass- word to access this repository.</reposito- </user>
You want to add any of the following repositories:	You can add all the repositories simultaneously that are in the same domain.

When	Action
• Multiple repositories that are owned by you and	You must then provide the URL of the repository domain
are contained in the same domain.	along with the required credentials to authenticate the
 Multiple repositories that are owned by others 	connection to the repository from HCL OneTest [™] Server.
and are contained in the same domain.	For example, the URL of the repository domain can be as <pre>https://github.com. You must select the platform and provide your personal access token to access the repositories.</pre>

- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project either from the navigation pane or from the My Projects page.

The **Overview** page of the project is displayed.

- 3. Click Manage > Configuration from the navigation pane.
- 4. Click the **REPOSITORIES** tab.
- 5. Click Add repository.

The Add repository dialog is displayed.

You can either choose to add a single repository individually or multiple repositories simultaneously from a single domain.

- 6. Perform either of the following actions:
 - To add a single repository, go to Step 7 on page 741.
 - To add multiple repositories from a domain, go to Step 8 on page 742.
- 7. Perform the following steps to add individual repositories at a time:
 - a. Enter the complete URL of the repository in the Git URL field.

For example, the URL to a single repository can be as https://
github.com/<user>/<repository>.git.

The required authentication fields are displayed that depend on the protocol you specified in the URL.

If	Then
The repository URL contains <i>http</i> or <i>https</i>	The following fields for authentication are dis- played: • Username • Password
The repository URL contains git@	The following fields for authentication are dis- played:

If	Then
	 SSH/Deploy Key Passphrase

Note: If you use SSH to connect to a remote repository and HCL OneTest[™] Server displays an Auth Fail error, you can resolve this error by regenerating your SSH keys by using the **-m PEM** option.

- b. Enter the credentials to authenticate the connection to the repository.
- c. Click Add to add the repository to your project.

You can add other individual repositories by specifying the URL and performing the actions in Step 7 on page 741.

- 8. Perform the following steps to add multiple repositories simultaneously that are contained in the same domain:
 - a. Enter the URL of the repository domain in the Git URL field.

For example, the URL of the repository domain can be as https://github.com.

- b. Select the platform from the list under Platform where your repositories reside.
- c. Enter your personal access token to authenticate your connection to the repository domain.



Note: If you do not have your *personal access token*, you can click **Generate** to generate your *personal access token* and use the token to authenticate your connection.

d. Click Next.

The connection to the repository domain is established and all the repositories that you own are listed. The time when the repository was last updated is displayed in the **Last updated** column.

- e. Select the repositories that you want to add to your project.
- f. Click Add.



Note: Depending on the size of the repository that you are adding, it can take a few to several minutes to add the repository to your project on the server.

All the repositories that you selected are added to your project and are listed on the Repositories page.

Results

You have added individual repositories or multiple repositories to your project on the server.

What to do next

You can perform the following actions on the repository that you added:

- Update the authentication credentials if they are changed in the Git repository configuration. See Updating the authentication credentials of the repository on page 743.
- Delete a repository if it is no longer required. See Deleting a repository on page 743.
- Refresh a repository to fetch and synchronize changes from the remote repository. See Refreshing repositories manually on page 744.
- Configure a webhook to notify you when there is a push event in the remote repository. See Creating webhooks on page 746.

Updating the authentication credentials of the repository

If the authentication credentials of the Git repository which was added to your project are changed, then you must update the credentials of the repository in HCL OneTest[™] Server.

Before you begin

You must have completed the following tasks:

- Been assigned a Member or Project Creator role in a team space.
- Been assigned the Tester or Owner role in the project with access permissions to edit repositories.

About this task

In HCL OneTest[™] Server, the repository is refreshed at regular intervals to pull the latest changes committed to the Git repository. After you update your authentication credentials of the repository, the repository is refreshed to ensure that you have access to the Git repository and to the latest assets in the repository.

- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project either from the left navigation pane or from the My Projects page.
- 3. Click Manage from the left navigation pane.

The **Repositories** page of the project is displayed.

4. Click the Open action menu icon inline with the repository that you want to update, and then click Change....

The Edit Repository dialog is displayed.

5. Enter the new credentials, and then click Update.

The new credentials are updated and your access to the repository is retained.

Deleting a repository

You can delete repositories that you no longer require in your test environment.

Before you begin

You must have completed the following tasks:

- · Configured the repository that contains the test assets in your project.
- Been assigned a Owner or a Tester role with access to delete repositories.

About this task

You can delete a repository that you have configured for your project.

- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project either from the left navigation pane or from the My Projects page.
- 3. Click **Manage** from the left navigation pane.

The **Repositories** page of the project is displayed.

4. Click the Open action menu icon inline with the repository that you want to update, and then click Delete.

The **Delete repository** dialog is displayed.

5. Select the checkbox, and then click the **Delete** button.

The repository is deleted and removed from the list.

Refreshing repositories manually

You can manually trigger the refresh activity for a repository to instantly fetch and synchronize the changes from the remote repository.

Before you begin

You must have completed the following tasks:

- Configured the repository that contains the test assets in your project.
- Been assigned a Member or a Project Creator role.
- Been assigned a *Owner* or a *Tester* role.

About this task

Every two minutes, the repository is refreshed automatically. You can also manually trigger the refresh activity for a repository.

- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project either from the left navigation pane or from the My Projects page.
- 3. Click Manage from the left navigation pane.

The **Repositories** page of the project is displayed.

4. Click the **Open action menu** icon inline with the repository, and then select **Refresh**.

The refresh activity is triggered.

Note: The **Refresh** option is disabled when the refresh is in progress. After the refresh is completed, the **Refresh** option is enabled.

The following table lists the icons and their description based on the status of the refresh activity:

Refresh icon	Description		
0	The last refresh activity was successful.		
•	 The last refresh activity was successful but errors were found while processing some of the test assets. To view the error details of the test assets for a specific repository, you can click the arrow inline with the repository name. You can resolve the errors of these test assets in the Git server, and then refresh the server repository, if required. Note: The repository, which contains the branch that is selected in the Branch field, displays the unprocessed test assets for that branch. Other repositories display the unprocessed test assets assets for their default branch. 		
	The refresh activity was not successful due to any one of the following reasons: • Internal error • Connection issue • Authentication failure • Disk quota exceeded • Repository unreachable		

Results

You have manually refreshed the repository and the Last Refreshed field is updated with the following details:

- The time when it was last refreshed in the remote repository.
- Latest commit ID and message of the remote repository.

Selecting the global branch in a project

After you add one or more repositories to your project, you can start accessing all branches in all repositories of that project. You can select only one branch as a global branch from the list of branches in the **Execution**, **Datasets**, and **Overview** pages.

Before you begin

You must have completed the following tasks:

- Been assigned a Member or Project Creator role in a team space.
- Added at least one repository in your project.

About this task

You can access all the branches contained in all the repositories, which are added to the project, by using the **Branch** field on the **Execution**, **Datasets**, and **Overview** pages.

After you select a branch from any of the repositories as the global branch, this selection is retained for you as the global branch unless you change the branch on any of the following pages: **Overview**, **Execution**, or **Datasets** pages.



- When you add the first repository to a project, the global branch is set to the default branch of the repository.
- Branches are arranged in an increasing order of their names in the list.
- When you change the branch in one of the pages, then the same branch is displayed as selected in the other pages and the contents of that page displays the assets from the selected branch.
- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project either from the left navigation pane or from the My Projects page.

The project **Overview** page is displayed.

3. Select a branch from the Branch field.

The branch that you select on any of the following pages is reflected in the rest of the other pages and the test assets are filtered based on the global branch selection on each of these pages.:

- Overview
- Execution
- Datasets

Results

You have selected a global branch in a project.

Creating webhooks

You can configure a webhook for a repository in the Git server to notify HCL OneTest[™] Server whenever there is a push event in the remote repository. Then, the refresh activity is triggered to fetch the latest changes to the server repository.

Before you begin

You must have completed the following tasks:

- · Configured the repository that contains the test assets in your project.
- Been assigned a Member or Project Creator role in a team space.
- Been assigned the Tester or Owner role in the project.
- 1. Log in to HCL OneTest[™] Server and open the team space that contains your project.
- 2. Open your project.
- 3. Go to the Repositories page.
- 4. Click the Menu icon and then click Webhook.

The Webhook Configuration dialog is displayed.

5. Copy the URL and the Secret of the repository that you want to configure.



Note: The URL and the Secret details are specific to a repository.

6. Click the link of the repository for which you want to configure the webhook.

The remote repository page is displayed.

7. Paste the details, which you copied from HCL OneTest[™] Server, in the appropriate fields of the remote repository.

Results

You have configured the webhook for a repository in the Git server. The changes of the remote repository are synchronized in the repository of your project.

Protecting API test assets by using secrets

Secrets are key-value pairs that are created for your project in HCL OneTest[™] Server under a secrets collection. You can create secrets collections for your project that enable you or members in your project to use secrets at test runtime either in HCL OneTest[™] Server or in desktop clients.

The secrets collections in a project in HCL OneTest[™] Server has a separate access control list managed by the members with access to the secrets collections. Controlling access to secrets means controlling access to applications and systems under test. The introduction of secrets (under secrets collections) for a project has simplified managing access to separate environments. If a member of a project does not have access to a secret, for example, *a server credential* then the member cannot accidentally or maliciously run tests against that server. For example, tests that must access the database server by using the server credentials to retrieve stored data can only be run by a member if the access to the secrets is granted.

Note: Secrets and secrets collections are applicable to test assets authored in HCL OneTest[™] API that enable running tests in defined environments. Secrets are not applicable to tests authored in HCL OneTest[™] UI or HCL OneTest[™] Performance.

As a project member with the *Owner* or *Tester* role, you can create secrets collections in the project. You can grant or restrict access to the secrets collection that you create in the project.

Members with access to a secrets collection can access, edit, or delete the secrets collection in HCL OneTest[™] Server and can view secrets, edit secrets, or delete secrets.

Members with access to secrets collections can grant access to or remove the following:

- Other members added specifically
- All members with a specific role

Members in the project with the *Owner* or *Tester* role and with access the secrets collection can use the secrets in the secrets collection, in tests at runtime.

If you are configuring a project to run an API Suite with tests that refer to secret values, you must configure the secrets under a secrets collection by using the **SECRETS** tab. You must complete the following tasks:

- 1. Create a secrets collection. See Step 1 on page 749 in Managing secrets collections on page 748.
- 2. Add secrets in the secrets collection created. See Step 1 on page 751 in Creating a secret in a secrets collection on page 750.
- 3. Grant access to project members or member roles, who can access the secrets collection. See Step 1 on page 751 in Granting access to members or member roles on page 751.

Managing secrets collections

You can create secrets in a secrets collection for your project. Secrets are credentials required in certain tests during test runs. Secrets stored in the collection can be used by members to run tests on different environments and eliminates the need to store secrets in multiple locations. You can opt to edit or delete a secrets collection that you configured for your project any time after you create a secrets collection.

Before you begin

- You must have created a project on HCL OneTest[™] Server. See Test assets and a server project on page 724.
- You must have completed the following tasks before you edit or delete a secrets collection:
 - Configured a secrets collection in your project.
 - Created secrets in the selected secrets collection. See Creating a secret in a secrets collection on page 750.

- You must be a member with the *Owner* or *Tester* role to create a secrets collection.
- You must be a member with access to the secrets collection to edit or delete the secrets collection. See Granting access to members or member roles on page 751.

About this task

You must configure secrets collections in your project so that the members of the project can use secrets contained in a collection during test runs. You can configure secrets so that you can use them in different test environments.

As a member with access to the secrets collection, you can opt to edit or delete a secrets collection configured in a project. For example, you might want to edit the secrets collection name or delete the secrets collection if the testing environment has changed and if secrets that are configured earlier are not required.

- To create a secrets collection, go to Step 1 on page 749.
- To edit or delete a secrets collection, go to Step 4 on page 749.

To create a secrets collection:

- To create a secrets collection while configuring a new project in the HCL OneTest[™] Server UI, open the SECRETS tab in the Project Configuration and create a secrets collection. Use Add Collection.
- 2. Alternatively, to create a secrets collection in an existing project, complete the following steps:
 - a. Log in to HCL OneTest[™] Server and from the User Interface (UI) open the project listed under **My Projects** for which you want to create a secrets collection.
- b. Open the Project Configuration page, and then open the SECRETS tab to create a secrets collection.3. Enter a name for the secrets collection as its *Identifier*.
 - Tip: You can create a secrets collection that contains secrets for a particular test environment in your project. For example, the secrets collection *test_env* can contain secrets that application testers can use in tests that they run while the secrets collection *dev_env* can contain secrets that application developers can use in tests they run.

A message is displayed for the successful creation of the secrets collection.

The secrets collection created is displayed.

You can add secrets to the secrets collection you created.

To edit or delete a secrets collection:

- 4. Log in to HCL OneTest[™] Server and from the UI open the project listed under **My Projects**.
- 5. Open the secrets collection from the **SECRETS** tab in the Project Configuration page.

If there are multiple secrets collections in the project, select the secrets collection that you want from the list.

- To edit a secrets collection, go to Step 6 on page 750.
- To delete a secrets collection, go to Step 7 on page 750.

- 6. To edit a secrets collection, complete the following steps:
 - a. Click the **Edit** icon \swarrow to edit the selected secrets collection.



Note: The Edit icon 2 is displayed only for the project owner.

b. Edit the name of the secrets collection, and update the secrets collection.

The secrets collection is updated with the updated name.

7. To delete a secrets collection, click the **Delete** icon III to delete the selected secrets collection.

The selected secrets collection is removed from the list of secrets collections configured for the project.

Results

You have completed the following tasks:

- Created a secrets collection for your project.
- · Edited the name of a secrets collection in your project.
- Removed a secrets collection from your project.

What to do next

- If you have created a new secrets collection, you must add secrets to your secrets collection.
- You must provide access to project members or member roles to the secrets collection by selecting members or member roles.

Creating a secret in a secrets collection

You must create secrets in the secrets collections configured in your project so that the secrets contained in a collection can be used in certain tests by members of the project with access to the secrets collections during an API suite run.

Before you begin

You must have created a project on HCL OneTest[™] Server and configured a secrets collection in your project.

You must be a member with access to the secrets collection.

About this task

You can also configure secrets such that the secrets can be used across different test environments by members with access to the secrets collection. Secrets correspond to the environment variables or tags that you create in a HCL OneTest[™] API project specific to an environment.

- 1. To create a secret under a secrets collection while configuring a new project in the HCL OneTest[™] Server UI, select the secrets collection listed in the **SECRETS** tab in the Project Configuration page and create a secret under the secrets collection.
- 2. Alternatively, to create a secret under a secrets collection in an existing project, complete the following tasks:
 a. Log in to HCL OneTest[™] Server and from the UI open the project listed under My Projects.
 - b. Open the secrets collection from the **SECRETS** tab in the Project Configuration page.
- 3. Enter a name for the secret as its *Identifier* and enter the password as the *Value* for the secret.

For example, under the secrets collection (named as test_env), enter the name of the secret to access a database as dbcred and enter the password required to access the database as its value.

A message is displayed for successful creation of the secret.

Results

You have created secrets in the selected secrets collection for your project.

What to do next

- You can view, edit, or delete the secrets created under a secrets collection any time you want.
- You can use the secrets in the tests that require these secrets during test runs.

Granting access to members or member roles

You can grant or revoke access to the secrets collection in your project to individual members with different roles or the all members with a specific role. Without access to the secrets collection, members cannot view, create, edit, delete, or use the secrets in the secrets collection.

Before you begin

You must have created a project on HCL OneTest™ Server and configured a secrets collection in your project.

You must be a member with access to the secrets collection.

- 1. To grant access to a secrets collection while configuring a new project in HCL OneTest[™] Server UI, select the secrets collection listed in the **SECRETS** tab in the Project Configuration page.
- 2. Alternatively, to grant access to a secrets collection in an existing project, complete the following tasks:
 - a. Log in to HCL OneTest[™] Server and from the UI open the project listed under My Projects.
 - b. Open the secrets collection from the SECRETS tab in the Project Configuration page.
 If there are multiple secrets collections in the project, select the secrets collection that you want from the list.
- 3. To grant access to a secrets collection in a new project or an existing project, select from the following methods:

- To add all members with a specific role, click the role listed under Grant access to role. For example, if you select Testers, then all members in the project with a tester role are granted access to the secrets collection. You can select any role or all the roles listed.
- To select specific members to grant access to the selected secrets collection, enter the name or the email ID of the member in the field box and add them from the list that is displayed.



Note: Members added specifically are listed under **Members with access to this collection** but all the members granted access solely due to their roles are not listed.

Important: Irrespective of the role that the member (*Owner*, *Tester* or *Viewer*) was assigned in the project, the access to the secrets collections has to be specifically granted to the members from the SECRETS tab.

Removing access to a secrets collection

- 4. To remove access granted to all members with a specific role or a specific member, select from the following methods:
 - To remove all members with a specific role, click the role listed under **Grant access to role** to clear the selection. For example, if **Testers** is selected and you clear it, then all members in the project with a tester role are removed from the access list to the secrets collection.
 - To remove specific members with access to the secrets collection, select the member and click the Delete icon

Notes:

- Any member with access to the secrets collection can remove access of other members specifically added or of all members with a specific role.
- Members with access to the secrets collection can remove themselves from the access list.
 Members can do this when there is at least one member remaining in the list. After removing themselves, members cannot add themselves back to the access list and must be added by any of the other remaining members in the list.

Results

You have added members from your project or members with specific role to the access list of people who can access secrets in the selected secrets collection, or you have removed specific members or members with specific role from the access list.

What to do next

You can create secrets under secrets collections for your project.

Managing secrets

You can view, edit, or delete the secrets configured under a secrets collection any time after you have created secrets or after you were granted access to the secrets collection. You can change the value of the secret by editing the secret. You can delete secrets that you no longer require in your test environment.

Before you begin

You must have created a project on HCL OneTest™ Server and configured a secrets collection in your project.

You must have created secrets in the selected secrets collection or the secrets collection must contain secrets.

You must be a member with access to the secrets collection.

- 1. Log in to HCL OneTest[™] Server and from the UI open the project listed under **My Projects**.
- 2. Complete the following steps:
 - a. Open the secrets collection from the SECRETS tab in the Project Configuration page.
 - b. Optionally, select the secrets collection that you want from the list if there are multiple secrets collections in the project.

The secrets configured in the selected secrets collection are displayed.

3. Complete the steps for the task you want to perform as listed in the following table:

Task	Steps	
Viewing a secret val- ue	Click the Show icon ⁽⁽⁾) for the secret you want to view its value, which most likely is a password for the secret. The value configured for the secret is displayed.	
Editing a secret value	et value Click the Edit icon <i>P</i> for the secret you want to edit, and enter a new value for the cret as its <i>Value</i> . The value can be a password for the secret.	
	Note: You can only change the value of the secret.	
	The value of the selected secret is changed.	
Deleting a secret	Click the Delete icon 🔟 in the row of the secret you want to delete. After deleting it, the secrets list in the collection is removed from the list.	

Results

- You viewed the password configured of the secret under a secrets collection that you created or were granted access.
- You changed the secret value of the secret under a secrets collection in your project.
- · You deleted and removed the secret from the selected secrets collection in your project.

What to do next

You can use secrets in the tests that require these secrets during test runs.

Related information Test run configurations on page 327 Becoming a project member on page 733

Managing an encrypted dataset

You can use encrypted datasets to limit access to confidential information such as account number or passwords. You can arrange data by an appropriate category so that project members can use datasets more effectively in certain tests and protect them.

About this task

A dataset can contain classified information that other members can access with permission. As a project owner, you can group encrypted datasets into different classifications and enable project members to view and edit datasets and run tests associated with the encrypted datasets. After you have created a classification, you can change the classification for a dataset. You can also delete a classification if you do not require it in your test environment.



- You must grant access and provide an encryption key of an encrypted dataset to other members of the project to work with the encrypted dataset.
- A project member who has been added as a **Tester** role can work with the encrypted dataset.

Creating a classification

As a project **Owner**, you can organize encrypted datasets by creating a classification so that project members can use and protect datasets more efficiently.

Before you begin

You must have completed the following tasks:

- Created a project in . See Test assets and a server project on page 724.
- Configured the repository that contains the test assets in your project. See Adding repositories to a server project on page 728.
- Created at least one dataset and encrypted the dataset with an encryption key. See Dataset encryption on page 156.

About this task

After creating a classification, you can grant access and provide the encryption key to other members of the project to work with the encrypted dataset.

- 1. Log in to if you are not already logged in.
- 2. Open a project from the team space.
- 3. Click Manage, and then the DATA SECURITY tab.
- 4. Click New classification and enter a name for the classification.
- 5. Click Create.
- 6. Click the Add icon \oplus to select the encrypted dataset to become part of the new classification.
- 7. Select a dataset from the list and enter the encryption key in the **Password** field for the dataset, and then click the **Add** icon.

The encrypted dataset that is added to the classification is displayed.

DETAILS	REPOSITORIES	SECRETS	DATA SECURITY	
Classification				1
Credentials				*
Datasets				O
Name Encrypted Columns		olumns	Actions	
JqueryAccordion Tag programming languages2		nming languages2	/ 8	

What to do next

You can grant access to other project members to use the encrypted dataset.

Editing or deleting a classification

After you have created a classification, you can edit the name of the classification. You can also delete a classification when it is not required in your test environment.

Before you begin

You must have completed the following tasks:

• Created at least two classifications. See Creating a classification on page 754.

About this task

You can opt to edit or delete a classification for your project any time after you create a classification. For example, you might want to edit the name of the classification or delete the classification if the classification that is created earlier are not required.



Note: You must be a project Owner to create, edit, or delete a classification.

- To edit a classification, go to Step 1 on page 756.
- To delete a classification, go to Step 2 on page 756.
- 1. Perform the following steps to edit a classification:
 - a.
 - b.
 - c. Select a classification that you want to edit from the list.

DETAILS	REPOSITORIES	SECRETS	DATA SECURITY		
Classification				1	8
class					*
class					
Credentials					
Imp Credentials					

- d. Click the **Edit** icon \checkmark to edit the selected classification.
- e. Edit the name of the classification, and then click Save.
- 2. Perform the following steps to delete a classification:
 - а.
 - b. Select a classification that you want to delete from the list.
 - c. Click the **Delete** icon III.

d. Click Delete in the Delete classification window to confirm the deletion of the classification.



Note: Before deleting a classification, you must move the added encrypted datasets to another classification else the delete icon is disabled.

Results

- You have edited the name for a classification in your project.
- You have deleted a classification.

Moving an encrypted dataset to another classification

When you add many encrypted datasets to the same classification, you can move some of them to another classification.

Before you begin

- 1.
- 2.
- 3. Select a classification from the list that has the encrypted dataset.
- 4. Click the Edit icon 2 from the Actions column of a dataset.
- 5. Select a classification from the list and enter the encryption key of the dataset in the Password field.
- 6. Click Save.

A classification for a dataset is updated successfully.

DETAILS	REPOSITORIES	SECRETS	DATA SECURITY		
Classification				1	8
Imp Credentials					*
Datasets					0
Name		Encrypted C	olumns	Action	ns
JqueryAccordio	n	Tag program	ming languages2	1	d

Results

You have moved the encrypted dataset from one classification to another.

Removing a dataset from the classification

You can remove a datasets added to a classification when they are no longer required.

Before you begin

You must have completed the following tasks:

- Created a classification and added the encrypted dataset to it. See Creating a classification on page 754.
- 1.
- 2.
- 3. Select a classification from the list that has an encrypted dataset.
- 4. Click the **Delete** icon III from the **Actions** column of a dataset.
- 5. Click Remove in the Change the classification for the Dataset window.



Note: Removing dataset from the classification also removes the password stored in for encrypted data. You must enter the password again to gain access to the encrypted columns.

Results

You have removed the datasets from a classification.

Granting classification access to members or members roles

You can grant or revoke access to the classification in your project to individual members with different roles or the all members with a specific role. Without access to the classification, members cannot view, create, edit, delete, or use the classification.

Before you begin

You must be a project **Owner** and have completed the following tasks:

- •
- Added one or more users to your project. See Adding users to a project on page 731.
- •
- Created at least one classification. See Creating a classification on page 754.
- 1.

2.

- 3. Select the classification from the drop-down list.
- 4. Choose any of the following methods to grant access to a member: **Choose from:**

- To add all members with a specific role, click the role listed under **Grant access to role**. For example, if you select **Testers** then all members in the project with a tester role are granted access to the selected classification. You can select any role or all the roles listed.
- To select specific members to grant access to the selected classification, enter the name or the email ID of the member in the Grant access to member field and add them from the list that displays.
- Note: Members added specifically are listed under Members with access to this classification but the members added for a role are not displayed.
- Important: Irrespective of the role that the member (Owner, Tester or Viewer) was assigned in the project, the access to the classification has to be specifically granted to the members from the DATA SECURITY tab.
- Choose any of the following methods to revoke access from a member: Choose from:
 - To remove all members with a specific role, click the role listed under **Grant access to role** to clear the selection. For example, if **Testers** is selected and you clear it, then all members in the project with a tester role are removed from the access list to the classification.
 - To remove specific member with access to the classification, select the member and click the **Delete** icon **O**.

Notes:

- Any member with access to the classification can remove access of other members specifically added or of all members with a specific role.
- Members with access to the classification can remove themselves from the access list provided that there is at least one member in the list. After removing themselves, members cannot add themselves back to the access list and must be added by any of the other members in the list.

Results

You have granted or revoked the classification access to project members.

Related information

Adding a project on page 727

Managing notifications

HCL OneTest[™] Server provides a feature to display notifications for different events within the user interface (UI) of HCL OneTest[™] Server. You can configure an SMTP server on HCL OneTest[™] Server when you want HCL OneTest[™] Server to send out notifications about the different events as emails to the subscribed users.

HCL OneTest[™] Server provides you the following features to receive notifications about server events:

Channels	Description	
In-app	Notifications are displayed within the UI of HCL OneTest™ Server.	
SMTP	Notifications are sent by HCL OneTest [™] Server in emails to subscribed users.	

When you register as a user in HCL OneTest[™] Server, the in-app and SMTP channels are automatically subscribed for you.

Managing notifications in the server UI

Viewing the in-app notifications or notifications in the server UI is a feature that is enabled automatically when you register as a user in HCL OneTest[™] Server.

You are subscribed to the following channels for all events as the default option when you sign up on the server.

In-app

• SMTP

If you want to receive notifications about specific events and not all events, you can change the default subscriptions and modify your subscription for the server events. You can also view the in-app notifications that are displayed for you. See Managing in-app notifications on page 761.

Managing SMTP notifications

You, as a Server Administrator or Team Space Owner can configure an existing Simple Mail Transfer Protocol (SMTP) server so that HCL OneTest[™] Server can send out notifications about the server events in emails to the registered users. See Configuring an SMTP server to manage email notifications on page 771.

You are subscribed to the following channels for all events as the default option when you sign up on the server.

- In-app
- SMTP

If you, as a registered user of HCL OneTest[™] Server want to receive the email notifications about specific events and not all events, you can change the default subscriptions and modify the subscription for the server events. See Managing email notifications on page 766.

Managing in-app notifications

You can manage the in-app notifications by changing the subscriptions that are automatically enabled for you for all server events. You can view the server events that are automatically subscribed and then change the subscription for any or all events. For example, as a team space owner, you can choose to be notified when members of the team space create new projects or delete their projects but not be notified when tests are run.

Before you begin

•

•

About this task

The in-app notifications that are automatically subscribed for you, are displayed in the server UI under the following categories for the server events that occur:

Category Notifications displayed	
User	Include information about actions performed by team space members in the team space.
System	Include information about actions performed by registered users at the server level.

1.

- 2. Select from the following actions that you want to perform:
 - Modify notification settings. Go to Step 3 on page 761.
 - View notifications. Go to Step 4 on page 763.
 - Unsubscribe from the in-app notifications. Go to Step 5 on page 764.
- 3. Perform the following steps to modify the notification settings:
 - a. Click the **User** icon (2) on the menu bar.
 - b. Click Notification Settings.

The Notification Settings dialog is displayed.

c. Change the language in which you want to receive the notifications, if you do not want to use the default language.

The default language is the locale language set on the computer that hosts .

You can notice that for each of the server events, both the channels are displayed as selected, which is the default selection unless you have modified the subscriptions.

Notifications	Channels	1
Execution Completed with Verdict Error	2 channel(s) ▽	
Execution Completed with Verdict Fail		
Execution Completed with Verdict Pass	V In App	L
	SMTP	
Execution Completed without any Verdict	Z channel(s)	

- d. Identify the server events for which you want to change the subscription.
- e. Perform the actions indicated in the following table to clear the subscriptions for server events that you do not want to be notified and to select the in-app subscription for the server events that you want to be notified.

When	Action
You do not want to receive the in-app notifications for a specif- ic server event.	 Perform the following steps: Expand the channel list in the row of the server event. Clear the checkbox in the header row to clear the subscriptions to both channels. Click Apply. You have unsubscribed from both channels and the in-app notifications for the server event is not displayed for you when the event occurs.
You want to receive the in-app notifications for a specific serv- er event.	 Perform the following steps: i. Expand the channel list in the row of the server event. ii. Select any of the following actions: Clear the SMTP checkbox. The In App selection is retained while the checkbox in the header row and for the SMTP options are cleared. Clear the checkbox in the header row to clear the subscriptions to both channels, and then select the In App checkbox.
	In App checkbox. iii. Click Apply.

When	Action
	You have unsubscribed from the SMPT channel and retained the
	subscription for the in-app notifications for the server event.

- f. Go to Results on page 766.
- 4. Perform the following steps to view the in-app notifications:
 - a. Click the **Notifications** icon On the menu bar.

The Notifications dialog is displayed. The notifications are displayed in the following tabs:

- User
- System

The notifications in the **USER** tab is displayed as the default option.

- b. View the notifications in the **USER** tab.
- c. Click the SYSTEM tab to view the notifications at the server level.

You can find the information about the default notifications that you can view based on your role in the server as in-app notifications in the **USER** tab and **SYSTEM** tab.

Category	Notification details	or	or		
User notifications	Information about events at the server level or across team spaces performed by other team space owners.	~	~	×	×
	Information about events in the team space performed by other team space members.	~	×	×	×
	Information about events in the project performed by other project members.	×	~	~	×
	Information about events per- formed by you in a project.	×	×	~	~

Category	Notification details	or	or		
System notifications	Information about events at the server level or across team spaces.	~	~	×	×
	Information about events in the team space performed by other team space members.	~	~	×	×
	Information about events in the projects at the team space lev- el performed by other project members.	~	~	×	×

d.


5. Perform the following steps to unsubscribe to the in-app notifications:

a.

b.

c. Click the **Open action menu** icon in the row of **Notifications**.

The following panel is displayed:



You can notice that the subscriptions to in-app, SMTP, and all channels are displayed as selected.

d. Perform the actions indicated in the following table for the option you want:

When	Action	Results in		
You do not want to receive any in-app notifications.	Click the Unsubscribe from In App option, and then click Ap - ply .	The in-app channel selection for all server events is cleared and you are unsubscribed from the in-app channel. The SMTP noti- fications is displayed as select- ed for subscription for all server events.		
You do not want to receive any in-app or the SMTP email notifi- cations.	Click the Unsubscribe from all Channels option, and then click Apply.	The in-app channel and the SMTP channel selections for all server events are cleared and you are unsubscribed from both the channels. No channel is dis- played as selected for subscrip- tion for all server events.		
You want to subscribe to the in- app notifications for all server events.	Click the Subscribe to In App option, and then click Apply .	The in-app channel for all server events is selected and you are subscribed to the in-app chan- nel. The in-app notifications is		

When	Action	Results in	
		displayed as selected for sub- scription for all server events.	
You want to receive notifica- tions as in-app and as SMTP email notifications.	Click the Subscribe to all Chan- nels option, and then click Ap- ply .	The in-app channel and the SMTP channel are displayed as selected for all server events and you are subscribed to both the channels.	

e.

Results

You completed the following tasks:

- Modified the notification subscriptions.
- Viewed the notifications displayed for you in the USER tab and SYSTEM tab.
- Unsubscribed from or subscribed to either the in-app channel or both the channels.

Related information

Managing notifications on page 760

Managing email notifications

You can manage the email notifications by changing the subscriptions that are automatically enabled for you for all server events. You can view the server events that are automatically subscribed and then change the subscription for any or all events. For example, as a project owner, you can choose to be notified when members of the project add a repository or run a test in a team space but not be notified when projects are created in the team space.

Before you begin

• Ensured that the or has configured a Simple Mail Transfer Protocol (SMTP) server. See Configuring an SMTP server to manage email notifications on page 771.

About this task

The email notifications in the SMTP channel are automatically subscribed for you for all server events. You can view the server events that are subscribed in the **Notifications Settings** dialog. You can either unsubscribe from the SMPT channel or change your subscriptions for the server events for which you do not want the email notifications.

1.

- 2. Select from the following actions that you want to perform:
 - Modify notification settings. Go to Step 3 on page 767.
 - Unsubscribe from the email notifications. Go to Step 4 on page 768.
- 3. Perform the following steps to modify the email notifications settings:
 - a. Click the **User** icon (2) on the menu bar.
 - b. Click Notification Settings.

The Notification Settings dialog is displayed.

c. Change the language in which you want to receive the email notifications, if you do not want to use the default language.

The default language is the locale language set on the computer that hosts .

You can notice that for each of the server events, both the channels are displayed as selected, which is the default selection unless you have modified the subscriptions.

Notifications	Channels	:
Execution Completed with Verdict Error	2 channel(s)	
Execution Completed with Verdict Fail		
Execution Completed with Verdict Pass	In App	
	SMTP	
Execution Completed without any Verdict	2 channel(s)	V

- d. Identify the server events for which you want to change the subscription.
- e. Perform the actions indicated in the following table to clear the subscriptions for server events that you do not want to be notified and to select the SMTP subscription for the server events that you want to be notified in emails.


When	Action
You do not want to receive the email notifications for a specific server event.	Perform the following steps: i. Expand the channel list in the row of the server event. ii. Clear the checkbox in the header row to clear the subscrip- tions to both channels. iii. Click Apply .

When	Action
	You have unsubscribed from both channels and the email notifi- cations for the server event are not sent to you when the event oc- curs.
You want to receive the email notifications for a specific serv- er event.	 Perform the following steps: i. Expand the channel list in the row of the server event. ii. Select any of the following actions: Clear the In App checkbox. The SMTP selection is retained while the checkbox in the header row and for the In App options are cleared. Clear the checkbox in the header row to clear the subscriptions to both channels, and then select the SMTP checkbox. iii. Click Apply. You have unsubscribed from the in-app channel and retained the subscription for the email notifications for the server event.

f. Go to Results on page 770.

- 4. Perform the following steps to unsubscribe to the email notifications:
 - а.
 - b.
 - c. Click the **Open action menu** icon in the row of **Notifications**.

The following panel is displayed:



You can notice that the subscriptions to in-app, SMTP, and all channels are displayed as selected.

d. Perform the actions indicated in the following table for the option you want:

When	Action	Results in
You do not want to receive any email notifications.	Click the Unsubscribe from SMTP option, and then click Ap- ply .	The SMTP channel selection for all server events is cleared and you are unsubscribed from the SMTP channel. The In App option is displayed as selected for subscription for all server events.
		In App
		In App
You do not want to receive any in-app or the SMTP email notifi- cations.	Click the Unsubscribe from all Channels option, and then click Apply.	The in-app channel and the SMTP channel selections for all server events are cleared and

When	Action	Results in
		you are unsubscribed from both the channels. No channel is dis- played as selected for subscrip- tion for all server events.
		No channels
		SMTP
You want to subscribe to the email notifications for all server events.	Click the Subscribe to SMTP op- tion, and then click Apply .	The SMTP channel for all server events is selected and you are subscribed to the in-app chan- nel. The In App option is dis- played as selected for subscrip- tion for all server events.
You want to receive notifica- tions as in-app and as SMTP email notifications.	Click the Subscribe to all Chan- nels option, and then click Ap- ply .	The in-app channel and the SMTP channel are displayed as selected for all server events and you are subscribed to both the channels.

e.

Results

You completed the following tasks:

- Modified the notification subscriptions.
- Unsubscribed from or subscribed to either the SMTP channel or both the channels.

Related information

Managing notifications on page 760

Configuring an SMTP server to manage email notifications

Before you can receive email notifications about events that occur in HCL OneTest[™] Server, you need to configure an existing Simple Mail Transfer Protocol (SMTP) server in HCL OneTest[™] Server. When events occur in HCL OneTest[™] Server, email notifications are sent to the registered users of HCL OneTest[™] Server if they are subscribed to the SMTP notification channel.

Before you begin

You must have completed the following tasks:

- Ensured that you are assigned a role as a *Team Space Owner* in the team space. See Managing members and their roles in a team space on page 720.
- Ensured that an existing SMTP server is available to be connected to HCL OneTest[™] Server.

About this task

The configuration works for emails that are supported by the SMTP server. To use this capability, you must enable HCL OneTest[™] Server to connect to the SMTP server to send email notifications.

As a server administrator, you can configure email notifications so that other users can receive information about actions on the server projects.

1. Log in to HCL OneTest[™] Server.

The team space that contains your project is displayed.

2. Click the **Settings** icon 🔯 from the menu bar.

The Notifications page is displayed.

3. Click Add Configuration.

- 4. Provide the following details to configure the SMTP server:
 - A name to the configuration.
 - $\, \circ \,$ The host name and port number of the SMTP server.



Note: The default configuration uses a local SMTP server that listens to the default port 25. This SMTP server does not require any authentication.

- The email address of the sender. The email address is displayed in email notifications. The email notifications are sent to the users based on the notification settings.
- The encryption type for secure communications is when the SMTP server is on an external network. You can enable either **STARTTLS** or **SSL/TLS**.

Note: The SMTP server for the secure communication listens to the default port 465.

• Login credentials are required if the SMTP server requires authentication.

5. Click Add.



Note: The SMTP configuration is added after a valid connection is established with the SMTP server.

Results

You configured an SMTP server to connect with HCL OneTest™ Server and send out email notifications about the server events to users who have subscribed to the SMTP channel.

What to do next

You can modify the default subscriptions for the SMTP channel, see Managing email notifications on page 766.

Related information Managing notifications on page 760

Chapter 8. Reference Guide

This guide describes conceptual information about data design environment components when you want to use the data fabrication feature in HCL OneTest[™] Server.

Files

You add a file to a project to use it as input in the project. You can upload a file from your local file system to a project from the **Files** tab to generate test data. Alternatively, you can upload it when you define an action.

You also can download a file from a project to your local file system. From your local file system, you can upload the file to a different project.

Connections

A connection defines the properties that are required to connect to an external resource. An action uses a connection to provide source data to a project or write data from a source to a target. Multiple actions can use the same connection. You can define both connections and actions at the project level.

Project-level connections

You can reuse project-level artifacts in multiple projects. You use the **Connections** tab to define a new project-level connection and its actions or to select an existing project-level connection and its actions.

For example, you can define a project-level connection to a database that is used as a data source or target of multiple projects. A project-level action might be an SQL query and schema that multiple maps use to look up the same database data.

Connection testing

You can test project-level connections. When the Design Server has access to an external resource, testing validates the properties of the resource connection. If the Design Server can not access the external resource, the connection test fails, even if the connection properties are correct.

Resource adapters

HCL® OneTest[™] Data resource adapters are used to retrieve data. These resource adapters provide access to the databases.

The following resource adapters are supported by the HCL® OneTest[™] Data

- Java Database Connectivity (JDBC) adpater
- Excel adpater
- Systems Applications and Products in Data Processing (SAP) adapter

Related information

HCL OneTest Data support to write the generated test data in JDBC-supported databases on page 194

SAP applications

This topic provides an information about integration of SAP applications with HCL® OneTest[™] Data.

Introduction

The Systems Applications and Products in Data Processing (SAP) applications acts as resource adapters. HCL® OneTest[™] Data integrates with the SAP application to generate a schema, and then generate the test data to perform application testing.

SAP applications overview

The SAP applications is a unique data transformation technology for interfacing SAP R/3 software applications with third-party applications and legacy systems. Connectivity to the SAP R/3 environment is provided for both inbound and outbound data, and is supported on the major SAP platforms.

Pack for SAP Applications makes use of SAP's synchronous and asynchronous (transactional) Remote Function Calls (RFCs). This approach ensures effective and secure communication between external systems and SAP R/3. Detailed knowledge of RFCs is not required to create interfaces for SAP R/3 that are reliable, efficient, and easy to maintain. Some knowledge of Remote Communication Basis is helpful but not required.

In addition, the pack can be used with several file-based interfaces, such as SAP DXOB/DMI and EDI subsystems.

The Pack for SAP Applications is used for:

- Initial data load
- · Ongoing real-time or near-real time interfaces



Note: The Pack for SAP Applications is applicable to the following versions: SAP R/3 4.6, 4.7, mySAP 2004 (ECC 5.0) and mySAP 2005 (ECC 6.0).

Overview of SAP R/3 interfaces

The Pack for SAP Applications supports the following interfaces and technologies that include the automatic generation of metadata-specific schemas:

- Intermediate Documents
 - Application Link Enabling (ALE)
 - ALE Message Handler (AMS)
 - Electronic Data Interchange (EDI)
- DXOB/Data Migration Interface (DMI)
- For the adapter-specific commands, see the Adapter Commands List on page 776.

Intermediate Documents (IDocs)

The IDocs interface consists of the definition of a data structure and the processing logic for this data structure. This interface is used to exchange business data between two different systems. SAP R/3 support for the IDoc interface includes both Electronic Data Interchange (EDI) and Application Link Enabling (ALE) technologies.

Application Link Enabling (ALE)

ALE links multiple SAP R/3 systems in distributed environments, and non-SAP systems to SAP R/3 without file-to-file transfers. The SAP R/3 architecture supports the transfer of data between applications using messaging as opposed to files. SAP R/3 enables the creation of a distributed, fully integrated suite of loosely coupled applications.

The SAP component supports the integration of distributed SAP R/3 systems under ALE and the flow of information among multiple SAP R/3 systems to accomplish specific business objectives. It also embraces integration among non-SAP R/3 applications, such as third-party applications or legacy systems, by providing the conversion technology required to accomplish this level of integration among diverse systems.

The ALE adapter (JALE) adds Unicode character set data support inbound to and outbound from SAP.

ALE Message Handler (AMS)

The AMS interface provides connectivity between SAP R/3 and one or more disparate applications sending and receiving IDocs for one or more SAP R/3 instances. AMS does not provide any conversion function and delivers IDocs without changing them. Transactional RFC must be the communication method used between the SAP R/3 system and the ALE Message Handler.

Electronic Data Interchange (EDI)

EDI enables companies with the ability of communicating business transactions and documents electronically with their partners, vendors, and clients.

DXOB/Data Migration Interface (DMI)

DXOBs are SAP R/3 business objects that can be transferred automatically into the SAP R/3 system. Examples of business objects are organizational units.

The Pack for SAP Applications support for the DXOB interface includes data transfer object structures in both beta and released formats. During data transfer, data is transferred from an external system into the SAP R/3 system.

SAP applications support the data transfer of numerous SAP business objects. The data transfer program specifies the data format definition that is necessary to import the data into the SAP R/3 system. The pack provides the data transformation server to convert the external system data format to the format of the DX object.

Business Application Programming Interface (BAPI)

The BAPI adapter (JBAPI) enables full Unicode support when installed with the latest version of ITX. The JBAPI adapter provides unified access to both Unicode and non-Unicode systems.

BAPI provides a business-oriented interface for accessing SAP R/3 business processes and data from external systems. BAPIs are part of the SAP business framework, an open component-based architecture enabling software components from SAP and other providers to be integrated.

The R/3 adapters

The SAP specific components for the SAP R/3 runtime environment are the R/3 adapters for Windows[™] based and UNIX[™] based platforms.

This section introduces the R/3 adapters and provides instructions for adapter use, adapter settings, and adapter commands, including the following:

Overview of the R/3 adapters

Both client and server functionality is supported within an R/3 adapter. An R/3 adapter contains the Remote Function Calls (RFCs) necessary to pass inbound and outbound data to and from SAP R/3. The adapter includes transparent integration of the RFCs so that it is not necessary to possess detailed knowledge about the RFCs. The adapters also manage transactional information such as message transaction IDs (TIDs) as needed. This feature ensures seamless integration with SAP R/3 and also provides a robust auditing mechanism.

The R/3 adapters used to interface with the SAP R/3 application are:

- JALE
- JBAPI

Adapter commands list

The following table lists each R/3 adapter command, the command syntax, and the interfaces for which it can be used for a source (outbound data), target (inbound data), or both.

Table 17. Adapter command list

Name	Command Syntax	JALE	JBAPI
Program ID	-A pgm_id	source	
Audit	-AR3[+][U] [%tid% full_path]	source/target	
Backup	-B[I][X] [%tid% full_path]	source/target	
Load Balancing	-BAL	target	target
Bytes Per Character	-BPC	source/target	
Client Number	-C clnt_num	source/target	target
Character set encoding	-enc	source	
Destination	-D dest_key	source/target	target
GatewayHost	-G gtwy_name	source	
IDoc Field Generation	-GEN [0 !] [<i>flds</i>]	target	
Group	-group NAME	target	target
Host ID	-H host_name	source/target	target
Logon Language	-L lang_cd	target	target
Listen	-LSN {0 dur [: int]}	source	
Listener Threads	-N	source	
Password	-P pwd	target	target
Packet Size	-PKT <i>IDoc_qty</i>	target	
Reprocess backup files	-R	source	
System ID	-S sys_num	source/target	target
Timeout	-timeout secs		target
Trace	-T[V E N][+] [full_path]	source/target	target

Name	Command Syntax	JALE	JBAPI
Transaction ID	-TID trans_ID	source/target	
ІДос Туре	-TY OTHER\$ doc_type*	source	
User ID	-U usr_id	target	target
Gateway Service	V	source	

Table 17. Adapter command list (continued)

Intermediate Documents (IDocs)

IDocs are SAP standard data containers or formats that provide the basis for both ALE and EDI interfaces to SAP R/3. The topics below discuss using IDocs with SAP R/3 and provides the specific information required for ALE and EDI interfaces:

Overview of IDocs

Several hundred IDocs are shipped with each SAP R/3 system. ALE and EDI interfaces use functionally equivalent IDocs; however, they differ in the manner in which the IDocs are communicated to or from SAP R/3.

- ALE IDocs are communicated through memory buffers, without intermediate files, directly to or from an RFC port using transactional remote function calls (RFCs).
- EDI IDocs are passed using an intermediate file.

These interfaces (ALE and EDI) that use the IDoc structure represent SAP's strategic approach to interfacing SAP R/3 with legacy and third-party applications where loose coupling is appropriate. Therefore, the SAP R/3 IDoc approach should be considered the first choice for developing interfaces where asynchronous, near-real time, or batch links are required. This pack supports SAP-supplied IDocs as well as user-defined IDocs.

One or more IDocs are held in a container called a packet. A packet is the largest data container in an IDoc schema. The restart attribute is automatically added to reject invalid IDocs contained within a packet.

IDoc structural format

The IDoc format consists of hierarchically structured segments with multiple levels of nesting. IDocs exist for data such as customers and materials, for transactional data such as sales orders, and for control data such as company codes. In ALE terms, these are called IDoc types, which are described as follows:

Control record

There is one control record, and its format is identical for all IDoc types. It consists of the IDoc ID, Sender ID, Receiver ID, IDoc type, and EDI attribute.

Data records

There can be one or more data records. A data record consists of a fixed administration section (IDoc ID, Sequence/Hierarchy) and a data part (Segment). A Segment is the formal definition for header data and item data. The number and format of the segments can be different for each IDoc type.

Status records

The status records describe the processing stages through which an IDoc can pass, and contain the IDoc ID and status information. There will be several status records.

The IDoc types are assigned to release-independent message types, which themselves are assigned to object types in the Business Object Repository (BOR). Customer enhancements are generally subject to naming conventions. IDoc data segments are a maximum of 1000 bytes in length and generally only contain CHAR fields. The data segments of an IDoc type are described by release-independent segment types and have release-specific segment definitions that are stored as internal structures in the Dictionary. This means IDocs can be sent with different data contents to different recipients because the recipient's release is defined in the sending system.

Data Transfer Objects (DXOB)

Data transfer objects (DXOB) are SAP R/3 business objects that can be transferred into an SAP R/3 system. To use SAP R/3 to create DXOB interfaces including the creation of initial data transfer files (DXOB reports) and using Connections and Actions to generate the corresponding schemas read the sections below:

Business Application Programming Interface (BAPI)

The BAPI adapter (JBAPI) enables full Unicode support when installed with the latest version of ITX. The JBAPI adapter provides unified access to both Unicode and non-Unicode systems.

BAPI provides a business-oriented interface for accessing SAP R/3 business processes and data from external systems. BAPIs are part of the SAP business framework, an open component-based architecture enabling software components from SAP and other providers to be integrated.

Overview of the Interface (BAPI)

SAP Business Objects reside in the Business Framework and provide the interoperability of software components. Collectively, Business Objects are contained within the Business Object Repository (BOR). They cover a wide range of SAP R/3 business data and processes. BAPIs allow external non-SAP R/3 systems, such as HCL® OneTest[™] Data, to access the methods on a SAP Business Object by using appropriate adapters. SAP Business Objects and their BAPIs provide an object-oriented view of SAP R/3 functionality.

BAPIs are accessed in SAP R/3 using the transaction code BAPI.

Vendor is a Business Object in the Financial Accounting area of Business Framework. Expanding the Vendor Business Object exposes the available methods.

ChangePassword is a method (BAPI) on the Vendor Business Object. This method provides the capability to change a vendor's password, which is selected by the key field **VendorNo**. The BAPI name of this method is found by clicking

the **Detail** tab. The BAPI name is BAPI_VENDOR_CHANGE_PASSWORD, the name you specify in Connections and Actions.

The dialog also provides documentation on the parameters and attributes of the BAPI. All BAPIs are composed of a combination of Importing, Exporting, and/or Table parameters. Importing parameters are input, Exporting are output, and Tables are in/out. A BAPI may have any combination of these parameter types. Documentation for the parameters, structures, and scalars of a BAPI can be found in the BAPI Browser, the SAP Assistant, and the Function Module.

Schema design

A schema is a graphical data dictionary that contains metadata definitions of the structure of a document to generate test data. Schema provides visual cues for understanding the structure and complete definition of an object.

Schema designer helps to:

- · Create and manage schema that define properties for data structure
- Create data validation rules

Introduction to schema design

Use the **Schemas** tab to define, modify, and view schemas. A schema describes the syntax, structure, and semantics of your data.

The syntax of data refers to its format including tags, delimiters, terminators, and other characters that separate or identify sections of data. The structure of data refers to its composition including repeating substructures and nested groupings. The semantics of data refer to the meaning of the data including rules for data values, relationships among parts of a large data object, and error detection and recovery.

About schemas

A schema defines the contents for generating the test data. A schema is a mechanism for defining each element of your data. Similar to a data dictionary, a schema contains a collection of type definitions.

Because data definitions are defined in a schema, you must be familiar with the specifications that define your data before attempting to create one.

A data file is a simple example. The data file is made up of records and each record is made up of fields. In this case, there are three kinds of data objects: a file, a record, and a field.

In a file of records, think of the data in terms of the three data objects. For example, one type defines the entire file; another type defines the entire record contained in that file. Other types in the same schema define the data fields of the record.

A schema has three data type classifications: group, category, and item. The *root* type is the base type from which all other types stem, representing the data objects of all types in the schema. *Root* is the default name, however, you can modify any type name.

Types within a schema are listed in alphabetical order by default. To change the order for new types, modify the root type properties.

Subtypes

Subtypes are created for a number of reasons like identifying distinct data object. Another reason is that specific types of an object may have different properties such as different date formats.

Think of subtypes as different "flavors". Ice cream flavors can be chocolate, strawberry, or vanilla. To create a schema to represent ice cream as data, the different flavors of ice cream could be subtypes of the type **IceCream**.

The type **IceCream** is generic and describes any kind of ice cream. The type **Chocolate**, a subtype of **IceCream**, represents a certain kind of ice cream: chocolate.

A file of purchase order data may have two different kinds of records: header and detail. The schema representing this data might have a **Record** type with **Detail** and **Header** as subtypes of **Record**.

Schema hierarchy

The types in a schema are arranged in a hierarchy. If a type is subordinate to another type, it is called a *subtype*. The type on the branch stemming above a specific type is called its *supertype*.

Subtypes have more specific properties. For example, two different kinds of fields, **Name** and **Date**, may be defined as subtypes of **Field**.

The item type **Field** describes any field. The item types **Date** and **Name** are more specific kinds of fields. In a classification hierarchy such as this, the deeper the subtype is in the type tree, the more specific the data characteristics.

Example scenario

Imagine that a schema represents your house. There is a type for the entire house (**House**). A type for each room (**Bathroom**, **Bedroom**, and so on), and types for the different furnishings in these rooms (**Bed**, **Chair**, and so on). Each type represents a complete object. A house is made up of rooms. Inside these rooms are beds, chairs, couches, and so on. You know this, but you cannot see it by looking at the classification hierarchy view of the schema. You must open one of the types in the group view to see its components.

Defining data

For optimum test data generation, the entire contents of your data must be defined. Using the Type Designer, you can define input data so that each data object of the source data is identified. You can define the output data according to your output specifications.

How specifically you define the data is up to you. For example, if there is a large section of data that you want to process quickly, define it loosely as a chunk of text.

The purpose of the Type Designer is to define your data.

Objects, types, and classes

Schemas consist of objects, types, and classes.

Objects

A data object is a complete unit that exists in your input or is built on output. A data object can be simple (such as a date) or complex (such as a purchase order).

A data object is some portion of data in a data stream that can be recognized as belonging to a specific type. When you create types, identify all of the objects that make up the data: input objects and output objects.

Types

A type defines a set of data objects that have the same characteristics. For example, the type "Date" can be defined as representing data objects in the form MM-DD-YY. The type "CustomerRecord" can be defined as representing data objects, each of which consists of a **Company**, **Address**, and **Phone** data object.

Classes

A type is classified according to whether or not it consists of other objects. Each type in a schema must be defined in one of three classes: item, group, or category.

Item type

An item type represents a simple data object that does not consist of other objects. It is a default class of schema.

• Group type

A group type represents a complex data object that consists of other objects. For example, "FullName" is a group type that contains the components: FirstName, MiddleInitial, and LastName. Each group must have at least one item type.

Category type

A category type is used for inheritance and for organizing other types in a schema. For example, you might have a category named "OrderField" to organize the different kinds of order fields in your schema.

Type properties

The properties of a type define the characteristics of the data objects of that type.

For *item* types, properties define whether that item is text, a number, a date and time, or a syntax value. Properties include such characteristics as size, pad characters, and justification.

For *group* types, the properties are related to the format of that group. The format of a group may be explicit or implicit. In addition, type properties include syntax objects that appear at the beginning or end of the object, as well as release characters.

Defining type properties

About this task

You can define specific properties for each type. Type properties generally consist of the following:

- Definition of a type's Class, Group or Item properties
- Type Initiator, Terminator, and Release character
- A list of where a type is used in the definitions of other types

Basic type properties

The following type properties are common to categories, groups, and items:

- Name on page 783
- Class on page 784
- Description on page 785
- Intent on page 785
- Partitioned on page 785
- Order Subtypes on page 785
- Initiator on page 785
- Terminator on page 786
- Release Characters on page 786
- Empty on page 788
- National Language on page 807
- Document Type on page 789
- Where Used on page 789

Item-specific properties are discussed in more detail in "Item Properties" on page 792. Group-specific properties are discussed in more detail in "Group Properties" on page 830.

Name

The name of the type should be as descriptive as possible and reflect the information that the type represents.

A type name must confirm to the following guidelines:

- A type name cannot be more than 256 characters long.
- A type name cannot be a reserved word or contain a reserved symbol. For a list of reserved words, refer to Design Studio Introduction documentation.
- A type name cannot contain only digits and/or periods.
- A type name may contain numbers and special characters.
- A type name cannot contain spaces. Use an underscore instead.
- A type name can contain the following:
 - Letters
 - Digits
 - ASCII characters 128-255
 - $\,\circ\,$ Special characters: #, ~, %, _, ? or \
 - Double-byte characters (Japan edition only)

• A type name cannot have the same name as another type on the same level in the same schema.

A type name can be up to 256 characters in length, but use a short type name if possible. The full path name of each type is used in map rules in the map designer.

Class

The class of a type describes whether the type represents a simple data object (item), a complex data object (group), or whether is used to organize types (category). Define the class of the selected type by selecting the check box.

Category

Categories organize types that have common properties. Each category has a set of item properties and a set of group properties. Subtypes of the category inherit these properties.

A category does not define data objects in detail. A category type may be a component of a partitioned group, after a component with the identifier attribute. A category cannot be a component of a non-partitioned group.

ltem

The item type represents a simple data object that does not consist of any objects. An item does not have components.

Group

The group type represents a complex data object that consists of components.

To change a type's class, select the type and choose the desired class in the Properties window.

If you change a type to an item, all the types in its subtree become items. If you change a type to a group, all the types in its subtree become groups. This is because the schema has a classification hierarchy and all the nested subtypes of an item must be items. Similarly, all the nested subtypes of a group must be groups.

Description

Use this property to record a brief description of the type. The description entered is for informational purposes only. It is not used for identifying data objects at runtime.

It is good practice to add a meaningful description of the type when you are defining it.

Intent

Indicates whether the type is a general type or an XML type.

The type can only be an XML type if the type tree was created using the XML DTD Importer or the XML Schema Importer.

Refer to *"XML Properties in the Type Tree"* on page 839 for more information about type properties created from XML.

Partitioned

If the data of this type can be divided into mutually exclusive subtypes, it can be partitioned. For information about partitioning, see "Partitioning" on page 854.

Yes

Partitioning is enabled for this type.

No

Partitioning is not enabled for this type.

Order subtypes

Choose the method in which the subtypes of this type will be added or viewed in the schema.

Ascending

Add and view subtypes of this type in alphabetic or numeric order.

Descending

Add and view subtypes of this type in reverse alphabetic or numeric order.

User-defined

Add subtypes of this type to manually reorder the subtypes.

Initiator

An initiator is a syntax object that appears at the beginning of a data object. Defining an initiator for a type specifies that when data of that type appears, the initiator appears at the beginning of the data object. The initiator becomes part of the data type definition.

None

There is no initiator.

Literal

The initiator is literal. Expand the **Initiator** property to enter the literal initiator value and data language of the initiator value.

Variable

Allow for possible values. Expand the **Initiator** property to define the variable terminator **Default**, **Item**, and **Find** properties.

If each record begins with an asterisk *, define the * as a literal initiator of the record type.

The following data represents the classes in a college English department. An asterisk * is displayed at the beginning of each **ClassRecord**.

For information about other symbols used in the **Value** field of the **Initiator** property, see the Type Tree Importer documentation.

Terminator

A terminator is a syntax object that appears at the end of a data object. The terminator becomes part of the data type definition.

None

There are no terminators.

Literal

A constant value. Expand the Terminator property to define the literal terminator Value.

Variable

Allow for possible values. Expand the **Terminator** property to define the variable terminator **Default**, **Item**, and **Find** properties.

For example, a carriage return/linefeed (CR/LF) at the end of a record is the record's terminator.

Generally, if the data ends with a given syntax object, you should define a literal terminator. For example, it is very common to define a CR/LF as a terminator of a record when you know that the record always ends with a CR/LF, regardless of where the record appears.

Release characters

A release character is a one-byte character in your data indicating that the character(s) following it should be interpreted as data, not as a syntax object. The release character is not treated as data, but the data that follows it is treated as actual data.

Building release characters for output data

If a release character is defined for a type, a release character is inserted for each occurrence of a syntax object in the data of any item contained in that type.

Guidelines for using release characters

Guidelines for using release characters include the following:

- Release characters apply to character data only, not binary data.
- Characters defined as pad characters are not released.
- The maximum size of an item does *not* include the release characters.

Release character example

The group type **Record** type has a literal delimiter of , and a release character of ?. The group type **Record** has three item components. Data for the record looks like the following:

Miller?, MD, Harkin Hospital, 1996

The ? releases the comma after Miller.

In the first field, the actual data value is **Miller**, **MD**. Because the comma appears as part of the data, it is necessary to have the release character **?**, which indicates that the , following it is data, *not* a delimiter. This data would be interpreted as the following:

Data for component #1: Miller, MD

Data for component #2: Harkin Hospital

Data for component #3: 1996

A release character can apply to a delimiter, a terminator, or even the release character itself.

If a release character appears in the data and it is not followed by a syntax item, the release character is ignored.

Building release characters for output data

If a release character is defined for a type, a release character is inserted for each occurrence of a syntax object in the data of any item contained in that type.

Guidelines for using release characters

Guidelines for using release characters include the following:

- Release characters apply to character data only, not binary data.
- Characters defined as pad characters are not released.
- The maximum size of an item does not include the release characters.

Release character example

The group type **Record** type has a literal delimiter of , and a release character of ?. The group type **Record** has three item components. Data for the record looks like the following:

Miller?, MD, Harkin Hospital, 1996

The ? releases the comma after Miller.

In the first field, the actual data value is **Miller, MD**. Because the comma appears as part of the data, it is necessary to have the release character **?**, which indicates that the , following it is data, *not* a delimiter. This data would be interpreted as the following:

Data for component #1: Miller, MD

Data for component #2: Harkin Hospital

Data for component #3: 1996

A release character can apply to a delimiter, a terminator, or even the release character itself.

If a release character appears in the data and it is not followed by a syntax item, the release character is ignored.

Empty

The Empty property provides alternative type syntax for groups or items when they have no data content.

When the **Empty** property is specified for a type and there is no data content, the **Empty** syntax is displayed. For example, this can be used for XML data that contains either start and end tags or an empty tag.

You can use the **Empty** type property instead of syntax object items to potentially improve the schema runtime processing time (during data validation).

The following options are available for the Empty property.

None

Default setting. Select None if you do not have an initiator, terminator, or release character.

Literal

A constant value. When **Literal** is selected, the **Value**, **Ignore Case**, **Required**, and **National language** sub-fields become available. You can use only one literal to indicate a zero-length data item.

Empty type property example

Consider an XML element called *comment*. Presuming that this element has a simple content of an arbitrary length, it can be represented in a schema as a text item, with the initiator value <*comment>* and the terminator value <*/comment>*.

This item can then be used to validate the following data:

<Comment>Some comment...</Comment>

The resulting value for the item will be:

Some comment...

As another example, the following data is also successfully validated:

<Comment></Comment>

The resulting value for the item will be a zero-length string.

The problem occurs with the following data: <Comment/>

From the XML perspective, this data is equivalent to the <<u>comment</u>></<u>comment</u>> data shown above, as it represents the **Empty** element <u>comment</u>. However, from the schema perspective, this data is invalid because it does not start with <<u>comment</u>> and does not end with <<u>/comment></u> as required by the initiator and terminator item property values.

This is where the **Empty** property is useful. By defining the **Empty** property for the item to have a value of <<u>Comment</u>/>, it will be possible to validate the data <<u>Comment</u>/>.

Even if the data does not match the syntax described by the initiator and terminator properties, it will be validated because it will match the **Empty** property value. It will be treated as an *empty item*, that is, the resulting value for the item will be a zero-length string, similar to the example shown previously.

Document Type

The **Document Type** setting is a component of Document Verification. A requirement of using Document Verification is to set the **Document Type** properties of the associated schema object.

To use the Document Verification option for XML documents, you must do the following:

- Set the Document Type property to XML.
- Set the Document Type Metadata value to Schema or DTD.
- Specify the Location of the DTD or Schema file.

Default

This is the default value, which indicates a non-XML document type.

XML

Indicates an XML document type. When this value is set to **XML** and the appropriate **DocumentVerification** map settings are in place, the XML document will be validated by an external program in addition to the standard data validation process.

See the map designer documentation for information about using the Document Verification option.

Where used

Where Used shows how and where the type is used within other types in the tree.

Symmetric swapping

When the input and output objects have different symmetric swapping characteristics, the Symmetric Swapping property is considered "on" for the related mapping rule.

Examples

Original text	Resulting text
abcF(E)Dghi	abcF(E)Dghi
Input Object	
No swapping	
Output Object	
Swapping	
Original text	Resulting text
abcF(E)Dghi	abcF(E)Dghi
Input Object	
Swapping	
Output Object	
No swapping	
Original text	Resulting text
Original text	Resulting text
-	
abcF(E)Dghi	
abcF(E)Dghi	
abcF(E)Dghi Input Object No swapping	
abcF(E)Dghi Input Object No swapping Output Object	
abcF(E)Dghi Input Object No swapping Output Object No swapping	abcF)E(Dghi
abcF(E)Dghi Input Object No swapping Output Object No swapping Original text	abcF)E(Dghi
abcF(E)Dghi Input Object No swapping Output Object No swapping Original text abcF(E)Dghi	abcF)E(Dghi
abcF(E)Dghi Input Object No swapping Output Object No swapping Original text abcF(E)Dghi Input Object	abcF)E(Dghi
abcF(E)Dghi Input Object No swapping Output Object No swapping Original text abcF(E)Dghi Input Object Swapping	abcF)E(Dghi

Orientation

Orientation is to change characters from one direction to a different direction.

Example

A simple orientation example is to define English characters "abc" as a bidirectional object with left-to-right (LTR) orientation. If you moved the object to a right-to-left (RTL) object, the output should be "cba". The following example demonstrates a string of characters that change in orientation.

Original text	Resulting text
ABC DEF à Ã;â	âÃ;à FED CBA
Input	
left-to-right (LTR)	
Output	
right-to-left (RTL)	

Shaping

Text shaping is the concept of combining or separating characters where possible. The Arabic usage is with ligatures (such as the LAM, ALEF, and LAM-ALEF characters). For example, in a non-shaped word, both LAM and ALEF characters would appear separately. In a shaped word, the two characters would be replaced with a single LAM-ALEF character.

Numeric shaping is the idea that normal regular numerals (0-9) can be shaped to be Arabic-Indic

Examples

Ù" = LAM ï° = ALEF ۙﻻ = LAM ALEF

Original text

Resulting text

abcï»»def

abcÙ"ï°def

Input

Shaped

Output

Unshaped

Original text

Resulting text

abcÙ"ïºdef

Input

Unshaped

Output

Shaped

Item properties

Item types define data for a selected type. Item types are divided into the following subclasses: **Number**, **Text**, **Date & Time**, and **Syntax**. Each item subclass has a specific set of properties.

abcï»»def

Item subclass

The subclass of an item represents the characteristics of the data. Both category and item types have the **Item Subclass** property.

To define the subclass of an item type:

- 1. Access the Properties for the selected category or item type.
- 2. For the Item Subclass property, select a value that defines the data for the type:

Number

Any number excluding active syntax objects. The interpretation can be either character or binary. See "Number Item Subclass properties" on page 793.

Text

Any character excluding active syntax objects. The interpretation can be either character or binary. See *"Text Item Subclass properties"* on page 815.

Date & Time

A valid date and time format based on the data. The interpretation can be either character or binary. See Date &" *Time Item Subclass properties*" on page 819.

Syntax

Syntax objects are used as separators between portions of data. A restricted set of values used to define a dynamic delimiter, initiator, terminator, or release character. The interpretation is character. A syntax object cannot be longer than 120 bytes. Syntax objects, used as syntax, cannot be mapped. See *"Syntax Item Subclass properties"* on page 828.

For text and syntax objects, character size constraints can be in bytes or characters. Numbers are considered in digits and date-time formats are sized by the format, such as CCYYMMDD.

Number item subclass properties

Number item subclass properties can be of **Character** or **Binary** value. When you choose **Number** as the **Item Subclass** value, you must choose value as: **Binary** or **Character**.

The value defines how the data should be interpreted. Items with a subclass of **Number**, **Text**, and **Date & Time** can be interpreted as either character or binary. Items with a subclass of **Syntax** can be interpreted as character only.

Interpret as binary

Binary text items have content size and pad properties. Binary data is required to be sized or of a fixed size.

Binary number items interpret the data as a binary number or as a byte stream.

Items with an item subclass of Text can be interpreted as character or binary.

The binary presentation options are Integer, Float, Packed, or BCD.

Binary integer presentation

The Integer value is a whole number.

Byte Length

Can have a length of 1, 2, 4, or 8 bytes

Byte order

See "Byte order" on page 794.

Sign

See "Sign" on page 800.

Binary float presentation

The Float value is a number with decimals in a location as needed.

Byte Length

Can have a length of 4, 8, or 10 bytes

Binary packed presentation

The Packed value is a number that has size, decimal places, and sign properties.

The binary packed properties include Length, Implied places, and Sign.

Length

Can have a length of 1 - 16 bytes

Implied places

Can be from 0 - 31

Sign

Can be Trailing- or Trailing+

For Packed numbers, the Implied places cannot exceed the Length.

Binary BCD presentation

The **BCD** value is a binary coded decimal number that has size.

Byte Length

Use the Byte Length property to select the number of bytes that equals the length of the item.

The Byte Length property is an option when the Number item subclass property is interpreted with a Binary value.

Byte order

Use the **Byte order** property to define the way that bytes in the data are ordered by selecting one of the following values from the Byte order drop-down list.

Value	Description
Big Endian	The most significant byte has the lowest address. (Usually systems such as IBM, HP, and So- laris.)
Little Endian	The least significant byte has the lowest address. (Usually systems such as Intel and VAX.)
Native	The order is dictated by the platform.

Byte order is an option when the Number item subclass is interpreted with a Binary value.

Interpret as character

Character number items interpret the data as symbolic data. Symbolic data has the same meaning on different computers. For example, a comma is symbolic because it has the same meaning, regardless of the computer type.

Character text items can have content size and pad properties.

When you select **Character**, the **Release** property is specific to the **Character** value and is *not* available as an option for a **Binary** value. For more information, see "Release characters" on page 786.

When interpret is set to Character, integer, decimal, and zoned presentation options are available.

Character integer presentation

The Integer value is a whole number.

Further information on the Integer value is found in "Integer Separators" on page 796.

Character decimal presentation

The **Decimal** value is a number that contains decimals.

More information about the Decimal value is found in section "Decimal Separators" on page 798 .

Zoned character presentation

The Zoned value is a number that has a size, decimal place, pad, and sign properties.

Use the "Size (digits)" property to specify the size of the zoned number. The size of a zoned number can also be specified in terms of minimum and maximum. The minimum size must be less than or equal to the maximum size.

When the content size of a character-zoned number is used, the last digit and the sign are combined into the same digit but the content size does *not* include the initiator, terminator, release characters, or pad characters.

When the content size of a character-zoned number is important (for example, when the SIZE function is used on the character zoned number), the content size includes the sign but does not include the initiator, terminator, release characters, or pad characters.

Use the "Sign" on page 800 property to define whether the zoned number will be signed. The default value is No.

The size of a zoned number is specified in terms of the minimum and maximum number of digits. If the size is specified with the **Min** and **Max** properties, the sign is *not* included.

Example

Zoned Number Not Signed Signed Zoned Number

1230	123{
1231	123A
(Length = 4 digits)	(Length = 4 digits)

Places > implied

Numbers have implied decimal places. The number of decimal places cannot exceed the length specification. The list of available decimal places varies with the length selected. In the **Value** column, enter a total number of decimal places (not to exceed 31).

Size (digits)

Use the Size (digits) property to specify the minimum and maximum size of a number item.

Min

The minimum number of digits of the data object.

The default value is 0.

Max

The maximum number of digits of the data object.

If there is no maximum size, a Max value is not required.

Excluded from min and max size

For character number items, there are certain objects excluded from the **Min** or **Max** count. For each **Presentation** option, the following table lists what is excluded from the minimum or maximum **Size (content)** count.

Presentation:	Integer	Decimal	Zoned
	initiators	initiators	initiators
	pad characters	pad characters	pad characters
	release characters	release characters	release characters
	separators	separators	terminators
	signs	signs	
	terminators	terminators	

Size example

In the following ASCII number there are a total of 12 characters:

+1234567.999

However, because the initiator (+) and separator (.) are not counted, the number would validate for a maximum size of 10 (Max=10).

Separators

Integer and decimal number items can have a separator for thousands and fractional places. If you opt to have a separator, choose **Yes** and sub-options will appear that enable you to choose the format and syntax.

The Zoned value of the Presentation property does not have separators.

Integer separators

For integer numbers, the separator is the thousands separator.

Integer character numbers have separator properties of:

- Format
- 1000's Syntax
- Value

These properties specify the placement and value of the thousands separator.

Separator > format

Use the Separators Format property to specify the placement and value of the thousands separator.

To define the separator format, select one of the separator formats from the drop-down list in the Value column.

#[.]####

The thousands separator is not required on input, but if present, it must be in the proper location. The separator is not built on output.

#.####

The thousands separator is required on input in the proper location. The separator is built on output.

1000's syntax > value

Define the thousands separator as either literal or variable. Select one of the following from the drop-down list in the **Value** column:

Literal

The thousands syntax is a constant literal specified in the 1000's Syntax > Value column.

Variable

The thousands syntax allows for variable values. Use the **1000's Syntax > Default**, **Item**, and **Find** properties to define the variable fraction separator.

1000's syntax (literal) > value

For the literal thousands separator, define the literal separator by typing the literal separator character in the **Value** column or by clicking the browse button to display the **Symbols** dialog from which you can insert any non-printable value.

A separator can be from one to 120 bytes in length. A separator cannot start or end with a digit and cannot be the? character. The ? character is a reserved character that can be used as a wildcard to represent any single valid character.

1000's syntax (variable) > default

Use the **1000's Syntax > Default** property to define the default variable separator value for the thousands place. The default literal separator value for thousands syntax is a comma.

Enter the default variable separator character or click the browse button to display the **Symbols** dialog in which you can insert any non-printable value.

1000's syntax (variable) > item

For integer numbers with a variable thousands separator, the **Separator** property is **Yes**, and the **1000's Syntax** is **Variable**, you can specify an item type for the variable thousands separator.

You can select the desired syntax item from the drop-down list. Or, with the focus on the **Item** property (in the **Value** column), press **Alt** and drag the default separator type item from the schema editor into the **Value** column.

An item type with a class of Syntax must exist in the schema to be a valid 1000's Syntax Item.

1000's syntax (variable) > find

For integer numbers with a variable thousands separator, the **Separator** property is **Yes** and the **1000's Syntax** is **Variable** The value of the separator can be the current value or the value of the separator can be determined each time an occurrence of that type is found.

Yes

Determine the value of the separator each time an occurrence of that type is found. After the value of that separator is found, that particular value is used until it is reset either by another Find or by the occurrence of that separator as a component.

No

The system uses the value to which the separator item is currently set or, if not set, it uses the default value.

Decimal separators

For decimal numbers, the separator is the thousands separator and the fractional separator.

Decimal character numbers have separator properties of:

- Format
- 1000's Syntax
- Fraction syntax
- Value

These properties specify the placement and value of the fractional separator.

The item is assumed to have an implicit number of decimal places. To specify the number of implied decimal places, use the **Item Subclass Places** property to specify the number of implied decimal places.

Separators > format

Use the Separators Format property to specify the placement and value of the fraction separator.

To define the separator format, select one of the separator formats from the drop-down list in the Value column.

####[.##]

The fractional separator is present if there are fractional digits. There is no thousands separator.

####.##

The fractional separator is always present, even if there are no fractional digits. There is no thousands separator.

#[,]###[.##]

The fractional separator is present if there are fractional digits. There is an optional thousands separator.

#[,]###.##

The fractional separator is always present. There is an optional thousands separator.

#,###.##

The fractional separator is always present. There is always a thousands separator if there are more than three whole number digits.

Separators > 1000's syntax

Use the **Separators 1000's Syntax** to define the thousands syntax. Select one of the following from the drop-down list in the **Value** column:

Literal

The thousands syntax is a constant literal specified in the 1000's Syntax > Value column.

Variable

The thousands syntax allows for variable values. Use the **1000's Syntax > Default**, **Item**, and **Find** properties to define the variable fraction separator.

See the following topics for additional information:

- "1000's Syntax (Literal) > Value" on page 797
- "1000's Syntax (Variable) > Default" on page 797
- "1000's Syntax (Variable) > Item" on page 798
- "1000's Syntax (Variable) > Find" on page 798

Separators > fraction syntax

Use the Fraction syntax property to define the fraction syntax as either a constant literal value or a variable value.

You can define the Fraction syntax as literal or variable.

Literal

A constant value.

Use the Fraction syntax > Value property to select a literal fraction separator from the Symbols dialog.

Variable

Allow for variable fraction separator values. The following options are available to define the variable fraction separator:

- **Default** Use this property to define the default variable separator value for fractions. The default literal separator value for fractions is a period. Enter the default variable separator character or click the browse button to display the **Symbols** dialog in which you can insert any non-printable value.
- Item For decimal numbers with a variable fractional separator, the **Separator** property is **Yes** and the **Fraction syntax** is **Variable**, you can specify an item type for the variable fraction separator.

Note: An item type with a class of Syntax must exist in the schema to be a valid Fraction syntax Item.

- Find For decimal numbers with a variable fraction syntax, the **Separator** property is **Yes** and the **Fraction Syntax** is **Variable**, the value of the separator can be either the current value or the value of the separator can be determined each time an occurrence of that type is found. Select an option:
 - **Yes** Determines the value of the separator each time an occurrence of that type is found. After the value of that separator is found, that particular value is used until it is reset by another find or by the occurrence of that separator as a component.
 - No The system uses either the value that the separator item is set to currently, or, if it is not set, uses the default value.

Sign

Use the **Item Subclass Sign** property to define whether the number is signed for either the **Integer** or **Decimal** value. A sign is a symbol that identifies a number as being either positive or negative. A positive sign is plus (+); a negative sign is negative (-).

Yes

The number is signed. Expands the **Sign** property to define the sign values. If the **Sign** property is **Yes**, a minimum of at least one sign value (**If number is +**, **If number is -**, or **If number is 0**) must be specified and at least one value must be required as input.

No

The number is not signed. This is the default setting.

When you select Yes, you can further define the sign values. The following sub-options are available:

Leading-

The sign precedes the number when it is negative only. For input, a sign is required for negative data, but is optional for positive data.

Trailing-

The sign follows the number when it is negative only. For input, a sign is required for negative data, but is optional for positive data.

Leading+

The sign always precedes the number. A sign is required for input and output data.

Trailing+

The sign always follows the number. A sign is required for input and output data.

Custom

Defaults to Leading- but can be changed.

Sign values may be specified for the following:

- If Number is + (positive numbers)
- If Number is (negative numbers)
- If Number is 0 (value of zero)

For each value (If number is +, If number is -, or If number is 0), specify the following:

Leading sign

Enter the symbol to be placed before a number.

Trailing sign

Enter the symbol to be placed after a number.

Required on input

If the number has a sign, at least one value (**If number is +**, **If number is -**, or **If number is 0**) must be required on input. Select an option from the drop-down list:

Yes

The sign is mandatory on input.

No

The sign is optional on input.

Pad

Pad implementation determines how the pad value is sized during validation and how the pad value is sized when written as output.

When the data value of the target item is smaller than the minimum length of that item, pad characters can be used to pad the data to that minimum length. Output data is built according to the pad definitions of the types. Bytes are the default measurement for sizing, however, both byte and character sizing options are available.

Yes

Enables the Pad option. Allows the item to contain both content and pad characters.

No

All data is assumed to be content on input; no pad characters are built on output.

Pad > value

Use the Pad Value property to define a 1-character pad character. The default pad value is 0.

Type the pad character symbol between angled brackets < > in the **Value** field or click the browse button to display the **Symbols** dialog to insert any non-printable value.

For example, to enter a **FormFeed** value for the pad character, in the **Value** field enter <**FF**> or click the browse button to select the **FF** (**FormFeed**) symbol from the **Symbols** dialog.

Pad > Padded to

Use the **Pad > Padded to** property to define whether the data item is padded to a fixed size or to the minimum content size defined for the data object.

Fixed size

The data object is padded to a fixed size (in bytes or characters) that you specify in the Length field.

For any item padded to a fixed size, the item must have a value specified for the **Size (content) > Max** property and the **Padded to > Length** value must be greater than or equal to the **Size (content) > Max** value.

Min Content

The data is padded to the value specified as the minimum size (in the Size (content) > Min field).

You can further specify whether to count pad characters toward the length using the **Counts Toward Min Content** property.

Padded to > length

To pad to a fixed size, you must specify the length.

Input data can contain both content and pad characters but when an item is built for output, the item is padded to the number of bytes or characters specified in this field.

The Padded to > Length value must be greater than or equal to the Size > Max value.

You can specify the method of measurement (bytes or characters) using the Sized As property.

Padded to > Sized As

Use the Padded to > Sized As property to specify that padding is measured in either bytes or characters. The default setting is Bytes.

Trace file and audit log lengths are always reported in bytes.

Table 18. Pad implementation example (bytes compared to characters)

Scenario for empty field:	Result:
Data language is UTF-8	Two $\tilde{\mathtt{A}}$ pad characters using 4 bytes.
Pad > Value = À (hexadecimal representation = 0xC3 0x80)	
Pad > Padded to = Fixed Size	
Padded to > Length = 5	
Padded to > Sized As = Bytes	
Data language is UTF-8	Five à pad characters totaling 10 UTF-8 bytes.
Pad > Value = A (hexadecimal representation = 0xC3 0x80)	
Pad > Padded to = Fixed Size	
Padded to > Length = 5	

Padded to > Sized As = Characters

Padded to > Counts Toward Min Content

When you select Padded to > Min Content, the Counts Toward Min Content field is displayed. Use this setting to specify if pad characters should count toward the length of an object when determining if it meets its minimum content length.

Yes

Pad characters are included in the count for the length of an object.

No

Pad characters are not counted toward the length of an object.

You can use the Propagate function here to propagate the present Counts Toward Min Content value to the subtypes of the present type, if present.

If you are using the trace option, there might be cases where in the trace file the content length appears to be different than the input length. A trace file lists the input length (the length used to validate an object), which includes the input

length of each object plus the pad characters. In the case of numbers, signs and separators are also counted in the length.

Counts Toward Min Content > AcceptAllPads

The **AcceptAllPads** property is applicable to data objects that contain only pad characters. Use this property when you need an object that contains only pad characters (no content) to either pass or fail validation depending on whether it is a mandatory or an optional type, regardless of the minimum size requirement.

Yes

When an object contains only pad characters, the minimum size requirement is ignored and the object passes size validation. The object then passes or fails type validation depending on whether it is a mandatory or an optional type.

No

(Default setting) Pad characters do not count toward the minimum size requirement, therefore an object that contains only pad characters and that does not meet the minimum size (content) requirement fails size validation.

Example

The results of the following examples are based on these values:

Size (content)

5

Pad

Yes

Pad > Padded to

Min Content

Padded to > Counts Toward Min Content

No

Default Behavior: When Accept All Pads is set to No, the following results occur:

Input Data (X = pad character)

Valid?

ABCDE

Yes

ABC

No

ABCXX

No

XXXXX

No

When Accept All Pads is set to Yes, the following results occur:

Input Data (X = pad character)

Valid?

ABCDE

Yes

ABC

No

ABCXX

No

XXXXX

Yes (when type is optional)

No (when type is mandatory)

```
Х
```

Yes (when type is optional)

```
No (when type is mandatory)
```

Padded to > Allow Excess Trailing Pads

When you select **Padded to > Min Content**, the **Allow Excess Trailing Pads** property is displayed. Use this setting to flag an element as not valid when the following conditions apply:

- The element is padded to a minimum size.
- The number of pad characters exceeds the number that is required to achieve the minimum size.

Pad > justify

Use the Justify property to specify whether the data is padded to the left or right.

Left

The data will be on the left and will be padded (if necessary) on the right.

Right

The data will be on the right and will be padded (if necessary) on the left.

Use the TRIMLEFT and TRIMRIGHT functions to exclude pad characters from the justified side.

In the following example, XXXXXXXXX represent 10 spaces: For an input of 1234567891XXXXXXXX with a right justified pad, the rule =SIZE(input) returns 20. For the same input, the rule =SIZE(TRIMRIGHT(input)) would return 10 (removing the padding on the right).

Pad > Apply Pad

Use the Apply Pad property to specify when to apply the pad character. Choose a value from the drop-down list.

Fixed Group

Apply the pad characters only when the item appears in a fixed group.

Any Context

Apply the pad characters when the item appears in any context.

Each item in a fixed group must be padded to a fixed size or have the same value for the minimum and maximum content size.

For example, suppose the item Name has a space pad character with this value:

Mary<sp><sp>

If the **Apply Pad** property is **Fixed Group**, the two spaces at the end are treated as pad characters only when the item appears in a fixed group. If the **Apply Pad** property is **Any Context**, then the spaces are always treated as pad characters.

Each item in a fixed group must be padded to a fixed size or have the same value for the minimum and maximum content size.

Pad > fill

For padded signed numbers, this option determines placement of pad characters. Choose a value from the dropdown list.

After Sign

Pad characters are placed after the sign.

Before Sign

Pad characters are placed before the sign.

Regular expressions

Regular expression is a sequence of characters to define a pattern.

Use the Regular expression property to generate text or numerical data that matches the given regular expression.

The maximum length of the regular expression is 2000 characters.





- Regular expressions do not support certain notations like \\d and \\w. You cannot use regular expressions in JSON and XSD schemas.
- When you use @, #, < symbol, you need to escape it with backslash (\).

Restrictions

Restrictions of an item are the valid values of that item. When the **Interpret as** value is defined as **Character**, the **Restrictions** property is specific to the **Character** value and is not available as an option for a **Binary** value.

Depending on other Item Subclass settings, the Restrictions property can be set to Value, Character, or Range.

Restrictions > ignore case

By default, restrictions are case-sensitive. To enable or disable the **Ignore case** property of the **Restriction**, choose from one of the following options:

Yes

Ignore case of restrictions in item type properties.

No

Do not ignore case-sensitive restrictions.

For example, if Ignore Case = Yes and the restriction Value is Ft, the data values ft, fT, Ft, and FT are all valid.

Restrictions > rule

This setting indicates whether you are going to include or exclude the criteria (as "valid" or "invalid") specified for the restrictions.

Include

Includes the restriction values as valid data.

Exclude

Excludes the restriction values as invalid data.

National language

The **National language** default value is **Western**. For initiator, terminator, and release character **Literal** values, you can optionally specify a "Data language" on page 808.

When the **Interpret as** value is defined as **Character**, the **National language** property is specific to the **Character** value and is not available as an option for a **Binary** value.

National language > data language

Use the **National language > Data language** property to define the data language or character set of this character text item.

Supported code pages

HCL® OneTest[™] Data supports the following code pages:

Arabic ASCII (deprecated) Big5 Big5-HKSCS (IBM) BOCU-1 CESU-8 CII Kanji (deprecated) Cyrillic EBCDIC (deprecated) ebcdic-ar ebcdic-cp-ar1 ebcdic-cp-ar2 ebcdic-cp-be/ch EBCDIC-CP-DK/NO ebcdic-cp-es ebcdic-cp-fi/se/sv ebcdic-cp-fr ebcdic-cp-gb ebcdic-cp-he ebcdic-cp-it ebcdic-cp-roece/yu ebcdic-de ebcdic-he ebcdic-is EBCDIC-JP-kana ebcdic-xml-us EUC (deprecated) EUC-CN EUC-JP euc-jp-2007 EUC-TW euc-tw-2014 GB_2312-80 gb18030

GBK Greek8 Hebrew hp-roman8 HZ-GB-2312 IBM Kanji (deprecated) ibm-037 (ebcdic-cp-us/ca/wt/nl) ibm-1006 ibm-1025 ibm-1026 ibm-1047 ibm-1047-s390 ibm-1097 ibm-1098 ibm-1112 ibm-1122 ibm-1123 ibm-1124 ibm-1125 ibm-1129 ibm-1130 ibm-1131 ibm-1132 ibm-1133 ibm-1137 ibm-1140 (ebcdic-us-37+euro) ibm-1140-s390 ibm-1141 (ebcdic-de-273+euro) ibm-1141-s390 ibm-1142 (ebcdic-dk/no-277+euro) ibm-1142-s390 ibm-1143 (ebcdic-fi/se-278+euro) ibm-1143-s390 ibm-1144 (ebcdic-it-280+euro) ibm-1144-s390 ibm-1145 (ebcdic-es-284+euro) ibm-1145-s390 ibm-1146 (ebcdic-gb-285+euro) ibm-1146-s390 ibm-1147 (ebcdic-fr-297+euro) ibm-1147-s390 ibm-1148 (ebcdic-international+euro) ibm-1148-s390 ibm-1149 (ebcdic-is-871+euro) ibm-1149-s390 ibm-1153 ibm-1153-s390 ibm-1154 ibm-1155 ibm-1156 ibm-1157 ibm-1158 ibm-1160 ibm-1162 ibm-1164 ibm-1250 ibm-1251 ibm-1252 ibm-1253 ibm-1254 ibm-1255 ibm-1256 ibm-1257 ibm-1258 ibm-12712-s390 ibm-1276 (Adobe Standard Encoding) ibm-1363 (korean) ibm-1363_P110-1997 ibm-1364 ibm-1371 ibm-1373_P100-2002 ibm-1386_P100-2001 ibm-1388 ibm-1390 ibm-1399 ibm-16684 ibm-16804-s390 ibm-33722_P120-1999 ibm-37-s390 ibm-437 ibm-4517 ibm-4899 ibm-4909 ibm-4971

ibm-5123 ibm-5346 ibm-5347 ibm-5348 ibm-5349 ibm-5350 ibm-5351 ibm-5352 ibm-5353 ibm-5354 ibm-5471_P100-2006 ibm-720 ibm-737 ibm-775 ibm-803 ibm-813 ibm-8482 ibm-850 ibm-851 ibm-852 ibm-855 ibm-856 ibm-857 ibm-858 ibm-860 ibm-861 ibm-862 ibm-863 ibm-864 ibm-865 ibm-866 ibm-867 ibm-868 ibm-869 ibm-874 ibm-875 ibm-901 ibm-902 ibm-9067 ibm-916 ibm-921 ibm-922

ibm-930 ibm-933 ibm-935 ibm-937 ibm-939 ibm-9447 ibm-9448 ibm-9449 ibm-949_P110-1999 ibm-949_P11A-1999 ibm-950_P110-1999 ibm-954_P101-2000 ibm-971_P100-1995 ibm-eucKR IBM-Thai IMAP-mailbox-name ISO_2022,locale=ja,version=0 ISO_2022,locale=ja,version=1 (JIS) ISO_2022,locale=ja,version=2 ISO_2022,locale=ja,version=3 (JIS7) ISO_2022,locale=ja,version=4 (JIS8) ISO_2022,locale=ko,version=0 ISO_2022,locale=ko,version=1 ISO_2022,locale=zh,version=0 ISO_2022,locale=zh,version=1 ISO_2022,locale=zh,version=2 JIS (deprecated) KOI8-R KOI8-U Latin-9 Latin1 Latin1 (deprecated) Latin2 Latin3 Latin4 Latin5 Latin6 Latin8 LMBCS-1 macintosh MS_Kanji Native

SCSU Shift_JIS shift_jis78 SJIS (deprecated) Thai8 UNICODE Big Endian (deprecated) UNICODE Little Endian (deprecated) **US-ASCII** UTF-16 UTF-16 Big Endian UTF-16 Little Endian UTF-16 Opposite Endian UTF-16 Platform Endian UTF-16,version=1 UTF-16,version=2 UTF-16BE,version=1 UTF-16LE,version=1 UTF-32 UTF-32 Big Endian UTF-32 Little Endian UTF-32 Opposite Endian UTF-32 Platform Endian UTF-7 UTF-8 UTF-8 (deprecated) Windows 874 Windows 949 (korean) x-iscii-be x-iscii-de x-iscii-gu x-iscii-ka x-iscii-ma x-iscii-or x-iscii-pa x-iscii-ta x-iscii-te x-mac-ce x-mac-cyrillic x-mac-greek x-mac-turkish x11-compound-text

NONE and Zero

When the **Item Subclass** has a **Number** value and the **Interpret as** property has a **Character** value, the **NONE** and **Zero** properties are available. Expand the **NONE** or **Zero** property to specify an override data value to define the **Special Value** and **Required on input** properties.

NONE > Special Value and Zero > Special Value

Enter a value in the Special Value property if the item is NONE or Zero.

For example, if you specify * in the **Special Value** property for **NONE**, and a number object has the value *, it is interpreted as **NONE**.

If you enter a value in the **Special Value** property for **NONE** or **Zero**, enter the exact characters to be validated in the input data and built in the output data.

The maximum element length that is allowed for the Special Value property is 3000 bytes.

NONE > Required on input and Zero > Required on input

Select a value from the Required on input property list.

Yes

If the data object is **NONE** or **Zero**, the map uses the value in the **Special Value** property when it validates the item in the input.

No

Do not use the value in the **Special Value** property. No special values or input requirements are defined when data is **NONE** or **Zero**.

When the map builds the item in the output, the item might be either the value in the **Special Value** property or the default value for **NONE** or **Zero**. For example, if an item contains all pad characters and no actual data, the default value for **NONE** is used when that item is built in the output.

Places

The Places property allows you to specify the number of implied decimal places.

For item types defined with an **Item Subclass** of **Number**, a **Decimal** presentation, and a **Separator**, the **Places** property allows you to specify the minimum and maximum number of decimal places and whole number places. The minimum number of places must be less than or equal to the maximum number of places.

If the decimal number has no separator, use the Places property to specify the number of implied decimal places.

Text item subclass properties

You can interpret **Text** item subclass properties can be interpreted with a **Character** or **Binary** value. Depending on the value, character or binary, the following are text item subclass properties:

- "Interpret as Binary" on page 793 or "Interpret as Character" on page 794
- "Size (content)" on page 815
- "Pad" on page 801
- "Restrictions" on page 807
- "National language" on page 807

Interpret as binary

Binary text items have content size and pad properties. Binary data is required to be sized or of a fixed size.

Binary number items interpret the data as a binary number or as a byte stream.

Items with an item subclass of Text can be interpreted as character or binary.

The binary presentation options are Integer, Float, Packed, or BCD.

Interpret as character

Character number items interpret the data as symbolic data. Symbolic data has the same meaning on different computers. For example, a comma is symbolic because it has the same meaning, regardless of the computer type.

Character text items can have content size and pad properties.

When you select **Character**, the **Release** property is specific to the **Character** value and is *not* available as an option for a **Binary** value. For more information, see "Release characters" on page 786.

When interpret is set to Character, integer, decimal, and zoned presentation options are available.

Size (content)

Each text or syntax object can be defined with the minimum and maximum sizes in bytes and/or characters. The product determines size for text or syntax objects according to the following rules.

- When the size of an object is in bytes only, size and validation are calculated according to the size limitations set for bytes.
- When the size of an object is in characters only, size and validation are calculated according to the size limitations set for characters.
- When an object has size values defined for both bytes and characters, the object size is determined by characters (based on any character size limitations). Bytes are used to verify that the size of the data did not exceed any byte constraints that were set.

When the content size of a text or syntax item is specified in bytes, initiators, terminators, release characters, and pad characters are excluded from the count.

Min

The minimum size of the data object. You can enter values for bytes and/or characters.

The default value is 0. The largest value allowed is 65535.

Max

The maximum size of the data object. You can enter values for bytes and/or characters.

The default value is 0. The largest value allowed is 65535.

When there is no maximum content size limitation, this value is not required.



Note: If you delete the value in the Max Characters field, the maximum content size is set to zero.

During schema analysis, checks are performed on byte and/or character **Min** and **Max** values according to the following methods:

- When values are present for both Min > Bytes and Min > Characters, the Min > Bytes value must be greater than or equal to Min Characters.
- When values are present for both **Max Bytes** and **Max Characters**, **Max Bytes** must be greater than or equal to **Max Characters**.
- When no size limitations are present, no verification takes place.

Remember:

- Some character sets use two or more bytes per character.
- The trace file and audit log lengths are reported in bytes.

Pad

Pad implementation determines how the pad value is sized during validation and how the pad value is sized when written as output.

When the data value of the target item is smaller than the minimum length of that item, pad characters can be used to pad the data to that minimum length. Output data is built according to the pad definitions of the types. Bytes are the default measurement for sizing, however, both byte and character sizing options are available.

Yes

Enables the Pad option. Allows the item to contain both content and pad characters.

No

All data is assumed to be content on input; no pad characters are built on output.

Regular expressions

Regular expression is a sequence of characters to define a pattern.

Use the **Regular expression** property to generate text or numerical data that matches the given regular expression. The maximum length of the regular expression is 2000 characters.



- Regular expressions do not support certain notations like \\d and \\w. You cannot use regular expressions in JSON and XSD schemas.
- When you use @, #, < symbol, you need to escape it with backslash (\).

Restrictions

Restrictions of an item are the valid values of that item. When the **Interpret as** value is defined as **Character**, the **Restrictions** property is specific to the **Character** value and is not available as an option for a **Binary** value.

Depending on other Item Subclass settings, the Restrictions property can be set to Value, Character, or Range.

National language

The **National language** default value is **Western**. For initiator, terminator, and release character **Literal** values, you can optionally specify a "Data language" on page 808.

When the **Interpret as** value is defined as **Character**, the **National language** property is specific to the **Character** value and is not available as an option for a **Binary** value.

NONE

When the **Item Subclass** has a **Text** value and the **Interpret as** property has a **Character** or **Binary** value, the **NONE** property is available. Expand the **NONE** property to specify an override data value to define the **Special Value** and **Required on Input** properties.

NONE > Special Value

Enter a value in the Special Value property if the item is NONE.

For example, if you specify * in the **Special Value** property for **NONE**, and a text object has the value *, it is interpreted as **NONE**.

If you enter a value in the **Special Value** property for **NONE**, enter the exact characters to be validated in the input data and built in the output data.

The maximum element length that is allowed for the Special Value property is 3000 bytes.

NONE > Required on Input

Select a value from the Required on Input property list.

Yes

If the data object is **NONE**, the map uses the value in the **Special Value** property when it validates the item in the input.

No

Do not use the value in the **Special Value** property. No special values or input requirements are defined when data is **NONE**.

When the map builds the item in the output, the item might be either the value in the **Special Value** property, or the default value for **NONE**. For example, if an item contains all pad characters and no actual data, the default value for **NONE** is used when that item is built in the output.

Bidirectional

Use the Item subclass > Bidirectional property to define the data as bidirectional.

Certain languages that are read from right-to-left often contain numeric or other phrases that are read from left-toright. This type of data is called "bidirectional" because it changes direction in the middle of a line.

The default setting is No.

To enable this setting, select **Yes**. When you enable this setting, additional options are available to further define the bidirectional data.

Text items

The Bidirectional property for text item types provide options for symmetric swapping, ordering, orientation, and shaping.

Symmetric Swapping on page 790

Use this property to maintain the orientation of directional pairs of characters (such as parentheses, greater than/less than symbols, brackets, braces).

Ordering Scheme on page 914

This property pertains to the order of the data as stored in memory.

Logical, the default setting, indicates that the data is stored in memory from left-to-right, regardless of the orientation of the text. Using the **Visual** ordering scheme, the data is read and stored with the start character in the right-most position both visually and in memory.

Orientation on page 791

Orientation pertains to the direction of the text as read visually. The default direction is left-to-right (LTR), meaning the text object is read starting from the left. The direction can be right-to-left (RTL), meaning the object is read starting from the right. When you select RTL, the behavior of some text functions (such as LEFT, RIGHT, MID) can change.

Use the **Contextual LTR** and **Contextual RTL** settings when the orientation should be taken from the context of the data because the data contains "strong" characters that are either orientation left or orientation right. When no strong characters are present in the data, the orientation will be based on this setting.

For example, when you set the orientation to **Contextual LTR** and no strong characters are encountered (meaning the data is orientation-neutral), the data orientation will be considered left-to-right.

Text Shaping on page 791

Use this property to produce output in a different glyph (shape or bit pattern). The default setting is off, or **Unshaped**.

To enable text shaping, select **Shaped**. The output will be shaped according to the code page of the target object.

Character number items

For character number item types, you can additionally define a numeric shaping characteristic.

Numeric Shaping on page 791

Use this property to indicate whether the output of numeric values will have the shapes that are used in English (Arabic digits 0123456789) or the national numerical shapes.

The default setting is **Regular**, which means Arabic digits (0123456789). Otherwise, select **Arabic-Indic** (9 Λ V **1** ο ε Ψ Γ Ι •).

The Bidirectional property is not applicable to binary numbers.

Date & Time item subclass properties

The Date & Time properties provide the flexibility to define multiple combinations of date-time formats.

Date & Time items can be interpreted as either binary or character. (See sections "Interpret as Binary" on page 793 and "Interpret as Character" on page 794).

For binary Date & Time items, the Presentation property has two different values: Packed and BCD.

Packed

The Packed value is a number that has size, decimal places, and sign properties.

BCD

The BCD value is a binary coded decimal number that has size.

Other Item Subclass properties for Date & Time are displayed depending on the Interpret as setting (Binary or Character).

Date

For binary Date & Time items, use the Date property to define whether the date format is enabled.

Yes

Date format is enabled for this type. Expand the Format property to select the date format.

No

Date is not defined for this type.

Date > format

Select the date format that the data interpretation will be based on. For binary **Date & Time** items, the **Date > Format** property has four values.

CCYYDDD and YYDDD Julian date formats are supported.

- CCYYMMDD
- YYMMDD
- CCYYDDD
- YYDDD

Time

For binary **Date & Time** items, use the **Time** property to define whether the time format is enabled. Select one of the following options:

Yes

Time format is enabled for this type. Expand the Format property to select the time format.

No

Time is not defined for this type.

Time > format

Select the time format that the data interpretation will be based on. For binary **Date & Time** items, the **Time > Format** property has several values. The following choices are available from the drop-down list:

- HH24MMSS
- HH24MM
- HH24:MM:SS
- HH24:MM
- Custom

Format

You can define a date-time format from within the type properties, except for native schema XML.

The output format for the native schema XML date/time field is always:

{CCYY-MM-DD}T{HH24:MM:SS.3-3+/-ZZ:ZZ}

To specify a different output format, use Xerces XML instead.

To define the Date & Time format:

- 1. Open the type properties.
- 2. In the Item Subclass > Format property, click the browse button.

The **Date Time** dialog is displayed.

3. Make your format selections and click **OK**.

You can use alphabetical characters as separators. In the example, 2001-04-02T10:32:59-0500, **T** is the separator.

Separators are limited to 60 characters.

Supported date formats:

- CCYYMMDD
- YYMMDD
- MMDDCCYY
- MMDDYY
- CCYYDDD
- YYDDD
- DDMMCCYY

• DDMMYY

Note: The DDMMCCYY and DDMMYY formats did not exist prior to version 6.5 of the Design Studio. If you had defined either one of these formats prior to 6.5 as a custom format, it will be recognized in 6.5 as the respective new format, instead of the previously defined custom format.

Use of format elements

If you select the same format element more than once for the same item, that item may not be validated separately. If you specify **MON** twice, the day of the month is not validated separately for both months. For example, if the date format element **MON** is used twice for a single item, with the following format string:

MON D-MON D

Suppose the data is this:

Feb 28-Mar 31

28 is not validated for the month of February.

Some combinations of reserved words are invalid. A separator must follow reserved words representing a variable number of digits (**D** and **M** for date) if data follows.

For example:

- D/M/CCYY is valid.
- CCYYM/D is valid.
- DMCCYY is invalid.

See the Design Studio Introduction documentation for a list of reserve words and symbols.

Custom date format

After choosing **Custom** from the date format drop-down list, click browse. The **Date Format** dialog is displayed.

You can only use non-alphanumeric characters (excluding the {, } and [,] non-alphanumeric characters) as separators in the custom **Date Format** dialog.

The following table provides examples of date formats.

Date Format	Description	Example
CCYY	4-digit Century + Year	1999
YY	2-digit Year (00-99)	99
MM	2-digit Month (01-12)	12
М	1- or 2-digit Month (1-12)	8

Date Format	Description	Example
MON	3-character Month (Jan to Dec)	JAN
MONTH	Full name of Month	January
DDD	3-digit Day of year (001-366)	32
DD	2-digit Day of Month (01-31)	31
D	1- or 2-digit Day of Month (1-31)	7
DY	3-character Day of Week (Sun-Sat)	Fri
DAY	Full Name of Day of Week (Sunday-Saturday)	Friday
WW	1- or 2-digit Week of Year	13
Qn	Quarter of Year (Q1-Q4)	Q2
Custom	User defined custom date format	

After you define and save a custom format, the custom format string is displayed in the **Properties** window. For example, the custom date format **CCYYMMDD**, and the custom time format **HH24MMSS** display as:

{CCYYMMDD}{HH24MMSS}

Custom Time Format

After selecting Custom from the time format list, click browse. The Time Format window is displayed.

You can only use non-alphanumeric characters as separators, excluding the {, } and [,] non-alphanumeric characters, in the **Time Format** window.

The following table provides time format examples.

Time Format	Description	Example
HH24	2-digit hour in 24 hour format (00-23)	23
H24	1- or 2-digit hour in 24 hour format (0-23)	11
HH12	2-digit hour in 12 hour format (00-12)	08
H12	1- or 2-digit hour in 12 hour format (0-12)	8
ММ	2-digit minute (00-59)	09
Μ	1- or 2-digit minute (0-59)	9
SS	2-digit second (00-59)	05
S	1- or 2-digit second (0-59)	5
AM/PM	Meridian (AM/PM)	AM

Time Format	Description	Example
ZZZ	A time zone abbreviation. See "Time Zones" on page 824 for a list of supported time zones.	EST
+/-ZZZZ	Hours and minutes before or after the Greenwich Mean Time (GMT). GMT is now referred to as Coordinated Universal Time (UTC).	+0500
+/-ZZ:ZZ	4-digit time where the format is a 2-digit hour and 2-digit minute, separated by a colon.	+05:00
+/-ZZ[:ZZ]	4-digit time where the format is a 2-digit hour and an optional 2- digit minute, separated by colon.	+05:00
+/-ZZ[ZZ]	4-digit time where the format is a 2-digit hour and an optional 2- digit minute.	+0500
TZD	4-digit time where the format is a 2-digit hour and 2-digit minute, separated by a colon. Z on output, if value is $+/-00:00$.	+05:00

After you define and save a custom format, the custom format string is displayed in the **Properties** window. For example, the custom date format **CCYYMMDD**, and the custom time format **HH24MMSS** display as:**{CCYYMMDD**} **{HH24MMSS}**

Time zones

The following table lists the supported time zones.

Time Zone	Abbreviation	Hours before Green- wich Mean Time	Hours ahead of Green- wich Mean Time
Greenwich Mean Time (Zulu)	GMT	0	0
West African Time	WAT	-1	+23
Azores Time	AT	-2	+22
No name; Brasilia Time	###	-3	+21
Atlantic Standard Time	AST	-4	+20
Eastern Standard Time	EST	-5	+19
Central Standard Time	CST	-6	+18
Mountain Pacific Time	MST	-7	+17
Pacific Standard Time	PST	-8	+16
Yukon Standard Time	YST	-9	+15
Hawaii Standard Time	HST	-10	+14

Time Zone	Abbreviation	Hours before Green- wich Mean Time	Hours ahead of Green- wich Mean Time
Nome Time	NT	-11	+13
New Zealand Time	NZT	-12	+12
No name; no location	###	-13	+11
Guam Standard Time	GST	-14	+10
Japan Standard Time	JST	-15	+9
China Coast Time	CCT	-16	+8
West Australia Time	WAT	-17	+7
Zulu + 6 (Russia zone 6)	ZP6	-18	+6
Zulu + 5 (Russia zone 5)	ZP5	-19	+5
Zulu + 4 (Russia zone 4)	ZP4	-20	+4
Baghdad Time	ВТ	-21	+3
Eastern European Time	EET	-22	+2
Central European Time	CET	-23	+1

Time zone format string for XML

Note: The output format for the native schema XML date/time field is always:

{CCYY-MM-DD}T{HH24:MM:SS.3-3+/-ZZ:ZZ}

To specify a different output format, use Xerces XML.

The following time zone strings support the specification of a single character Z to indicate Coordinated Universal Time (UTC), as described by the World Wide Web Consortium (www.w3c.org) and the ISO 8601 standard:

- +/-ZZZZ
- +/-ZZ:ZZ
- TZD

When the +/-ZZ:ZZ or +/-ZZZZ format string is specified, the data validation process works in the following manner:

- Valid data that corresponds to this format string will contain either a character literal Z (representing UTC) or a zone in the appropriate format: +/-ZZZZ or +/-ZZZZ, as specified.
- If a character literal Z is present, it shall be interpreted, and treated at mapping time, as UTC, which is equivalent to +00:00 or +0000.

When the TZD format string is specified, the data validation and output generation processes work in the following manner:

- Valid data that corresponds to this format string will contain either a character literal Z, representing UTC, or a zone, in the +/-ZZ:ZZ format.
- If a character literal Z is present, it shall be interpreted, and treated at mapping time, as UTC, which is equivalent to +00:00.
- If the value is +/-00:00, it generates Z in the output. Otherwise, it generates the output in +/-ZZ:ZZ format.

The following time zone strings support the omission of the minute portion of the difference from UTC:

- +/-ZZ[:ZZ]
- +/-ZZ[ZZ]

Optional time segments of the time format string

This section discusses how you can specify a portion of a time-format string to be optional. For example, you can specify that either the *time zone* portion or the *hours, minutes, seconds, fractional seconds, Meridian* portion is optional.

This flexibility is also applicable to time-format strings used in functions or in schema scripts imported by the Type Tree Maker.

Only the time portion **or** the zone portion can be optional-not both.

To specify a portion of the time-format string as optional:

- 1. The following procedure assumes that the Item Subclass property of your schema is Date & Time.
- 2. From within the schema properties, navigate to Item Subclass > Format.
- 3. Click the browse button to open the Date Time dialog.
- 4. From a Format field that is set to **Time**, go to the field directly below it and choose **Custom** from the dropdown menu.
- 5. Next to the Format field with Custom selected, click the browse button. The Time Format dialog is displayed.
- 6. Choose from the following tasks:
 - To specify the *hours*, *minutes*, *seconds*, *fractional seconds*, and *Meridian*-portion of the time format string as optional, enable the check box on the far left side of the dialog.
 - To specify the time zone portion of the time format string as optional, enable the check box.

Only one segment of the time format string can be specified as optional.

Date and time format examples

The following list includes examples of popular standard date and time formats:

Format

Description

X12 EDI

Fractional seconds format: HH24MM[SS[0-2]].

SWIFT

Time Zone Designator or UTC Designator format: HH24MMSS[TZD].

TimeStamp format: CCYY-MM-DDTHH:MM[SS[.0-6]][TZD], which is a combination of date and time.

HL7

```
Time format: HH24MM[SS[.0-6]][+/-ZZZZ].
```

TimeStamp format: CCYYMMDDHHMM[SS[.0-6]][+/-ZZZZ], which is a combination of date and time.

SAP

Time format: HHMMSS.

ODBC

Time format: HH: MM: SS[.0-9], which is the form most commonly used in **ODBC** mapping. The fractional part is optional and not often used.

NONE and Zero

When the **Item Subclass** has a **Date & Time** value and the **Interpret as** property has a **Character** value, the **NONE** and **Zero** properties are available. Expand the **NONE** or **Zero** property to specify an override data value to define the **Special Value** and **Required on input** properties.

NONE > Special Value and Zero > Special Value

Enter a value in the Special Value property if the item is NONE or Zero.

For example, if you specify * in the **Special Value** property for **NONE**, and a data and time object has the value *, it is interpreted as **NONE**.

If you enter a value in the **Special Value** property for **NONE** or **Zero**, enter the exact characters to be validated in the input data and built in the output data.

The maximum element length that is allowed for the Special Value property is 3000 bytes.

NONE > Required on input and Zero > Required on input

Select a value from the Required on input property list.

HCL OneTest[™] Server

Yes

If the data object is **NONE** or **Zero**, the map uses the value in the **Special Value** property when it validates the item in the input.

No

Do not use the value in the **Special Value** property. No special values or input requirements are defined when data is **NONE** or **Zero**.

When the map builds the item in the output, the item might be either the value in the **Special Value** property or the default value for **NONE** or **Zero**. For example, if an item contains all pad characters and no actual data, the default value for **NONE** is used when that item is built in the output.

Syntax item subclass properties

Syntax objects are characters that precede, separate, or follow a particular data object. Item types with an **Item Subclass** of **Syntax** are defined and used to specify delimiters, initiators, terminators, and release characters. Syntax objects with variable values are defined as the syntax object's **Variable** property. Syntax objects appearing as actual data to be mapped as output data are defined as components of a type.

Syntax objects with variable values

About this task

Using a syntax item to specify delimiters, initiators, terminators, and release characters is required when the value of syntax objects (delimiters, initiators, terminators, and release characters) may vary.

The restrictions of syntax items define the variable literal values.

To define a variable syntax object:

- 1. Create an item type with an Item Subclass of Syntax to represent the syntax object.
- 2. Define the restrictions for the syntax item type.
- 3. For the item or group type with the variable syntax object, for the **Variable** delimiter, initiator, terminator, and release character, select the item from the **Item** drop-down list in the **Properties** view.
- 4. For the Find property, select Yes.

Only item types defined with an Item Subclass of Syntax appear in the drop-down list.

Example of variable syntax object as an item type

In this example, the group type Header has variable delimiter values of: , * + \sim

- 1. Create an item type with the **Item Subclass** of **Syntax** and the name **Delimiter**. (The name can be any valid type name, but naming this item **Delimiter** is useful).
- 2. To define the item restrictions, double-click the Delimiter type. The item view is displayed.
- 3. Define the restrictions in the Include column.

- 4. In the Properties window, select Syntax for the Item Subclass property.
- 5. Open the properties for the delimited group type Header.
- 6. For the Syntax property, choose Delimited.
- 7. For the Delimiter property, choose Variable.
- 8. Expand the Delimiter property.
- 9. Define the **Delimiter > Default** literal value.
- 10. For the variable **Delimiter Item** property, choose the item type **Delimiter** from the drop-down list.
- 11. Indicate that the variable delimiter should be determined for each occurrence of the object by selecting **Yes** for the **Delimiter > Find** property.

Syntax objects as data

The value of a syntax object (delimiters, initiators, terminators, and release characters) may appear as actual data that can be mapped. Syntax objects that appear as actual data are defined as components of a type.

Example of syntax objects as components of a type

The following is an example of defining a syntax object as a component of a group type. The following data represents a message received from multiple departments.

Each message is made up of segments. Each department uses different segment delimiters and terminators. The message format specifies that the delimiter and terminator are the first two bytes of the message, followed by the actual data.

To define syntax objects for the delimiter and terminator:

- 1. Define two separate syntax objects with an **Item Subclass** of **Syntax**, one for the message delimiter and one for the message terminator. Appropriate type names might be **SegmentDelimiter** and **SegmentTerminator**.
- Define the possible message delimiter values as restrictions of the SegmentDelimiter item type. Define the possible message terminator values as restrictions of the SegmentTerminator item type.
- 3. Define these item types as the first two components of the group type Message.
- 4. Expand the **Delimiter** property.
- 5. For the variable Delimiter > Item property, select SegmentDelimiter from the drop-down list.
- 6. For the variable Terminator > Item property, select SegmentTerminator from the drop-down list.

During the data validation process, the component **SegmentDelimiter** appears in the data with a value of *. The group type **Segment** has a variable delimiter specified as the item type **SegmentDelimiter**, with the value *. Therefore, it is understood that the segment has * as the delimiter.

When the value of a syntax object appears as actual data, it can be mapped as data. For example, source data may use different delimiters from several different sources. Acknowledgments of this data must be sent back to the source using the delimiter used in the original data. This data can be mapped from the input to the output if these syntax objects are defined as components within the data.

Delimiter > find

When syntax objects are **Variable**, the **Find** property must be defined. The **Find** property determines whether the value of syntax object is set on each occurrence or whether the current setting (or default value) is used.

When the **Initiator**, **Terminator**, **Release**, or **Delimiter** property value is **Variable**, select one of the following from the drop-down list in the **Value** column:

Yes

Determine the value of the syntax object each time an occurrence of that type is found. After the value of that syntax object is found, that particular value is used until it is reset by another **Find** or by the occurrence of that syntax item as a component.

INPUT: The value of the object in the input data is determined by the location in the data stream and the restrictions of the syntax item.

OUTPUT: The default value is used for building the syntax object in the output data.

No

The variable syntax object is defined as the current value or, if it is not set, as the default value.

INPUT: If the syntax object is not encountered in the data stream, the value of the syntax object is the default value.

OUTPUT: If the value of the syntax item has not been previously set, the default value is used.

Group properties

Group properties include the group's **Subclass** and **Format**, which describes how to distinguish one component of that group from another component of that group.

Group subclass

Group types have a subclass of Sequence, Choice, or Unordered.

Property	Description
Sequence	A partially-ordered or sequenced group of data objects.
	Each component of a Sequence group is validated sequentially.
Choice	Choice group provides the ability to define a selection from a set of components like a multiple-choice question on a test.
	A Choice group is valid when the data matches one of the components of the choice group. Validation of a Choice group is attempted in the order of the components until a single component is validated. If the Choice group has an initiator, the initiator is validated first.

Property Description

Unordered

An **Unordered** group has one or more components. **Unordered** group can only have an **Implicit** format property, with the same syntax options as sequence groups: **None** or **Delimited**.

Properties of group subclasses

The distinction between **Sequence** and **Choice** group subclasses is that the **Choice** group has no **Partition** or **Format** properties.

Type syntax properties such as **Initiator**, **Terminator**, **Release**, and **Empty** can be applied to **Choice** groups. If a release character is defined, by default it applies to the **Terminator**.

Choice group components

A **Choice** group can have both items and groups as components. A partitioned **Sequence** group can only have group subtypes.

The components of **Choice** group must be distinguishable from each other. The **Choice** group components cannot have a range other than (1:1). Only one component of a **Choice** group built in the output data.

A **Choice** group data type is only one of the group components. For example, the data type **Record** is a group type with a **Group Subclass** of **Choice**. The group type **Record** has three components: **Order**, **Invoice**, and **Sales**. The data validation of **Record** can have only one of the components: **Order**, **Invoice**, or **Sales**. For this reason, the components of a **Choice** group must have a component range of (1:1).

Unordered group components

An **Unordered** group has one or more components that can appear in the data stream in any order. They allow many SWIFT and FIX message types, for example, to be defined in a more natural way.

Unordered groups have no partitioned property. They have **Implicit** format properties with the same syntax options as sequence groups: **None** and **Delimited**.

When a group is defined as **Unordered**, any component can appear in the data stream. A component can be an item or a group.

Unordered group components have a range property. For example, if the unordered group, **A**, has the following component list:

B(1:S) C D(S)

then **A** must have one **C**, at least one **B**, and possibly some **D**s. They could appear in any order. For example, data for **A** could have the pattern: **CDDBDDD** or **BBBDDCBD**.

Component rules of an unordered group cannot reference other components of the same group. They can only reference the component to which the rule refers and the objects contained in that component.

Sequence group formats

A Sequence group has either an Explicit or Implicit format.

Explicit

The explicit format relies on syntax to separate components. Each component can be identified by its position or by a delimiter in the data. Delimiters appear for missing components.

Implicit

The implicit format relies on the properties of the component types. The format is not fixed. If delimiters separate components, they do not appear for missing components.

For example, if each component of a fixed group has a fixed size, the component is distinguished from the next component by its position in the data. Or, a group may have delimiters that appear for missing components. In these cases, the format is apparent; the group has an explicit format.

If a group does not have an explicit format, it has an implicit format. An implicit format relies on the properties of the component types. In this example, the components make some pattern in the data and it is possible to distinguish between them, but the format is not fixed and if delimiters separate components, they do not appear for missing components.

When deciding what format a group has, it may help to ask first whether it is clear where one component ends and another begins. Generally, a group has an explicit format if the position of each component in the data stream is always the same or if a delimiter always marks the place for each component.

Explicit format

To specify that a group has an explicit format, choose **Explicit** for the **Format** property. Select a setting for the **Track** property, and choose the group's syntax: **Fixed** or **Delimited**.

Track

The **Track** property indicates whether the system should track only the components that have content or all components, including those that do not have content. The settings are **Content** and **Places**.

For example, if a group **StudyGroup** has the component **Name(s)**, and **Places** is specified for the **Track** property, any empty occurrences of **Name** are tracked.

Suppose Name has an * initiator and a space pad character. This is the data for StudyGroup:

*Carolyn * *Stuart *Margaret

Notice that the second Name is missing.

If **Places** is specified for the **Track** property, and you want to map the third **Name**, the empty **Name** would be counted as an occurrence, so the third **Name** would be Stuart. However, if **Content** is specified for the **Track** property, the empty **Name** would not be counted as an occurrence because it does not have content and the third **Name** would be Margaret.

Fixed syntax

If a group data object is always the same size (in bytes), it has a fixed syntax. For example, a record that is always 160 bytes has a fixed syntax.

Each component of a fixed group must be fixed. If you break down a fixed group, it ultimately consists of items that are fixed. Each is padded to a fixed size or its minimum and maximum content size are equal. Do not specify the size of a fixed group. The size is automatically calculated based on the size of the group's components.

Guidelines for defining a fixed group

- Each component must be a group with a fixed syntax or a fixed item. The item is padded to a fixed size or its minimum and maximum content size are equal.
- \bullet Each component must have a specified range maximum. The maximum cannot be $_{\rm s}.$
- If a component range minimum is not equal to the maximum, content is not required for optional component occurrences. For example, if a component is the item **ShippingAddress** (0:1) and **ShippingAddress** has a minimum content size of two characters, data may either contain: 1) all pad characters, or 2) if content is in the data stream, there must be a minimum of two characters for a **ShippingAddress**. If a component is a group, no content is required for any of the items contained in an optional occurrence of that component.

Explicit delimited syntax

An explicit-format group with a delimited syntax is one whose components are separated by a delimiter and the delimiter appears as a placeholder even when a component has no content.

About delimiters and explicit-format groups:

- The only time a delimiter can be missing is when all components following the delimiter are optional and there is no data for the optional components.
- A delimiter is a character or series of characters that separates data objects.
- A delimiter cannot be longer than 500 bytes.
- The delimiter of a group appears inside the group, separating its components. When a group is delimited, that indicates something about the components of the group. The delimiter inside a group is delimiting the components.

Example

The group **Employee** has an explicit-delimited format because a comma delimiter appears between **Employee's** components, the items that make up the **Employee** object. In addition, the delimiter is displayed when a component is missing and there is data for components following it.

The components of Employee are the items ID#, Name, Department, Address, and Age.

Delimiter

Use the **Delimiter** property to specify the value and location of the delimiter. For specific information on specifying the delimiter, see "Specifying a Delimiter" on page 836.

In an explicit-delimited group, if the delimiter is whitespace <WSP>, the delimiter is interpreted as one byte long; each <WSP> character is interpreted as another delimiter. In the output, a <WSP> delimiter is one space.

The limit for <WSP> is 512 bytes.

Implicit format

In a group with an implicit format, the components are distinguishable not by delimiter or position, but by their pattern; something in the definition of the component types themselves. The group has no syntax property that distinguishes one component from another.

For example, the type **File** consists of **Record**(s). <CR><LF> appears at the end of each **Record**. It has been defined as the terminator of **Record**. **File**, however, has no syntax of its own. The **Record** terminator distinguishes one **Record** from another.

To specify that a group has an implicit format, choose **Implicit** for the **Format** property. Optionally, define a comment type, and choose the group's syntax: **Delimited** or **None**.

Floating component

The floating component represents an object that may appear after any component of the group.

An implicit group can have a floating component; an explicit group cannot. If the group is prefix or infix delimited, the floating component is displayed before the delimiter. If the group is postfix delimited, the floating component is displayed after the delimiter.

A floating component can be an optional component that may appear after any other component. However, it is not included in the component list because it does not appear at a specific location.

If a group has a floating component, a component must be distinguishable from a floating component. For example, components and floating component could start with different initiators.



Note: When a floating component appears in the input data, it is validated during mapping. If there are floating components in your output data, define them as actual components of the output.

A floating component can appear after the initiator (when the type has an initiator), after each component, or both. For EDI and other existing floating components, trees will be converted as *"after each component"*.

A floating component can be specified for implicit sequence group, choice group, and unordered group definitions.

Implicit whitespace syntax

Select **Whitespace** for the **Component Syntax** value when white spaces are not allowed in the data. When you select the **Whitespace** option, define the **Build As** and **Character Set** properties.



Note: Helpful for XML data.

Build as

Enter the characters that will replace white spaces.

The Build As property is only available when the Component Syntax property is defined as Whitespace.

Character set

Select a character set for the component from the drop-down list.

The default value is Native, where the literal values use the native character set of the computer.

Supported character sets (code pages) on page 808

Implicit delimited syntax

If a delimiter separates the components of a group, but the delimiter does not appear when a component is missing, the group has an implicit format with a delimited syntax.

In certain data, the delimiter may not be a placeholder.

Delimiter

Use the **Delimiter** property to specify the value and location of the delimiter. For specific information on specifying the delimiter, see "Specifying a Delimiter" on page 836.

In an implicit-delimited group, when the delimiter is whitespace <WSP>, all contiguous <WSP> characters are treated as one delimiter. In the output, a <WSP> delimiter is built as one space.

The limit for <WSP> is 512 bytes.

No syntax

To specify a group with an implicit format that has no syntax, choose None for the Component Syntax value.

Distinguishable components of an implicit group

Each component of an implicit group needs to be recognizable. If either of two different components appears at the same place in a data stream, there must be a distinguishable difference between one component and the other.

Sometimes components of an implicit group may be distinguished because there is something in the data that distinguishes them.

After the first item **Line** of the **Form**, the next data object could be another item **Line**. Or, it could be a **Trailer Line**. When looking at a particular **Line**, there is something in the data that identifies that **Line** either as a **Header Line**, an item **Line**, or a **Trailer Line**. The type **Line** has been partitioned to distinguish between the different kinds of **Lines**.

Specifying a delimiter

For the **Delimiter** property, specify whether the delimiter is a literal or a variable value.

Literal

If the delimiter is a constant value, enter the delimiter value in the **Value** field. To enter a non-printable value, click the browse button and select a value from the **Symbols** dialog.

National language

The **National language** default value is **Western**. For initiator, terminator, and release character **Literal** values, you can optionally specify a "Data language" on page 808.

When the **Interpret as** value is defined as **Character**, the **National language** property is specific to the **Character** value and is not available as an option for a **Binary** value.

Data language

Use the National language > Data language property to define the data language or character set.

Supported code pages on page 808

Variable

Sometimes you do not know what delimiter is used in the data source, especially if you receive that data from an outside source. However, you know all of the possible values that the delimiter could be. You can create an item to represent this delimiter and specify all of the possible values as restrictions of that item. The value of the delimiter in the data is found.

To specify an item as a Variable Delimiter:

- 1. In the **Properties** view for the delimited group, click in the **Delimiter > Item** value field.
- 2. Press Alt and drag the item from the schema editor into the Item field.

Location

The **Location** property specifies the location of the delimiter with respect to the components. The options are prefix (the delimiter appears before the component), postfix (the delimiter appears after the component), and infix (the delimiter appears between components).

The following table explains each option.

Property	Description	Example
Prefix	Before each component.	*a*a*b*c
	Before each member of a component in a series.	
Postfix	After each component.	a*a*b*c*
	After each member of a component in a series.	
Infix	Between components.	a*a*b*c
	Between members of a component in a series.	

Delimiter value appears as data

Delimiters do not appear as part of the actual data. For example, if the delimiter is specified as a comma, the comma in the following text item would be considered a delimiter, rather than part of the data itself:

Tom Smith, Jr.

If the data does contain the delimiter value, there are ways to format the data so that both the data and the delimiter are distinguishable. For example, text items can be enclosed in quotation marks. Or, a release character may be used. For information about release characters, see "Release Characters" on page 786.

Allow Excess Trailing Delimiters

The schema validation process allows data that contains excess trailing delimiters on sequence groups.

You can change the default setting for the **Allow Excess Trailing Delimiters** property to **No** so that the schema validation process, instead, fails data that contains excess trailing delimiters.

The schema validation process interprets a delimited sequence group that contains optional components at the end of its sequence, as having excess trailing delimiters.

For example, GROUPA contains the following components: COMPA (mandatory), COMPB (optional), COMPC (optional), and COMPD (optional). The group is infix-delimited by a tilde. The following data stream examples are valid for GROUPA:

A~B~C~D A~B~C~ A~B~~ A~~

For this example, you want the schema validation process to disallow all of the data stream examples that contain unnecessary or excess trailing delimiters. To disallow the excess trailing delimiters, you can change the setting for

the **Allow Excess Trailing Delimiters** property to **No**. The result is that the validation process fails all of the examples except the first one.

Defining exclude characters

During the run time, the data validation process uses the **Exclude Character List** group property to define a set of characters that are not allowed to exist in the data stream as data content.

The data validation process allows these excluded characters to exist in the data stream as syntax, such as delimiters, if they are not being used as data content.

The group exclude characters might be derived from previously parsed values in the data stream or might be defined as literal values.

When you define exclude characters at the group level, the data validation process handles these specified characters as if they were in-scope data syntax.

For example, you have a schema which defines two groups, GROUPA and GROUPB. The tree defines the asterisk (*) character as a group delimiter for GROUPA. It defines the at-sign (@) character as a group delimiter for GROUPB. The tree also defines the FILE group, which contains both GROUPA records and GROUPB records.

The data stream contains content corresponding to the FILE group, which is composed of a series of both GROUPA and GROUPB records.

When the data validation process starts, it parses and validates this data stream. Since the asterisk is the delimiter of GROUPA, the data content of GROUPA records is only allowed to contain asterisk characters that are escaped. If the data content contains non-escaped asterisk characters, those GROUPA records fail data validation. Similarly, since the at-sign is the delimiter of GROUPB, the data content of GROUPB records is not allowed to contain non-escaped at-sign characters. If it does, those GROUPB records fail data validation.

The schema defines the delimiters, or markup, for the GROUPA and GROUPB records. Asterisk characters are considered to be in-scope markup while the data validation process handles GROUPA records. At-sign characters are considered to be in-scope markup while the data validation process handles GROUPB records.

Conversely, GROUPA data content is allowed to contain at-sign characters, as the GROUPB at-sign delimiter does not apply to GROUPA records. Therefore, at-sign characters are considered out-of-scope markup for GROUPA records. GROUPB data content is allowed to contain asterisk characters, as the GROUPA asterisk delimiter does not apply to GROUPB records. Therefore, asterisk characters are considered out-of-scope markup for GROUPB records.

You might require the data validation process to exclude asterisk and at-sign characters in all of the data content for both GROUPA and GROUPB records, except when those characters are used as delimiters.

If so, use the **Exclude Character List** property to specify the asterisk and at-sign literal values at the FILE group level. When the validation process evaluates the data, it throws an exception if there is an asterisk (*) or an at-sign (@) character in the data content within the FILE group. The asterisk and at-sign characters are still valid if they are used as group delimiters; they are invalid if they are used in data content. Performance tip: The Exclude Character List property causes the map validation process to use more resources as it searches for each of the exclude group characters in every data element under the group on which it is defined.

Open the **Exclude Character List** window by clicking the **Value** field on the **Exclude Character List** property, and then clicking the button that appears at the end of the field. Specify the characters in the list as literal characters or syntax items. You can use the **Add Literal**, **Add Syntax Item**, **Edit**, **Remove**, and **Remove All** functions to add literal characters and syntax items to the list, edit them, and remove them from the list.

Escaping an excluded character in the data content

Select **Release Exclude Characters** when you configure the exclude character list to enable the release character to escape excluded characters. When enabled, a release character that precedes an excluded character in data content escapes the excluded character, and the data content passes validation.

Related reference

Release characters on page 786

XML properties in the schema

When you open a schema in the schema designer after you imported it from a DTD or XML Schema, the XML-specific properties are displayed as read-only fields.

For each type in the resulting schema, the **Intent** property is either **General** (indicating non-XML) or **XML**. All category types that are created during the import process are considered non-XML properties. All group and item types that are created during the import process are considered XML properties.

Any types that you manually add to the XML type tree are considered non-XML and have **General** intent. In such a case where there are both XML and non-XML types present (such as EDI data), the appropriate method of validation is determined automatically.

Support for XML constructs

HCL® OneTest[™] Data validation supports the following XML constructs.

Character Data

During validation, character data is mapped by the XML parser to HCL® OneTest[™] Data types. This data includes both parsed character data (PCDATA) and unparsed character data (CDATA).

Comments and Processor Instructions

XML comments and processing instructions (PI) are mapped to floating components in schemas.

Namespaces

The XML Schema importer supports the specification of arbitrary prefixes for namespaces declared in the input grammar.

XSDL Hints

The **xsi:schemaLocation** and **xsi:noNamespaceSchemaLocation** attributes are collectively known as XML Schema Definition Language (XSDL) hints. These attributes specify the location of the XML Schema(s) that the XML parser uses for validation.

An XML Schema allows either or both of these attributes to display within any element tag. But the XML parser respects the location values only when the XSDL hint is specified in the root element of the schema.

The **Doc** group type of schemas that are created with the XML Schema or XML DTD importer contains the location of the Xerces DTD or Xerces XML Schema that is used for Xerces XML validation. The **Intent > Validate As > Location** property can be modified. However, use the **Schema > Type > Metadata** card setting in the map to change the location of the DTD or Schema if needed.

Empty Elements

Only one set of initiators and terminators for the Empty element is required for validation.

Nillable Elements

A nillable element can have one of three states: absent, present with content, or present with nil content. Both the DTD and XML Schema allow the definition of optional elements in the instance document. Additionally, the XML Schema allows nillable elements where the content can be empty when it contains an **xsi:nil** attribute with a value of "true", despite the fact the element's content is mandatory.

The XML Schema Importer can create the content of a nillable element within a group with a range of (0:1), which makes the element content optional.

Mixed Content

When parsing elements with a mixed content model (containing both character data and child elements), the DTD and XML Schema importers generate text items within the mixed content (instead of character sequences).

Regular Expressions

An XML Schema allows the restriction of the values of simple types that are based on regular expressions or pattern facets. During XML validation, the parser enforces the pattern facet. The XML Schema Importer fills the appropriate type properties with pattern facets encountered in the input schema, which are viewable in the schema designer.

XML schema datatypes

This section describes the schema constructs that correspond to XML Schema datatypes.

The following table lists some common XML Schema datatypes with their corresponding type property values in the schema designer.

XML Schema Datatype	Type Property	Value
simpleType	Intent > Validate As	XML_SIMPLETYPE
complexType	Intent > Validate As	XML_COMPLEXTYPE
element	Intent > Validate As	XML_ELEMENT
attribute	Intent > Validate As	XML_ATTRIBUTE
group	Intent > Validate As	XML_GROUP

Simple types

Elements that have assigned simple types have character data content but not child elements or attributes.

Simple type elements are represented in the Type Designer type properties with the value XML_SIMPLETYPE.

Complex types

Elements that have assigned complex types can have both child elements and attributes. The order and structure of the child elements of a complex type are known as its content model. Content models are defined using a combination of model groups, element declarations or references, and wild cards. There are three kinds of model groups: **all, choice** and **sequence**.

Complex type elements, including the complex types using compositor elements, are represented in the type properties with the value XML_COMPLEXTYPE.

Elements

Element declarations are either local or global. Local elements are represented in the schema designer type properties with the value: XML_ELEMENT.

When the schema defines several global elements, the generated schema includes a Global choice group that contains all of the global elements. A Global choice group is represented in the type properties with the value XML_BODY.

Attributes

Attributes are another building block of XML. The import process uses attribute declarations to name attributes and associate them to particular simple types. Attribute declarations can be either local or global.

Attributes, including both local and global, are represented in the type properties with the value XML_ATTRIBUTE.

Groups and substitution groups

One way an XML Schema allows the creation of reusable content is by using named model groups. These global groups can be referenced throughout a schema.

Substitution groups are a flexible way to designate element declarations as substitutes for other element declarations in a content model. New element declarations can easily be designated as substitutes from other schema documents or namespaces without changing the original content model.

Groups and substitution groups are represented in the type properties with the value XML_GROUP.

Identity constraints

The XML parser in HCL® OneTest[™] Data enforces declared identity constraints. The XML Schema Importer sets these properties based on the XML Schema. In general, the identity constraint definition serves in one of the roles listed below:

Identity Constraint

Unique

Enforces that a value (or combination of values) is unique within a given scope. For example, all product numbers must be unique within a catalogue.

Key

Enforces uniqueness and requires that all values be present. For example, every product must have a number and it must be unique within the catalogue.

Key References

Enforces that a value (or combination of values) corresponds to a value represented by a key or uniqueness constraint. For example, for every product number that is displayed as an item in a purchase order there must be a corresponding product number in the product description section.

Namespaces

The XML Schema Importer supports namespace and prefix properties for all elements and attributes. The importer assigns the values of these properties based on the input grammar. For each namespace in the input grammar, the importer allows you to specify the namespace prefix to be used for output documents.

During the import process, a **Location** value is specified in the schema without a fully qualified path. In this case, an execution process would, by default, look for the XML Schema at this location. However, if you need to change this path, you can do so.

For example, if you refer to the proper location of the schema in the XML document, then you can manually remove the path location from the type properties. When the execution process does not find a **Location** value specified in the schema, the process then looks to the "XSDL Hints" on page 840 specified in the XML document. When XSDL hints are not present, validation fails.

The value specified in the schema takes precedence over the XML document.

Element type declarations

The XML DTD and XML Schema importers can generate a simple schema when encountering character content within mixed data. During the import process, when character data (CDATA/PCDATA) is encountered, the importer incorporates it into existing text items within the schema.

Element and attribute wildcards

DTDs and XML Schemas allow the specification of wildcard elements within a grammar. The HCL® OneTest[™] Data XML Schema and DTD importers recognize element wildcards, build the appropriate types, and set the appropriate properties for those types to represent element wildcards in the schema.

During the import process, when a wildcard element resolves to an element that is not defined in the imported grammar, it is represented by a text item.

The value of these text items is the text string from the input buffer that runs from the start of the open tag to the end of the close tag for that element.

XML Schemas allow the specification of an attribute wildcard that matches any number of undeclared attributes within the element tag. The XML Schema Importer recognizes the attribute wildcard and creates a sequence of name and value text item pairs within the attribute list of the enclosing element. The XML validation library fills this sequence with the names and values of attributes that do not match any declared attributes in the attribute list.

Item restrictions

Item restrictions are an optional feature you can use to specify valid or invalid data objects for an item type. Item restrictions are grouped into three categories: **Value**, **Character**, and **Range**.

Restrictions of an item type are the valid or invalid values for that item. "Include" restrictions are all of the valid values for an item. "Exclude" restrictions specify all of the invalid values. For example, a unit of measure field in the data must be one of a set of values: CN, BX, PK, BR. These values should be defined as "include" restrictions of the item **UnitOfMeasure**.

Defining restrictions for an item restricts the valid data for that item. Partial lists of the valid values are not possible. For example, it is not possible to define the values for a certain item to be {A, B, C, "some other possible values"}.

While you can define restrictions for any item, most items will not have restrictions. For example, you would not want to restrict the valid values of a name field because you would probably want to accept any name as valid data for that field. However, you could assign restrictions to it if needed.

Restrictions settings

Using the **Restrictions** property, you can create a "restriction list" to limit an item to a particular value or set of values. Depending on the **Item Subclass**, you can set value, character, or range restrictions.

Range restrictions

Include range restrictions define the minimum and maximum values valid values of a range. *Exclude range restrictions* define the minimum and maximum values of the range that are to be excluded or considered invalid.



Note: Unbound restrictions are not supported.

Value not in range

About this task

The minimum value and the maximum values can be specified as not included in the range. For example, when a number in an **Include Minimum** field displayed the **Value NOT In Range** icon, it indicates that the number is not included as the minimum value. The range will therefore extend from any value that is greater than that number to the maximum value specified. Similarly, if the **Include Maximum** value is designated as *"not in range"*, the valid range would extend up to any value this is less than the maximum value.

To specify a value as "not in range":

- 1. Select the field (cell) that contains the value to be designated as "not in range".
- 2. Right click on the value and choose the **Value NOT In Range** menu item.

Inserting symbols

About this task

Symbols are used to indicate non-printable characters. You can insert a symbol by typing it or by using the **Symbols** dialog.

For example, to define a carriage return/line feed as an item restriction, from the item restriction view area, right-click and select **Insert Symbols** from the context menu. From the list of symbols, double-click CR and double-click LF and select **OK**. The carriage return/line feed symbols are displayed in angle brackets in the item restriction view area:

Ignoring restrictions

There might be instances when you do not require the data for an item to match any of its restrictions. Suppose you defined restrictions for your data, but you want to run a test on some test data, and you do not want to use the restrictions for this time only. You can ignore the restrictions for a given execution of a map.

In another example, you have a list of valid part numbers that can appear in any data circulated within your company. Suppose you receive data from some other company in the same format as your internal data. The other company may be using different part numbers, so you do not want to make their data conform to the restrictions. When you map the other company's data, you could ignore the restrictions.

Components

A component represents a data object that is part of another data object.

Components are required for group types

Categories and groups can have components. Components of group and category types display in the group and category views. Item types do not have components.

Group types represent actual data objects, so groups must have components. The one exception is a partitioned group which is explained in "Partitioning" on page 854.

By contrast, a category is used for organizing types and for type property inheritance reasons. Categories do not define actual data objects in detail. A category does not need components.

Each group must have at least one component, unless it is partitioned.

Components must be in the same schema

A component must be a type in the same schema as the type that contains the component.

You cannot define the components of a type by opening up a different schema and dragging components from that tree. You can, however, copy types from one schema to another.

Importance of component order

In the group view, components are listed from top to bottom in the order they appear in the data stream. The component in the first cell appears first in the data stream. The component in the second cell appears next, and so forth.

Component range

A component range can be specified for any component. A component range defines the number of consecutive occurrences of that component. The range (s) represents some or any number greater than one.

When a component is selected, the component name is displayed in the rule bar. Click in the rule bar after the component name to type the component range.

The range is displayed in parentheses immediately after the component name. The range is two numbers separated by a colon. The first number indicates the minimum number of consecutive occurrences of that component. The second number indicates the maximum number of consecutive occurrences of that component. The syntax of the component name and range is:

Component (MIN:MAX)

To enter a range after a component name, type in the rule bar or use the Set Range command.

The maximum component range is 2147483647.

Whenever a component has a range, each occurrence of that component may be referred to as a "member" of a series. The words "occurrence" and "member" are used interchangeably in the documentation.

Indefinite number

When there is no maximum number of occurrences of a component (the maximum is indefinite) use the letter **s** to stand for *"Some - you do not know how many"*. Therefore, a file that contains at least one record and has no maximum number of records has this component:

Record(1:s)

If the range minimum is zero, omit the o and only enter s. If a file has a minimum of zero records and no maximum number of records, it would have this as its component:

Record(s)

Remember that when you see (s), the minimum of zero is implied. Therefore,

Record(0:s) is the same as Record(s)

If you enter any number alone in the parentheses, the range changes to a minimum of 0 and a maximum of that number. For example, if you enter (5) for a range and save and close the group view, the next time you open it, you see the range displays:

(0:5)

Single occurrence

If there is a minimum and a maximum of one consecutive occurrence of a component, its range is (1:1). This is the default. If there is no range after a component name, the range (1:1) is implied. When you drag a type to make it a component, it is automatically created with the default component range of (1:1).

Defining components

Most groups need at least one component. Categories do not have components, however, you can define components for a category for inheritance purposes.

To determine the components of a group, ask the question: This group type consists of what?

For example, "The file consists of what?" The answer might be "records". So, **Record(s)** is a component of that group or category type.

Suppose you have a data file containing order records for an office supply store. You need to define the components of the type **File**.

Guidelines for defining components

The guidelines below are numbered to allow references to each other. The numbering does not suggest a priority or a sequence to be followed in observing the guidelines.

1. Categories cannot have components.

A category is only used for organizing your schema and for setting common properties.

2. A partitioned group cannot have components.

A partitioned group always represents a choice among the subtypes of that group. You never map a partitioned group without its subtree, so it does not need components.



Note: A *subtree* is a branch of a schema that includes a type and all of the subtypes that stem underneath it.

3. If a group is not partitioned, it must have at least one component.

Nonpartitioned groups are sequences of data objects rather than choices. A sequence must contain at least one component.

- 4. A type and one of its subtypes cannot be in the same component list.
- 5. If a type has components, a subtype can inherit any of those components or any type in the subtree of one of those components.
- 6. If a type has no components, a subtype can inherit any type that could be in that type's component list.
- 7. A type that has an initiator and a terminator can have itself or one of its ancestors as a component.
- 8. A type cannot have one of its subtypes as a component.

Complete type name

The complete name of a group is displayed in the title bar of its window. A type's complete name is similar to a path name, beginning at the type and including all types in the path up to the root. Spaces appear between types in a complete type name.

You can have duplicate type names as long as they are not on the same level. Each type has a unique complete name, so there is no doubt as to which particular type is being referenced.

Relative type names

A component name is similar to a relative path name. Component names exclude types that the defined type and component type have in common in their complete names.

The relative type name excludes the names that appear in the complete names of both the type and the component type. For example, because **ROOT** is included in the complete type name of both **Row ROOT** and **Product Column**. **ROOT**, it is excluded from the relative type name **Product Column**.

If more than one type in a schema has the same relative type name as another in a group, then the full path of the type is exported instead of the relative type name. No two types that have different full type names but identical relative type names can be added to a component list.

Moving types with the same relative type name

In a schema, there could be two types with the same name that exist in different places within the tree. The relative type names could both evaluate to be the same, with respect to the component.

For example, the relative type **Group Category ROOT** might have a type named "Item" in both **ROOT** and **Category ROOT**. Both evaluate to "**Item**" with respect to the **Group** component. In this scenario, you can drag only one component named **Item** into the component list. An attempt to add a second component with the same name will be blocked.

Ambiguous type names

A component name can refer to more than one type. In this situation, you must change type names so that the component name is no longer ambiguous. The schema designer does not allow components with the same relative type name to be added to component lists.

If you delete a type that is used as a component of another type, and then perform an "Undo", thus adding the type back, and the component name is ambiguous; the component name remains unresolved in the component list. In this scenario, the "Undo" operation does not result in a complete reversal of the action.

Specifying minimum and maximum consecutive occurrences in the component list

The following table contains examples of how to specify in the component list the minimum and maximum consecutive occurrences for specific data objects:

Data Object	Min	Max	How to Specify
DateField	1	5	DateField (1:5)
DetailRecord	1	100	DetailRecord (1:100)
AddressField	2	3	AddressField (2:3)

Fixed and variable ranges

Sometimes the range of a component is described as fixed or variable. As an example, a fixed range has the same minimum and maximum, (5:5). A variable range has a different minimum and maximum, (1:10) or (s) for example.

Specifying a component range

About this task

You can specify a component range by using Set Range to enter the minimum and maximum number of occurrences.

You can select multiple components and use **Set Range** to apply the same range to each component. A range of (1:s) means that there will always be at least 1 occurrence, but could occur an infinite number of times. A range of (0:s) means that an occurrence is optional, but could occur an infinite number of times.

Variable component names

A component can refer to more than one type. To refer to all possible types whose names could appear at a certain place in the component name, use the word ANY.

The word ANY is like a wild card. It represents any type whose name could appear in that place.

The use of ANY is restricted to **Categories** and partitioned groups. For more information about using ANY in a partitioned group, see "Partitioning" on page 854. For a list of reserved words and symbols, see the Design Studio Introduction documentation.

Required and optional data

Sometimes, a certain data object is optional; it does not have to be present in the data. For example, in purchase order data, there might be a billing address and a shipping address. If the company wants the items shipped to the billing address, the shipping address would not appear in the data. The shipping address would be optional; it might not appear in the data.

Another example is a middle name field. Some people do not have a middle name, so the middle name field might be optional.

The schema designer needs to know what data is optional. This is evident from the component range. The range minimum tells how many occurrences of that object must be present in the data. These are the required occurrences. Optional occurrences are the ones that are not required.

For example, for the following component, the range minimum is zero. No occurrences must be present. It is optional data:

DateField (0:1)

Suppose the component looks like this:

DateField (1:5)

The range is between one and five occurrences. This means that one occurrence of **DateField** is required and the remaining four occurrences are optional.

The following table lists examples of components and explanations of their status.

Component		Status	
			_

Range minimum is 1

Reason

LineItem (1:s)

1 occurrence required

Component	Status	Reason
Note Field (5:5)	5 occurrences required	Range minimum is 5
RecordID	1 occurrence required	Range minimum is 1
ShipTo (0:1)	0 occurrences required (Optional)	Range minimum is 0
OrderRecord (s)	0 occurrences required (Optional)	Range minimum is 0

Significance of required data

If you define an occurrence of a component as required, you are saying that, for the data containing the component to be *valid*, this component must exist. If it does not exist, the data is *invalid*.

For example, if you define **Record** as having the component **Field (3:3)**, you are saying that there must be three **Fields** in the **Record**. If there are not three **Fields**, then either it is a **Record** in error or it is not a **Record**.

There are other factors, besides the existence of all required components that make data valid. The existence of required components is necessary, but not sufficient, for data to be valid.

Defining component rules

A component rule is an expression about one or more components. It indicates what must be true for that component to be valid. For given data, it evaluates to either "true" or "false". A component rule is similar to a test. If the data does not pass the test, it is invalid.

Component rules are used for validating data. Some important points about component rules are:

- Only components of a group can have component rules. Components of a category cannot have component rules.
- A component rule cannot be longer than 32K.
- If a component is optional and does not appear in the data, the component rule is evaluated after determining that the data is missing. In a component rule, you can specify relationships that depend on existence or nonexistence of data.

Sometimes components have relationships among each other. For example, an address field in purchase order data is preceded by a qualifier field which tells whether the address is a bill-to or a ship-to address. If the value of the qualifier field is BT, the address field following it is a bill-to address. If the value is ST, the following address is a ship-to address.

The qualifier and address fields are dependent on each other. They only make sense as a pair. If one of these fields is optional and is missing, the other field is not meaningful. If the qualifier is missing, you do not know whether the address is a bill-to or a ship-to. If the address is missing, the qualifier does not qualify anything!

You might want to define this kind of relationship and other relationships among data objects. To do this, use a component rule. For example, use a rule on the address field component to indicate that the qualifier must be present if the address is present.

Examples of component rules

A component rule can limit the acceptable values of a component as shown in the following example:

```
Quantity < 10000
Interest Rate > .13 & Interest Rate < .20
WHEN (PurposeCode != "PF", ShipValue = 200|ShipCode < 0)</pre>
```

The following example illustrates how a component rule can make the presence of one component mandatory, if another component is present:

```
WHEN (PRESENT (Address Field), PRESENT (Qualifier Field))
WHEN (PRESENT (PhoneNumber), PRESENT (AreaCode), ABSENT (AreaCode))
```

A component rule can compare a component to the result of an arithmetic operation as shown in the following example:

```
SUM (((QuantityOrdered:Item Record:Detail) = TotalQuantity:Summary Record:Detail
Account Balance = Credits - Debits
Extension = Quantity*Price
#Items Field = COUNT (Item Record IN Invoice)
```

Component rule syntax

A component rule is a complete expression that evaluates to either "true" or "false". It can contain functions (for example, PRESENT, COUNT, and SUM). It can also contain arithmetic operators (such as -+/*).

A component rule is a statement, so it does not start with an equal sign.

For more information about the syntax of expressions, see the Functions and Expressions documentation.

Entering object names in component rules

About this task

A component rule can refer to a component within a component. The syntax for a component is the component name, followed by a colon (:), followed by the object of which the component is a part. Whenever you see the colon (:) in an expression, it can be interpreted as "component of" or simply "of".

For example, the following expression means "The item number of the order record of the order":

Item#:OrderRecord:Order

All of the objects that can be used in component rules are shown in the group view. You can enter an object name into a component rule by pressing Alt and dragging the object into the edit area. The complete object name is automatically entered.

A component rule can refer to:

- The component it applies to and any nested components.
- Any component above the given component in the component list, and its nested components.

You can enter an object name in a component rule by typing it; however, the recommended method is to press Alt and drag the component into the edit area.

Shorthand notation

In a component rule, the dollar sign (\$) represents the component itself. When you enter an object name in a rule by pressing *Alt* and dragging the object, the dollar sign is automatically entered in the rule to represent the given component.

Component rules are context-sensitive

Component rules apply to components, not types. It applies to data in a certain context when the data is a component of a given group.

Suppose you have some order data that contains two kinds of records: a regular order record and a bulk order record. In the bulk order record, the quantity ordered must be greater than 1000. In the regular order record, the quantity can be any number. You could put a rule on the quantity ordered component of a bulk order, but not on the quantity ordered of a regular order.

Special characters in component rules

About this task

To enter the actual value of a special character in a component rule, you must enter the Hex value for one of the characters. For example, to enter the text value <wsp>, enter the Hex value for the less than sign <<3C>>, and then the rest:

<<3C>>WSP>

See the Design Studio Introduction documentation for a list of non-printable Hex and decimal values.

Comments in component rules

About this task

You can add comments to component rules. Comments do not affect how component rules are evaluated.

A comment begins with the characters /* and ends with the characters */. A comment can appear anywhere in a rule as long as it does not separate object names.

For example, the following component rule has a comment:

SIZE (Phone# Field:\$) >=7
/* Phone numbers must include area code */

Component attributes

Attributes can be assigned to a component in a component list.

Identifier attribute

The identifier attribute can be used on a component of a group. The identifier indicates the components that can be used to identify the type to which a data object belongs. All the components, from the first, up to and including the component with the identifier attribute, are used for type identification.

When this data is validated, it knows that, when it reaches the identifier, it has found a specific group. That group, therefore, is known to exist, even if part of the group following the identifier is missing. The map designer documentation discusses how data validation occurs.

The identifier attribute is also useful when identifying an object of a partitioned group. For information about using an identifier with partitioned data, see "Partitioning" on page 854.

In a component list, there can be only one identifier attribute.

Restart attribute

About this task

To continue processing your input data when a data object of a component is invalid, assign the restart attribute to that component.

Do not put the restart attribute on a required component. There must be a sufficient number of valid instances to cover all required components. If you have a required component that is not valid, the restart attribute does not validate the data.

For additional information about using the Restart attribute, see the map designer documentation.

Sized attribute

The sized attribute is used on a component in which the value specifies the size (in bytes) of the component immediately following it. The sized attribute can be used on more than one component of a group.

For example, you might have a variable length component with a number immediately preceding it that indicates the length of the component: 10Washington. The size of the component would be 10.

Some important points about using the sized attribute are:

- The component with the sized attribute must be defined as an unsigned integer.
- If a binary byte stream item does not have a fixed size, the component preceding it must specify its size and the sized attribute must be used on that component.

The size of a component is the number of bytes from the beginning of that component, up to and including the end of the component. If a component has a series range (such as [1:3]), the size includes all of the members in the series of that component. If a delimiter separates each member of that series, the delimiters must be included in the size. Also, if release characters appear in the component, they must be included in the size.

The size does not include delimiters that separate one component type from the next.

Include self in size

If the value of the component with the sized attribute includes the size of the component, use the **Include Self in Size** option. For example, suppose the component with the sized attribute has a length of seven bytes. The value of the component with the sized attribute would be seven. So, its data would be one byte long, to hold the character seven. If its value includes the length of itself, its value would be 7 + 1 = 8.

For example, a sized component is 7 bytes.

+ <u>1 byte</u> (the length of the character 7)

If Include Self in Size is selected: 8 bytes

Partitioning

By partitioning, you can define your data to distinguish the difference between data objects based on values in the data or differences in the syntax.

Partitioning is a method of subdividing objects into mutually exclusive subtypes. The partitioned type maintains the same class.

Determining when to partition

There are some cases in which you will *need* to partition your data and others in which you will *want* to partition your data. You are *required* to partition for unordered data when a data object at a certain place in the data stream can be any number of types and each type has different definitions. *Choose* to partition for convenience, either to simplify rules or to put additional logic into your data's definition.

Required partitioning

Partitioning is required when components are randomly or partially ordered. The following example represents unordered data:

BGI - 13100, REM, 931104, 19970424...

AXR - 10930, INV, 003X114, 19970422...

PVY - 19496, ORD, PO-104-1499, 19970425...

BGI - 13100, ORD, PO-182-2587, 19970425...

```
AXR - 10930, INV, 003X-114, 19970422...
```

PVY - 19496, REM, 931104, 19970424...

The file would contain three different types of transactions: **Invoice**, **Order**, and **Remittance**. Each transaction has a different definition based on the type of information it represents.

Partitioning for convenience

You might decide to use partitioning in your schema to build additional logic into the definition of your data. You may also use partitioning to simplify the rules.

The following is an example of partitioning to simplify rules. The example compares the differences between rules needed *with* and *without* partitioning. In the rule without partitioning, you would specify a condition for each state abbreviation in each region. This could make your rules long, difficult to read, and difficult to maintain. The rule with partitioning is more concise, self-documenting, and easier to maintain.

Rule without partitioning:

```
=IF(ShipToCode Field:.:Input="NY"|
ShipToCode Field:.:Input="NJ"|
ShipToCode Field:.:Input="PA",
F_MapEast (Record:Input), NONE)
```

Rule with partitioning:

```
=F_MapEast (EXTRACT (Record:Input,
PARTITION (ShipToCode Field:.:Input, East)))
```

Benefits of partitioning

Using the previous example on page 855, explore the benefits of partitioning.

- The rule with partitioning is shorter than the rule without partitioning. The knowledge of which states belong to each region is maintained in the type tree rather than the rule.
- It is easy to read this rule and understand the mapping function being performed. For example, if the state belongs to the list of states in the eastern region, execute the **MapEast** functional map.
- The partitioning method is easier to maintain. If a value for **State** is added or moves from one region to another, it can be easily changed in the schema and automatically reflected in any rules that reference the partitioned object.
- Partitioning using a restriction list used with the **Ignore Case** setting eliminates the need for PROPER, LOWERCASE, or UPPERCASE functions to compare each state with a literal.

Consideration for HCL® OneTest[™] Data

• Do not attempt to generate sample test data for a partitioned group. Sample test data should instead be generated for the specific subtype.

Partitioning types

When data objects of different types appear in the same place in the data, the types must be distinguishable. This means that the data needs to be distinguishable by their definitions in the schema.

When the data object at any given point in the data may belong to any of a number of different types, there must be some way to tell the difference between them. To do this, you create a type and define a mutually exclusive subtype for each data object that may appear in the same place in the data. Once the subtypes are created, the subtypes also need to be distinguishable. Subtypes are distinguishable based on a value in the data or in the syntax of the different types.

Partitioning items

Use one of the following three methods to partition items in schemas:

- Initiators
- Restrictions
- Format

Partitioning an item type using initiators

To partition by initiator, each subtype must have an initiator and the value of the initiator must be unique for each subtype.

Partitioning by initiator is the most efficient method of partitioning.

Partitioning an item type using restrictions

If an item has restrictions, you can partition that type, create mutually exclusive subtypes, and divide the restrictions between subtypes. A restriction cannot appear in more than one subtype of that item.

Example of using restrictions

You have new data that needs to be entered into the Type Designer. Each new record contains the name of the employee and his or her department.

The Employee List schema illustrates components of Record.

The following is the new data containing the name of the employee and the department.

Steven Barlow,Doc

Heather Proust,Qa Mary Whiting,Doc Genie Elks,Sup Francine Maxwell,Dev Mark Brown,Sup Daryl Schwartz,Acc Harry O'Brian,Sal Ellen Randolph,Dev Paula Keller,Qa

Define the values of **Department** as a character text item.

Define the example data as valid restrictions (enter in the Include column) of Department:

If the departments are located in different offices, you can divide the data into separate files; one file per office. To do this, map the data from the main office to one file, the data from the development office to one file, and the data from the support office to another file. Then create subtypes of **Department: MainOffice, DevelopmentOffice**, and **SupportOffice** and partition **Department**. When you partition **Department** and create subtypes, you are saying that a given department data object belongs to only one of the subtypes based on its value.

The subtypes of **Department** inherit the restrictions of **Department**. Now allocate restrictions among subtypes. To do this, delete the restrictions from the subtype that do not apply to that particular office. For example, the **MainOffice** item has only the departments in that office, **DevelopmentOffice** item has only the departments in that office, and the **SupportOffice** item has only the departments in that office.

Partitioning an item type by format

Subtypes that differ by their format are distinguishable from each other.

Partitioning groups

Use one of the following three methods to partition groups in schemas:

- Initiators
- Identifiers
- Component rules

Partitioning a group type using initiators

To partition by initiator, each subtype must have an initiator and the value of the initiator must be unique for each subtype.

The method of partitioning by initiators for group types is similar to item types.

Partitioning a group type using identifiers

About this task

In a component list, only one component can have the identifier attribute.

The identifier attribute distinguishes the components that can be used to identify the type to which a data object belongs. Typically, use this technique to distinguish group partitions when components following the identifier are different for each partition, or, if you have a multilevel partitioned subtree. In the latter case, using an identifier accelerates data validation.

A partition is valid when each component up to and including the identifier is validated. If the set of components is valid, the partition exists.

If the identifier set of components is not valid, the partition is determined not to exist. Either validation occurs for the next partition at the same level (if there is one) or it is determined that the partitioned group does not exist.

If the partition exists, what occurs next depends on the position of the partition type in the subtree.

- If the partition is partitioned (that is, it has subtypes), the rest of the components are skipped and the process begins to validate subtypes until a subtype is valid, exists and is in error, or does not exist.
- If the partition has no subtypes, the remaining components are validated. If all remaining components are valid, the partition not only exists, but also is valid. If one or more components are found to be in error, the partition exists, but its type is in error. If the partition exists, but its type is in error, the error is propagated back up the partitioned subtree until the group being validated is reached. When a partition is found to exist, the system will not continue to search for partitions.

To specify a component as the identifier:

1. From the schema editor, double-click a component.

Result

The Component view opens.

2. In the Component column, right-click on the component and choose Identifier from the context menu.

Results

The identifier symbol appears in the component column next to the component name.

Partitioning a group type using component rules

Component rules are used to partition data when a value or range of values can be used to distinguish one partition from another.

Type inheritance

Properties, components, and restrictions of a type can be inherited by the types created as subtypes under it. Some properties of a type can also be propagated to already existing subtypes.

When you create a type, it becomes a subtype of whatever type is selected at the time. Everything that defines a type gets passed down: properties (with the exception of the Partitioned property), components, and restrictions. After a type is created, you can then modify any aspect of its definition.

When a group is created within a category, the item properties do not apply, so they are not inherited. When an item is created under a category, the group properties are not inherited.

Inheritance of item properties and restrictions

Properties and restrictions of items are inherited when a new item is created.

For example, an item named **Department** is defined as a character text item that has a content size minimum of 2 and maximum of 3. Department has a list of "include" restrictions that consists of valid departments: ACC (Accounting), SLS (Sales), and MKT (Marketing).

The type **MainOffice** is created as a subtype of **Department**. **MainOffice** inherits the properties and restrictions of **Department**.

You can delete any restrictions that are not applicable to MainOffice.

Inheritance of category properties and components

Categories can be used for organizing types and for inheritance reasons. Generally, you would use categories when you want to put items, groups, and possibly other categories under it as subtypes.

Organizing types under a category

If you have two tables defined in one schema, you could divide the types of the two tables into different categories. A benefit of using a category type is that you can have any class of subtype: groups, items, and other categories.

Using categories for inheritance

The properties of a category include group and item properties. Assign properties to a category that you want types beneath the category to inherit.

Any group created under a category inherits the property of the category. Any item created under a category inherits the category's item properties. A category created under a category inherits both the group and item properties. Each type created under a category inherits the other properties of the category, such as initiator and terminator.

As an example, if most groups in your **LabInfo** data are infix delimited with ~ and most items in your **LabInfo** data are unsigned integers, you can define these as the properties of the category **LabInfo**. Any types you create under **LabInfo** inherit its properties.

You can change the properties of the root type, which is a category. Categories can have components, so you can also use them for inheriting components.

When not to use categories

It is best not to use a category type when the subtypes will specifically be item types or specifically be group types.

For example, you have a type named **Field** for which the only subtypes will be items. If you make **Field** a category type, each time you create a subtype, the new type will also be a category type by default. You will have to change the **Class** property from **Category** to **Item** for each subtype that you create. Instead, make **Field** an item type so that the **Class** property for any subtypes you create will automatically be defined as item types.

Propagation of type properties

Creation time is not the only time type properties can be passed from a type to its subtypes. You can use propagation to pass along certain type properties.

Propagation passes the setting of a particular type property from the given type to all of the types in the subtree as applicable and defined by their context. When you select a type property for propagation that does not apply to a given subtype, it is not propagated.

Propagation of type properties common to all types

You can propagate some type properties that are common to all types such as **Item Subclass**, **Description** and **Type Syntax**, to each of its subtypes, without the process checking additional criteria to determine if the type property can be propagated.

The type properties that fall into this category are the properties in the root of the tree, or are children properties that apply to all types to which their parent property is set, and are global in that these properties apply to all items.

The propagation process checks that the settings for some type properties such as the **Item Subclass** property, the **Interpret as** property, and if applicable, the **Presentation** property in a type, match the settings for these same properties in its subtypes, and if they match, the selected property is propagated. But, the propagation process does not check the settings of other properties to determine if the selected property exists in the item, because the selected property in this case, applies to all item types.

Examples of propagating a type property that has no children properties

A given category type that is in the root of the tree has the following type property setting: **Description > An example**. The **Description** type property has no children properties. When you select the **Description** type property setting of **An example** to be propagated, the process propagates the **Description** setting of **An example** to all types in the tree. The **Description** property is a type property that is common to all types.

A given category type has the following type property settings: **Item Subclass > Text** and for its child property, **Interpret as > Character**. When you select the child **Interpret as** type property to be propagated, the process propagates the **Interpret as** setting of **Character** to each subtype of that category that also has the same **Text** type property setting. The **Interpret as** property is a type property that is common to all types except syntax types.

Examples of propagating a type property that has children properties

A given category type has the following type property settings: **Item Subclass > Number**, and for its children properties, **Interpret as > Binary**, and **Presentation > Integer**. When you select the parent **Item Subclass** type property to be propagated, the process propagates the **Item Subclass** setting of **Number**, as well as the settings for its children properties, **Interpret as** setting of **Binary**, and the **Presentation** setting of **Integer**, to each subtype of that category. The **Item Subclass** property is a type property that is common to all types.

A given category type has the following type property settings: **Item Subclass > Text** and for its child property, **Interpret as > Character**. When you select the parent **Item Subclass** type property to be propagated, the process propagates the **Item Subclass** setting of **Text**, as well as the setting for its child property, **Interpret as** setting of **Character**, to each subtype of that category. The **Item Subclass** property is a type property that is common to all types.

Propagation of type properties for specific types

You can propagate some other type properties such as **Separators** and **Restrictions**, to each of its subtypes for specific types, with the process checking additional criteria to determine if the type property can be propagated.

The type properties that fall into this category are children properties that do not apply to all types to which their parent property is set, and are specific to a type, in that these properties do not apply to all item types.

The propagation process checks that the settings for some type properties such as the **Item Subclass** property, the **Interpret as** property, and if applicable, the **Presentation** property in a type, match the settings for these same properties in its subtypes, and if they match, the selected property is propagated. But, depending on the property being propagated and the context, the process also checks other property settings. If you are propagating a child property, depending on the context, the process also checks the settings of the parent property, because the selected property might only apply to specific item types.

Examples of propagating a type property that applies to a specific type

A given category type has the following type property settings: **Item Subclass > Number**, and for its children properties, **Interpret as > Character**, and **Presentation > Decimal**. When you propagate the **Separators** child property, the process affects only types in the schema that also have those same **Number**, **Character**, **Decimal** type property

settings. The **Separators** property is a type property that applies to the specific **Presentation** types, **Decimal** and **Integer**. For those types that have the **Presentation** type property setting of **Zoned**, the **Separators** property does not apply; it is not an available type property.

A given category type has the following type property settings: **Restrictions > Value** and for its child property, **Ignore case > No**. The **Ignore case** type property has no children properties. When you select the child **Ignore case** type property setting of **No** to be propagated, the process propagates the **Ignore case** setting of **No** to all types in the category whose parent **Restrictions** property setting is **Value**. The **Ignore case** property is a type property that applies to a specific **Restrictions** type, **Value**. For those types that have the **Restrictions** type property setting of **Range**, the **Ignore case** property does not apply; it is not an available type property.

Schema analyzer

Use the schema analyzer to analyze your type definitions.

The schema analyzer analyzes type definitions and ensures internal consistency. For example, if you defined a group as fixed, but accidentally defined one of its items with no **Padded To** length, errors occur during analysis.

The analyzer checks your data definitions for logical consistency. It does not compare your definitions to your actual data. The resulting analyzer messages indicate whether your schema definitions are acceptable; not whether they match your data.

Note: The HCL® OneTest™ Data does not support schema analysis of JSON or XSD format schema.

Mapping effects

The analyzer helps you define your data by locating objects in your input data and creating the objects in your output data. The analysis indicates whether there is something in your definition that may prevent a correct mapping of your data.

If you do not analyze a tree before you map the data or you analyze a tree and do not resolve the errors, you will be warned that you may receive unpredictable results when you map.

Internal consistency

The analyzer checks the logic of your data definitions. For example, suppose you defined a group **PO** as fixed and consists of **Line(s)**. For the **PO** to be fixed, it cannot have an indefinite number of **Lines**. An analysis error would occur, indicating that you defined **PO** as fixed but it has a variable number of components.

Logical analysis

Logical analysis addresses the integrity of the relationships that you define. Logical analysis detects, for example, undefined components, components that are not distinguishable from one another, item restrictions that do not match the properties of that item, and circular type definitions. The analyzer also checks delimiter relationships to each other and to components, undefined inherited relationships, and logic errors contained in component rules.

Structural analysis

Structural analysis addresses the integrity of the underlying database. Generally, you should not encounter structural analysis errors. Structural analysis might be able to detect and possibly correct defects caused by system environment failures.

Error and warning messages

Analysis results might contain error and warning messages.

Warnings are relatively insignificant. They indicate an inconsistency that occurred when you changed something in the tree that was resolved. For example, if you change a group to an item, the analyzer removes the components of that type because items do not have components. To remind you of this change, the analyzer issues a warning.

Errors are important. An error is a problem in your type definitions that you should correct. An error may result in unpredictable results in your mapping.

Occasionally there are errors that prevent the analysis of the rest of your definitions (for example, when a component type cannot be found in the tree). Analysis halted before completion is displayed. This error might be due to one of the following:

- Undefined COMPONENT found: ending analysis.
- Circular reference found in COMPONENT list: ending analysis.

When this occurs, correct the errors and analyze the tree again.

Distinguishable objects

Differences can be identified for objects in a data stream. This information is helpful when a schema analysis produced an error message concerning objects that are not distinguishable.

Objects in a data stream

A data stream is a byte-by-byte flow of data. Objects in a data stream include both data objects and syntax objects. Syntax objects indicate where a data object begins or ends. They include separators, initiators, terminators, delimiters, release characters, and pad characters. Sometimes, data values are used to identify where another data object begins or ends.

It might be necessary to distinguish between data objects in a component series, data objects of different types, or even syntax objects.

Schema analyzer and distinguishable objects

The schema analyzer indicates whether your data definitions are sufficient to distinguish the objects in your data stream. The following discussion explains how you can define your data so that the objects that need to be

distinguishable are distinguishable. Chances are, if you analyzed your tree and received a message that involves distinguishable objects, you need to define the types differently or more specifically.

Bound types

A type is bound if its definition makes it clear where an instance of that type ends. If a type is bound, different objects of that type can be distinguished in a data stream. A bound type is easier to distinguish between an object of that type and an object of another type. The following tables describe how types may be bound.

An object of this type:

Is bound if any of the following is true:

ltem

It is padded to a fixed size or its minimum and maximum content size are equal.

It has a terminator.

It has an include restriction list.

Partitioned item

Each non-partitioned item in the subtree is bound.

Sequence Group

It has an explicit fixed format.

It has a terminator.

Its last component is bound.

It is postfix delimited and its last component has a fixed range. For example, **Comment Field (3:3)** has a fixed range of **(3:3)**.

Partitioned Group

Each non-partitioned group in its subtree is bound.

Choice Group

It has a terminator.

The type of each selection component is bound.

Unordered Group

It has a terminator.

Bound components

A component is bound if it is possible to tell if a data object belongs to that component without comparing it to a component that follows it.

Component of a fixed group

Condition

Example

A range maximum is specified (it is not "s"), and its type is either a fixed group or an item whose length is fixed.

The component **InventorySection (0:3)** is bound because it is assumed there will be spaces in the data stream for 3 **InventorySections**.

Component of an explicit delimited group

Condition

Example

A range maximum is specified (it is not "s") if a component of the same group follows.

In the component list, **Security Sequence (0:10) Trailer** is bound in an explicit delimited group. It is assumed there will be a delimiter for all 10 **Security Sequences** in the data stream because **Trailer** is required.

The component is the last one and the explicit group has a terminator.

In the component list, **Security Sequence (s)** is bound in an explicit delimited group with a terminator. The system assumes the terminator will appear to indicate that there are no more **Security Sequences**.

Component of an implicit group

Condition

Example

Its range is fixed and its type is bound.

The component **Inventory Record (3:3)** is bound, if the type **Inventory Record** is bound according to any of the conditions listed under "Bound Types" on page 864.

It has a component rule that binds it.

The component PO Record (s) is bound, if it has the following component rule which binds it:

PO# Field:PO Record = PO# Field:PO Record[LAST]

The schema analysis checks only that the component has a rule that refers to the component itself. The analysis does not check that the rule binds the component. You must ensure that the rule is one that binds the component.

It is sized (using the Sized attribute) by the component that precedes it.

The component **Name Field (0:2)** is bound, if the previous component in the group has the Sized attribute.

Component of a choice group

Condition

Example

A component is bound if the type of a component is bound.

The component Customer Record is bound if the type Customer Record is bound.

Component of an unordered group

Condition

Example

A component is bound if its range is fixed and its type is bound.

The component Address Field is bound if its range is fixed, for example (3:3), and the type Address Field is bound.

Group starting set

Data objects in a data stream need to be distinguishable when they could belong to two different groups. Specifically, the difference between the data that can come first in one group and the data that can come first in the other group. All of the possible types of data that may appear first in a group are referred to as the group's starting set.

The following describes the starting set of a group based on its group format:

Group Format

Starting Component Set

Explicit

Includes the type of its first component.

- Delimit-
- ed
- Fixed

• Se-

• Un-

Implicit

- · Includes the type of all components up to and including the first component that has a minimum range of at least one. quence
 - · Includes the type of each component.
- ordered

Choice Includes the type of each component.

Group unbound set

Based on the nature of a bound group, the end of a bound group is determined without analyzing the data that follows it. However, if a group is not bound, the data that belongs to that group must be distinguishable from data that belongs to another type that might follow it in the data stream.

The unbound set of a choice or unordered group consists of the type of each component. The unbound set of a partitioned group consists of the unbound set of each unbound partition.

Unbound set of a sequence group

The unbound set does not include a type that could come last, if that type is a required occurrence. For example, if the type **Comment Record** could appear last and the component is specified as **Comment Record (2:2)**, it is not in the unbound set, because the two occurrences of **Comment Record** are required. However, if **Comment Record** could appear last and the component is specified as **Comment Record (1:2)**, then **Comment Record** is in the unbound set, since its second occurrence is optional.

To determine the unbound set of a group, start with the last component of the group and proceed backward up the component list. If a component is unbound or has a minimum range of zero, continue up the list. Stop at the first component that is bound or that is unbound but has a minimum range greater than zero. Essentially, a group's unbound set is everything that is not clearly defined at the end of the group.

Initiator-distinguishable types

Initiator-distinguishable types are used during validation to determine existence of a type object based on the existence of its initiator.

Determining if a component is initiator-distinguishable from its following set

A component is initiator-distinguishable from its following set if:

- The component is not a member of the identifier set and
- The type of the component has an initiator and
- The following set is empty or
- The type of the component is initiator-distinguishable from each type in its following set.

Schemas are analyzed to determine if components are initiator-distinguishable. Each implicit sequence group, choice group, and unordered group is analyzed to determine if their components are initiator-distinguishable. A component is marked as initiator-distinguishable when that component is initiator-distinguishable from its following set. The basis for this determination is found in "Determining If Two Types are Initiator-Distinguishable" on page 868.

Determining if a partition is initiator-distinguishable from its following set

In a partitioned type, a partition is initiator-distinguishable from its following set if:

- The type of a partition has an initiator and
- The following set is empty or
- The type of the partition is initiator-distinguishable from each partition in its following set and the following set of a partition is the type of each partition that may follow.

Schemas are analyzed to determine if partitions are initiator-distinguishable. Each partitioned type is analyzed to determine if its partitions are initiator-distinguishable.

Determining if two types are initiator-distinguishable

The following table lists ways two types may be initiator-distinguishable. This is helpful if data validation errors indicate a type does not exist.

Type1	Type2	How to define them as initiator-distinguishable
item	item	If Type1 and Type2 have an initiator, and the initiators are differ- ent.
item	sequence group	Either:
		 Type1 and Type2 both have an initiator and the initiators are different.
		or
		• Type1 has an initiator, Type2 does not, Type2 has no de- limiter, and Type1 is initiator distinguishable from type of each component in the starting component set of Type2.
item	choice group or un-	Either:
	ordered group	• The Type1 and Type2 both have an initiator and the initia- tors are different.
		or
		• Type1 has an initiator, Type2 does not, Type2 has no de- limiter, and Type1 is initiator distinguishable from type of each component of Type2.
item	partitioned item or parti- tioned group	Type1 has an initiator and is initiator distinguishable from each partition of Type2.
partitioned item	item or sequence group	Type1 has an initiator and each partition is initiator distinguish- able from Type2.

Type1	Type2	How to define them as initiator-distinguishable
partitioned item	partitioned item or parti- tioned group	Type1 has an initiator and each partition is initiator distinguish- able from each partition of Type2.
sequence group	item	Type1 has no identifier, Type1 and Type2 both have initiators, and the initiators are different.
sequence group	sequence group	Type1 has no identifier and
		 Type1 and Type2 both have initiators and the initiators are different
		or
		• Type1 has an initiator, Type2 does not have an initiator, Type2 has no delimiter, and Type1 is initiator distinguish- able from the starting component set of Type2.
sequence group	choice group or un-	Type1 has no identifier and
	ordered group	 Type1 and Type2 both have initiators and the initiators are different.
		or
		• Type1 has an initiator, Type2 does not have an initiator, Type2 has no delimiter, and Type1 is initiator distinguish- able from the type of each component of the Type2.
sequence group	partitioned item	Type1 has no identifier and Type1 must be initiator distinguish- able from each partition of Type2.
sequence group	partitioned group	Type1 has no identifier and the Type1 must be initiator distin- guishable from each partition of Type2.
partitioned group	partitioned item	Type1 has no identifier and each partition Type1 must be initiator distinguishable from Type2.
partitioned group	sequence group	Type1 has no identifier and each partition of the Type1 must be initiator distinguishable from Type2.
partitioned group	partitioned item	Type1 has no identifier and each partition of Type1 must be ini- tiator distinguishable from each partition of Type2.
partitioned group	partitioned group	Type1 has no identifier and each partition of Type1 must be ini- tiator distinguishable from each partition of Type2.

Type1	Type2	How to define them as initiator-distinguishable
choice group or un- ordered group	item	Type1 and Type2 both have an initiator and the initiators are dif- ferent.
choice group or un- ordered group	partitioned item	Type1 is initiator-distinguishable from each partition of Type2.
choice group or un- ordered group	choice group or un- ordered group	Either: • Type1 and Type2 both have an initiator and the initiators are different.
		or
		• Type1 has an initiator and Type2 does not, Type2 has no delimiter, and Type1 is initiator-distinguishable from the type of each component of Type2.
choice group or un-	sequence group	Either:
ordered group		• Type1 and Type2 both have an initiator and they are dif- ferent.
		or
		• Type1 has an initiator and Type2 has no initiator and no delimiter, and Type1 is initiator-distinguishable from the type of each component in the starting component set of Type2.
choice group or un- ordered group	partitioned group	Type1 is initiator distinguishable from each partition of the Type2.

Distinguishable objects of the same component

When a component has a series range, for example, (1:10) or (s), one occurrence of that component must be distinguishable from the next occurrence of that same component.

Different data objects of a component are distinguishable if any of the following is true:

- The component type is bound.
- The component type is a non-partitioned group with an unbound set that is content distinguishable from the component type as a whole.
- The component type is a partitioned group and the unbound set of each non-partitioned group in its subtree is content-distinguishable from the component type as a whole.

Content-distinguishable components

A component is distinguishable from its following set when the component is:

• Initiator-distinguishable from its following set.

or

· Content- distinguishable from its following set.

A component is content-distinguishable from its following set when:

The following set is empty.

or

• The type of the component is content-distinguishable from each component in its following set.

Content-distinguishable types

The following table lists the ways in which two types may be content-distinguishable. The table is helpful particularly if you analyzed your tree and received an error indicating that two types are not distinguishable. Look up the combination of types in the first two columns and read the list of ways to define them that would make them distinguishable.

For example, if you get an error indicating that **X** is not distinguishable from **Y**, where **X** is an item, and **Y** is a partitioned group, you would find the row in the table where **Type1** is an item and **Type2** is a partitioned group.

Remember that the order in which you compare two types matters. When you ask the question *"Is type A content-distinguishable from type B?"*, this is not the same question as *"Is type B content-distinguishable from type A?"*

If you are trying to determine whether two types are distinguishable and you follow the guidelines in the following tables, you may encounter a situation in which you are comparing a type to itself. A type is never distinguishable from itself.

Another thing to keep in mind is that the context in which a type is used matters. When you ask the question, "Is type A, as a component of type C, content-distinguishable from type B?" this is not the same question as, "Is type A, as a component of type D, content-distinguishable from type B?"

The following table shows how to define types as content-distinguishable.

Т	ype 1 Type 2	How to define them as content-distinguishable
item	item	The first component or partition is either:
		 An item and marked as initiator distinguishable and
		Both items are different partitions of the same partitioned subtree, or The second type has an initiator and those initiators are mutual- ly exclusive, or Both types have the same initiator and the value of the first item is distinguishable from the value of the second item, or The second type has no initiator and the initiator of the first type is distinguishable from the value of the second type.
		An item and not marked as initiator distinguishable and
		Both items are different partitions of the same partitioned subtree, or The first item has an initiator, second has an initiator and initia- tor value of first is distinguishable from initiator value of the sec- ond. Both types have initiators and they are the same, or both types have no initiator and the value of the first item is distinguishable from the value of the second item. The first item has an initiator, second does not, and value of initiator distinguishable from the val- ue of second item. The first item has no initiator, second does, and the first item's value is distinguishable from the value of the sec- ond item's initiator.
item	sequence group, choice	The first component or partition is either:
	group, or unordered group	• An item marked as initiator distinguishable and
		The second type has an initiator and those initiators are mutually exclusive, or The second type has no initiator and the item is initia- tor-distinguishable from each type in the starting component set of the group.
		An item not marked as initiator distinguishable and
		The item and group both have an initiator and the initiator of the item is distinguishable from the initiator of the group, or The item has no initiator, the group has an initiator, and the item's value is distinguishable from the value of group's initiator, or Both types have initiators and they are the same or both types have no initia- tor, and the item's value is distinguishable from the type of each component in the starting component set of the group, or The

Туре 1	Type 2	How to define them as content-distinguishable
		item has an initiator, the group has no initiator, and the item is con- tent-distinguishable from the type of each component in the start- ing component set of the group, or The item has no initiator, the group has an initiator, and the item's value is distinguishable from each type in the starting component set of the group.
item	partitioned item or parti- tioned group	The first component or partition is content-distinguishable from each partition of the second type.
partitioned item	item	Each partition of the first type is content-distinguishable from the second type.
partitioned item	sequence group	Each partition of the first type is content-distinguishable from the second type.
partitioned item	choice group	Each partition of the first type is content-distinguishable from sec- ond type.
partitioned item	unordered group	Each partition of the first type is content-distinguishable from sec- ond type.
partitioned item	item	Each partition of the first type is content-distinguishable from sec- ond type.
partitioned item	partitioned group	Each partition of the first type is content-distinguishable from sec- ond type.
group	item	Each partition of the partitioned group is content-distinguishable from the item.
partitioned group	partitioned item	Each partition of the partitioned group is content-distinguishable from each partition of the item.
partitioned group	sequence group	Each partition of the partitioned group is content-distinguishable from the second group.
partitioned group	partitioned group	Each partition of the first partitioned group is content-distinguish- able from each partition of the second partitioned group.
partitioned group	choice group	Each partition of the partitioned group is content-distinguishable from the choice group.
partitioned group	unordered group	Each partition of the partitioned group is content-distinguishable from the unordered group.
sequence group	item	The first component is either:

• A group marked as initiator distinguishable and

Type 1	Type 2	How to define them as content-distinguishable
		The item has an initiator and the initiator value of the group is dis-
		tinguishable from the initiator value of the item, or The second
		type has no initiator and the initiator value of the first type is distin-
		guishable from the value of the second type.
		 A group not marked as initiator distinguishable and
		The group has an initiator, the item has an initiator and the initia-
		tor value of the group is distinguishable from initiator value of the
		item, or The group has an initiator, the item does not, and value of
		the initiator is distinguishable from value of the item, or Both types
		have initiators and they are the same, or both types have no ini-
		tiator and each type in the starting component set of the group is
		content-distinguishable from the value of the second item.
sequence group	sequence group	The first component is either:
		• A group marked as initiator distinguishable, and
		Both groups are different partitions of the same partitioned sub-
		tree, or The second type has an initiator and those initiators are
		mutually exclusive, or The second type has no initiator and the
		first group is initiator-distinguishable from each type in the starting
		component set of the second group.
		• A group not marked as initiator distinguishable, and
		Both groups are different partitions of the same partitioned sub-
		tree, or Both groups have an initiator and the initiator value of the
		first group is distinguishable from the initiator value of the second
		group, or The first group has no initiator, the second group has an
		initiator and the type of each component in the starting component
		set of the first group is content-distinguishable from the second
		group, or The first group has an initiator, the second group has no
		initiator and the first group is content-distinguishable from the type
		of each component in the starting component set of the group.
		Both types have initiators and they are the same or both types have

no initiator and The first group is content-distinguishable from the starting component set of the second group, or The second group is content-distinguishable from the starting component set of the first group, or The starting component set of the first group is con-

Туре 1	Туре 2	How to define them as content-distinguishable
		tent-distinguishable from the starting component set of the second group.
sequence group	choice group or group	The first component is either:
		• A group marked as initiator distinguishable and
		Both groups are different partitions of the same partitioned sub- tree, or The second type has an initiator and those initiators are mutually exclusive, or The second group has no initiator and the first group is initiator-distinguishable from the type of each compo- nent of the second group.
		• A group not marked as initiator distinguishable and
		Both groups are different partitions of the same partitioned sub- tree, or Both groups have an initiator and the initiator of the first group is distinguishable from the initiator of the second group, or The first group has an initiator, the second group has no initiator and the first group is content-distinguishable from the type of each component of the second group, or The first group has no initiator the second group has an initiator, and each component in the start- ing component set of the first group is distinguishable from the second group, or Both types have initiators, either the initiators are the same or both types have no initiator, and each component in the starting component set of the first group is content-distinguish- able from the type of each component of the second group.
sequence group	partitioned item or parti- tioned group	The first component is either:
		 A group marked as initiator-distinguishable and the group is initiator-distinguishable from each partition of the sec- ond type, or A group not marked as initiator-distinguishable and the group is content-distinguishable from each partition of the second type.
choice group or	item	The first component is either:
unordered group		 A group marked as initiator distinguishable and
		The item has an initiator and the initiator value of the group is distinguishable from the initiator value of the item, or

Type 1	Type 2	How to define them as content-distinguishable
		The second type has no initiator and the initiator value of the first type is distinguishable from the value of the sec- ond type.
		 A group not marked as initiator distinguishable and
		Both types have an initiator and the initiator value of the group is distinguishable from initiator value of the item, or
		The group has an initiator, the item does not, and the value of the initiator is distinguishable from value of the item, or
		The group has no initiator, the item has an initiator and the starting component set of the group is content-distinguish- able from the item, or
		Both types have initiators and they are the same, both types have no initiator and the type of each component of the group is distinguishable from the value of the second item.
choice group or	sequence group	The first component is either:
group		 A group marked as initiator distinguishable and
		Both groups are different partitions of the same partitioned sub- tree, or The second type has an initiator and those initiators are mutually exclusive, or The second type has no initiator and the first group is initiator-distinguishable from each type in the starting set of the second group.
		• A group not marked as initiator distinguishable, and
		Both groups are different partitions of the same partitioned sub- tree, or Both groups have an initiator and the initiator value of the first group is distinguishable from the initiator value of the second group, or The first group has an initiator, the second group has no initiator and the first group is content-distinguishable from the type of each component in the starting component set of the second group. The first group has no initiator, the second group has an initiator and the type of each component of the first group is con- tent-distinguishable from the second group, or. Both types have ini- tiators and they are the same or both types have no initiator, and the type of each component of the first group is content-distin-

Type 1	Type 2	How to define them as content-distinguishable
		guishable from the type of each component in the starting compo-
		nent set of the second group.
choice group or group	choice group or group	The first component is either:
group		 A group marked as initiator distinguishable and
		Both groups are different partitions of the same partitioned sub-
		tree, or The second type has an initiator and those initiators are
		mutually exclusive, or The second group has no initiator and the
		first group is initiator-distinguishable from the type of each compo- nent of the second group.
		• A group not marked as initiator distinguishable and
		Both groups are different partitions of the same partitioned sub- tree, or Both groups have an initiator and the initiator of the first group is distinguishable from the initiator of the second group, or The first group has an initiator, the second group has no initiator and the first group is content-distinguishable from the type of each component of the second group, or The first group has no initiator the second group has an initiator, and each component of the first group is distinguishable from the second group, or Both types have initiators and the initiators are the same or both types have no ini- tiator, and the type of each component of the first group is con- tent-distinguishable from the type of each component of the sec- ond group.
choice group or	partitioned item or parti-	The first component is either:
group	tioned group	 A group marked as initiator-distinguishable and the group is initiator-distinguishable from each partition of the sec- ond type, or A group not marked as initiator-distinguishable and the group is content-distinguishable from each partition of the second type.

Ending-distinguishable types

Ending-distinguishability is used to determine if the end of a data object is distinguishable from the start of any other data object that could be next in the data.

The following table describes how two types may be ending-distinguishable. This is helpful if you are validating data and you receive a message that says a type exists, but it belongs to the wrong component.

Type1	Туре2	How to define them as ending-distinguishable
item	item or sequence group or choice group or unordered group	Type1 is bound or the value of Type1 is content-distinguish- able from Type2.
item	partitioned item or partitioned group	Type1 is bound or the value of Type1 is content-distinguish- able from each partition of Type2.
sequence group	item or sequence group or choice group or unordered group	Either: • Type1 is bound.
		or
		For each component in the unbound set of Type1
		 If the component has a fixed range it must be end- ing-distinguishable from Type2. If the component range is variable, it must be con- tent-distinguishable from Type2 and ending-distin- guishable from Type2.
sequence group	partitioned item or partitioned group	Either:
		 Type1 is bound.
		or
		For each component in the unbound set of Type1
		 If the component has a fixed range it must be end- ing-distinguishable from each partition of Type2. If the component range is variable, it must be con- tent-distinguishable from each partition of Type2 and ending-distinguishable from each partition of Type2.
choice group or un- ordered group	item or sequence group or choice group or unordered	Either:Type1 is bound.
	group	

Type1	Туре2	How to define them as ending-distinguishable
		 For each component of Type1,
		The type of that component is bound, or The type of that component is unbound, and that type must be ending-dis-tinguishable from Type2.
choice group or un-	partitioned item or partitioned	Either:
ordered group	group	• Type1 is bound.
		or
		 For each component of Type1,
		The type of that component is bound, or The type of that
		component is unbound, and that type must be ending-dis-
		tinguishable from each partition of Type2.
partitioned item or partitioned group	item, sequence group, choice group, or unordered group	For each partition of Type1, either:
partitionea group	group, or anoracica group	 The partition is a partitioned type and ending-distin- guishable from the second type, or
		• The partition of the first type is bound, or
		• The partition of the first type is unbound and end-
		ing-distinguishable from the second type.
partitioned item or partitioned group	partitioned item or partitioned group	For each partition of the first type, either:
P 9 P	3	The partition is a partitioned type and ending-distin-
		guishable from the second type, or
		• The partition of the first type is bound, or
		The partition of the first type is unbound and end-
		ing-distinguishable from the second type.

Distinguishable data objects of an implicit group

When a data object belongs to an implicit sequence, determining the component a data object belongs to depends on the format of the sequence, the type definition of a component, and the component properties.

Guidelines for defining an implicit delimited sequence

- If the type of a component has a terminator, that terminator must be different from the delimiter of the explicit group. If the delimiter and terminator are both defined as literal values, a type analysis confirms both have different values.
- The type of a component cannot be a binary item whose length is not fixed or sized.
- If the type of a component or a contained component is not bound, the type of the component cannot have a delimiter that is the same as the delimiter of the implicit sequence.
- If the range of a component is not bound, the type of that component must be content-distinguishable from the type of each component in the following set of that component.
- If the type of a component has both an initiator and terminator, the nested delimiters do not have restrictions. If this is not the case, all contained delimiters must be different.

Guidelines for defining an implicit sequence that has no delimiter

- The type of a component cannot be a binary item whose length is not fixed or sized.
- If the range of a component is bound, but the type of the component is unbound, the type must be endingdistinguishable from each type in the component's following set.
- If the range of a component is not bound, all the following rules apply:
 - The type of the component must be content-distinguishable from each type in the component's following set.
 - If the maximum range for that component is greater than one, and the type is unbound, the type must be ending-distinguishable from itself.
 - If the type of the component is unbound, the type must be end-distinguishable from each type in the component's following set.

Guidelines for defining an implicit unordered group that is delimited

- The type of a component cannot be a binary item whose length is not fixed.
- The type of a component must be content-distinguishable from the type of each other component.
- If the type of a component has both an initiator and terminator, the nested delimiters do not have restrictions. If this is not the case, all contained delimiters must be different.

Guidelines for defining an implicit unordered group that has no delimiter

- The type of a component cannot be a binary item whose length is not fixed.
- The type of a component must be content-distinguishable from the type of each other component.
- If the type of a component is unbound, the type must be ending-distinguishable from the type of each other component.
- If the maximum range is greater than one and the type is unbound, the type must be ending-distinguishable from itself.

Distinguishable data objects of an explicit group

When a data object belongs to an unordered group, distinguishing one data object from another depends on the format of the unordered group and the type definition of each component.

Guidelines for defining an explicit fixed group

- In a fixed group, each component must be either an item of fixed size, an item padded to a fixed length, or an explicit fixed group.
- The range maximum for each component must have a specific value; it cannot be **s**. A fixed amount of space is assumed in the data stream for each series member of a component in a fixed group.

Guidelines for defining an explicit delimited group

A component of an explicit delimited group can be a group or item, with the following restrictions:

- If the type of a component has a terminator, that terminator must be different from the delimiter of the explicit group. If the delimiter and terminator are both defined as a literal, analysis confirms if both have different values.
- If a component of an explicit delimited group is a binary item whose length is not fixed, that component must be sized by the component that precedes it.
- If the type of a component, or a contained component, does not have a terminator and the type of the component has a delimiter that is the same as the delimiter of the explicit group, the type of the component *must* be an explicit sequence. In this case, the delimiter appears as a placeholder for every data object if data of the same delimiter follows it.
- If an explicit group has a delimiter, the range maximum of any component other than the last one must have a specific value; it cannot be **s**. A delimiter is assumed in the data stream for each series member of a component of an explicit group with a delimiter.

Objects of a choice group

When a data object belongs to a choice group, which component the data object belongs to is based on the order the components appear in the type definition.

In a choice group, if a component is unbound it must be content-distinguishable from the type of each component that follows it in the component list.

Objects of a partitioned type

When data objects of different types appear in the same place in the data, the types must be distinguishable. The data must be distinguishable in the type definition. When a partition is part of a partitioned object, the process of cycling through the partitioned subtree begins to make the determination of which partition the data object belongs to.

In a partitioned type, each partition must be content-distinguishable from the type of each partition that follows it.

Distinguishable syntax objects

The system must be able to distinguish between different syntax objects contained within a group. To ensure that the syntax objects are distinguishable, use the following guidelines:

• If a component is unbound, make sure its delimiter and any delimiter contained in it is distinguishable from the delimiter of the group. If you get an analysis error, look for missing placeholders or components with a range maximum of **s**.

In a component or a contained component with the same delimiter as the type delimiter, the system assumes that the delimiter appears as a placeholder for every data object if data with the same delimiter follows it.

• If the delimited group has a terminator, make sure that the delimiter and any contained delimiter is distinguishable from the terminator.

The schema analysis verifies if the above requirement is met in a non-partitioned group.

Functions and expressions

Expressions and evaluations

You can use functions and expressions to create component rules in the Type Designer.

The **Examples** directory, located in the product installation directory, contains type trees that can help you learn how to accomplish your tasks. These type trees and maps contain component rules that show the use of many functions and expressions.

Expressions

An expression is a statement about data objects. Expressions are used in component rules in the schema designer and in map rules in the map designer.

The following are examples of expressions:

```
Account Balance = Credits - Debits
TrunkRoom < 15
PRESENT (Store#:StoreInfo)
```

As you enter an expression, you can add spaces before and after component names and operators to make the expression more readable. Additional spaces have no effect on an expression.

Expressions are a combination of literals, object names, operators, functions, and map names.

Component rule expressions evaluate to true or false

Component rules are expressions that evaluate to "true" or "false". For example, the result of each of the following component rules is "true" or "false".

```
WHEN (PRESENT (Qualifier), PRESENT (Address))
COUNT (Exchange) < COUNT (Purchase)
Invoice#:Item = Invoice#:Item[1]</pre>
```

Map rule expressions evaluate to data

Map rules are expressions that evaluate to data.

For example, the result of each of the following map rules is data:

```
= "Florida"
```

= Price:Input

```
= COUNT ( Name:Roster )
```

```
= RecordMap ( FixedRecord )
```

Literals

A literal is a constant value. A literal may be a number or a text string.

The rules for using numeric literals are:

- A numeric literal is in integer or decimal format and can be signed.
- A comma separator should not be included in a numeric literal.
- A numeric literal cannot be greater than 254 digits.

The rules for using text literals are:

- A text literal is enclosed in double quotes.
- A double-quote included in a text literal is released by another double quote.

Literals are encoded in UTF-16 (Unicode).

The following are some examples of literals:

```
"This is a text literal"

"ABC Company"

"Some ""quoted data"" to show use of a double double-quote."

1.23

-9

1045
```

Carriage return/line feeds cannot be within a quoted string. To use a carriage return/line feed the string must be broken into two strings with <CR><LF> between them. For example:

="username=????" + "<CR><LF>" + "&password=????"

will place the output username and password information on separate lines.

<CR><LF> must be within quotation marks.

Data object names

A data object is referenced in an expression by its name. An object name can be as simple as a card name or a local type name. It can also be complex depending on the object you want to reference.

Object names in map rules

In a map rule, data object names always refer to the card name that contains the data object name. So, in a map rule, a data object name ends with a card name. In the following example image, the object name for the component **Contact** of the card **ContactFile** is **Contact:ContactFile**.

The general definition of an object name in a map rule can be divided into three parts as described in the following table. If one of these parts is used, it must be sequenced according to the order in the table.

Parts of an Object Name Required Component name No Set of component-paths, each ending with either a colon or the reserved word IN No Card name Yes When IN is used, there must be a space before and after it, such as Dependent IN Claim. Object names in component rules

In a component rule, data object names always refer to components in the same component list. In a component rule, a data object name ends with a component name. For example, if **LineItem** is in a component list, the object name for the **Qty Info** component of **LineItem** is **Qty Info:LineItem**.

In the preceding **Qty Info:LineItem** example, the colon would be interpreted as *"is a component of"*. If the example was **Qty Info LineItem**, the space between **Info** and **LineItem** would be interpreted as *"is a subtype of"*.

The general definition of a component rule object name can be divided into the two parts described in the following table. If one of these parts is used, it must be sequenced according to the order in the table.

Parts of an Object Name	Required
Set of one or more component-paths	At least one is required
, infix separated with either a colon or the reserved word, $\ensuremath{\textbf{IN}}$	
The reserved word, COMPONENT	No

IN and COMPONENT are reserved words. Reserved words are not case sensitive.

Card name

A map rule can reference the object of an entire card. A card name is a simple type name from 1 to 32 bytes in length in UTF-8 encoding. For example, if the input card name is **Invoice**, the name for the card object would be **Invoice**.

Local type name

An object name can be a local type name. A local type name is specified as one or more simple type names separated by spaces, such as:

City Field

Local type names are typically used to refer to a component. If used in a component rule, for example, the component referenced in a rule is specified as a local type name. In a map rule, local type names refer to components contained in a card object.

Local type names can also be used to refer to the partitioned type of a component. When a type is partitioned, you can refer to all of its partitions by simply referring to the partitioned type.

For this example, the type **Record** is partitioned into **Header**, **Detail**, and **Trailer**. The object name that references **Header**, **Detail**, and **Trailer Record** is: **Record**

Here is another example: the type **Transcript** has **Header Record**, **Detail Record**, and **Trailer Record** as components contained within it. The object name that references all **Header**, **Detail**, and **Trailer Records** within **Transcript** would be **Record IN Transcript**.

Partition list

A partition list is a set of partition names separated by the symbols <>. A partition name is the simple name that represents the partitions found under the parent, or partitioned, type. For example, the partition Header of the type Record would have this component path: **Header<>Record**

Component path

A component path is specified as an optional partition list, followed by a local type name and then followed by an optional index. Here are some examples of component paths:

```
Grand<>Ball Room[5]
Ball Room[LAST]
Really<>Grand<>Ball Room
Ball Room
```

Indexed object names

An object name can refer to a particular occurrence of a data object. The index of the occurrence appears in square brackets immediately after its name. For example, the object name of the third **Note** would be:

Note[3]

The index between the square brackets can be an integer or the reserved word, "LAST" (a special index value that refers to the last data object of a particular series). The index cannot be another object name. To use a variable index, use the CHOOSE function.

LAST is interpreted in the context in which it is used.

Using LAST in a map rule to reference an input

In a map rule, when referencing an input, LAST refers to the very last occurrence of that input. For example, the last **Note** of the input **Report** would have the name:

Note[LAST]:Report

In this context, all of the input has been validated before map rules are evaluated.

Using LAST in a component rule

In a component rule, LAST refers to the last occurrence found. For example, in the rule:

```
PO# Field:Order = PO# Field:Order[LAST]
```

LAST refers to previous occurrence of **Order** because when this rule is evaluated, the last known **Order** is the last one found.

Using LAST in a map rule to reference an output

In a map rule, when referencing an output, LAST refers to the last built occurrence of that object. For example, using the same expression:

```
PO# Field:Order = PO# Field:Order[LAST]
```

LAST refers to the previous occurrence of **Order** because, when this rule is evaluated, the last known **Order** is the last one built.

LAST is a reserved word and is not case sensitive.

Component paths separated by a colon

A component in the component list of another object is always referenced by a colon (:). The local type name of the nested component precedes the colon. The name of the object that contains the component follows the colon. For example, the **Line Item** component of **PO** would have this name:

Line Item:PO

The Last Name component of Client, which is in turn a component of Account, would have this name:

Last Name:Client:Account

Component paths separated by IN

To reference all occurrences of an object contained in another object, use the keyword IN.

For this example, ShipSchedules appears as a component of different components within OrderAck.

The object name for all occurrences of ShipSchedules within ORD_ADR_OUT_WD Record is:

ShipSchedules IN ORD_ADR_OUT_WD Record:OrderAck

When IN is used, the contained object name must refer to the same type. In the example, the **ShipSchedules** component of **ORD_ADR_OUT_WD Record** and the **ShipSchedules** component of **OrderLine Structure** must be of the same type.

In the map designer, you can refer to all occurrences of an object contained in a card object. The object name for all occurrences of **ShipSchedules** within **OrderAck** is:

ShipSchedules IN OrderAck

Referring to all occurrences with IN COMPONENT

In the schema designer, you can refer to all occurrences of an object contained in a component list. To refer to all components in a component list, up to a given component, the word COMPONENT is used.

For example, the rule on the component **Conclusion Topic** needs to count all of the valid **Topics** up to, and including, **Conclusion Topic**.

The IN COMPONENT expression can be used:

#Topic Field:\$ = COUNT (Topic IN COMPONENT)

The above component rule works only if Topic is partitioned.

Comment object name

A comment name can be either an in-comment name or an @-comment name.

An in-comment name references all comment objects within a specified object. An in-comment name is specified as a component-path, a space, the reserved word IN, followed by another space, followed by the component path of the component on which the floating component type is defined. For example, given the data structure shown below, to reference all **INPUT Parameters** for a particular **Input**, regardless of whether they followed **Method OpenFile** or **Method GetEntry**, the object name would be **INPUT Parameters IN Input**.

An @-comment name references all comment objects that follow immediately after a specified object. An @comment name is specified as the component path of the comment, followed by the reserved symbol "@", followed by the component path of the component that follows the comment. For example, to reference only the **INPUT Parameters** that follow immediately after the **Method OpenFile** (and before **Method GetEntry**), the object name would be **INPUT Parameters** @ **Method OpenFile:Input**.

Shorthand notation

In a rule, a dollar sign (\$) can be used to refer to the object to the left of the rule cell. In the schema designer, the \$ sign refers to the object you are qualifying. In the map designer, the \$ refers to the object to which the rule evaluates.

In certain cases, you can also use a period between colons to shorten the reference to a data object name. The Use Ellipses command can be used to automatically shorten data object names you drag into rule expressions.

Using the dollar sign (\$)

The dollar sign can be used to refer to the object to the left of a rule cell.

For example, the component rule below applies to the component RunRule.

The **RunRule** in the rule can be replaced by **\$**. You can remember it this way: a dollar sign always means *"whatever component appears to the left of the rule"*.

Here is an example of a map designer rule that uses the dollar sign:

Order:Invoice = MapMyOrder (Order:PO , Index (\$))

In this example, each time this rule is evaluated, the index of the **Order:Invoice** being built is the object referred to by the **\$**.

Using ellipses

A single period can be used, like ellipses, in place of object names, as long as that object name can be interpreted as a unique object.

For example, if you have the following object name:

```
City Field:BillTo Customer:Account:File
```

you can replace it with

City Field:.:File

If file also contains another City Field, such as

City Field:ShipTo Customer:Account:File

and you use the Use Ellipses option, the system returns

```
City Field:BillTo Customer:.:File
```

Evaluating expressions

Expressions are evaluated based on the context in which data object names, literals, operators, function names and map names appear in the expression, and the data on which it operates. A component rule always evaluates once for each occurrence of a component. A map rule can evaluate many times.

When a map rule evaluates, the map designer selects an evaluation set of values and then evaluates the rule. Then it selects another evaluation set of values, if there is one, and evaluates the rule again. This continues until all the different evaluation sets have been used.

The same number of evaluations is always produced, but output objects can be ordered differently, depending on how you define your map.

For a selected evaluation set, a particular instance of a rule is evaluated using parentheses, operator precedence rules, and left-to-right precedence rules to get one result.

Card order can influence the order of evaluation sets

When an evaluation set is selected, card object names are ordered by their position in the map: card 1 before card 2, and so on. The card order for a map can affect the order of output results.

For example, suppose you want to evaluate the following map rule.

NumberSet (s) = B:Card2 + A:Card1

In this example, an evaluation set for this rule consists of one value for B and one value for A. One evaluation set produces one **NumberSet**.

As an example, here there are three As and three Bs in the data:

	A Values		B Values
1		3	
2		2	
3		1	

There are nine evaluation sets. The order of the cards might affect the order of the evaluation sets.

	Evaluation #	Α	В	Result
1		1	3	4
2		2	3	5
3		3	3	6
4		1	2	3
5		2	2	4
6		3	2	5
7		1	1	2
8		2	1	3

E	Evaluation #	Α	В	Result
9		3	1	4
E	valuation #	В	Α	Result
1		3	1	4
2		2	1	3
3		1	1	2
4		3	2	5
5		2	2	4
6		1	2	3
7		3	3	6
8		2	3	5
9		1	3	4

If both A and B are contained in the same card object, evaluation sets are selected based on the order A and B appear in the rule. Leftmost objects are selected first. If you change the rule to this:

NumberSet (s) = B:Card2 + A:Card2

the same results are produced as when card 2 is the first card.

Functions influence the number of evaluation sets

For this example, you have the following rule:

NumberSet (s) = A:Card1 + SUM (B:Card1)

Using the same values for A and B, there are only three evaluation sets as shown.

	A Values		B Values
1		3	
2		2	
3		1	
	A Values		B Values
1		3	

A Values		B Values	
2	2		
3	1		
A Values		B Values	
1	3		
2	2		
3	1		
If your rule looks like:			
NumberSet (s) = SUM (A:Card1) + SUM	(B:Card1)		
there is one evaluation set: NumberSet[1] = 12			
A Values		B Values	
1	3		
2	2		
3	1		

If you have the following rule:

NumberSet (s) = A:Card1 + EXTRACT (B:Card2 , B:Card2 != 2)

the order of the operands does not affect the order of evaluation set selected. This is because an A is selected, then the EXTRACT is evaluated, then evaluation sets are determined for that A and a given EXTRACT result. When all EXTRACT results are used, the next A is selected, and so on.

Given the same data, this time you get the following results:

Evaluation #	Α	I	B Extract Values	Result
1	1	3	4	
2	1	1	2	
3	2	3	5	
4	2	1	3	
5	3	3	6	
6	3	1	4	

As another example, the following map rule applies to the output Status(s):

The first argument of the IF function is an expression. One evaluation set of this expression requires:

- the Order
- one Order Record
- one Quantity of the selected Order Record
- all the Stores of the selected Order Record

The IF function evaluates once for each **Quantity** of each **Order Record**. Other than the first argument of the IF function, nothing else in the map rule affects the number of times the map rule will be evaluated. So, if there are 1000 **Quantity** data objects contained in **Order**, this map rule will evaluate 1000 times.

Object names influence the number of evaluation sets

In some expressions, the same data object name might appear more than once. The same data object name always refers to the same data object. The same data object name influences the combinations of evaluation sets that are selected. For example:

BackOrder(s) = Qty Ordered:Record:Order - Qty Received:Record:Order

When a **BackOrder** evaluation set is selected, the **Record** that contains **Qty Ordered** is always the same **Record** that contains **Qty Received**. And an **Order** is always the same one for one evaluation set. When the same object name is used more than once in the same expression, both references bind to the same object.

If there is always one Qty Ordered per Record and one Qty Received per Record, the following would be sample data:

	Record #		Qty Ordered		Qty Received
1		5		4	
2		4		4	
3		6		2	

This would produce three Back Orders, one for each Record.

You can coordinate nested data objects easily by the way an object name is used.

Using object names to coordinate evaluation sets

In the following example, common object names are used to coordinate **Qty** and **UnitPrice** so they do not get mixed up across different **Records**:

Extension = SUM (Qty:Detail Record:Order * UnitPrice:Detail Record:Order)

This rule has only one evaluation set because the SUM consumes all the objects referenced in the rule.

Using IN to decouple object name coordination

Suppose you have a situation in which you do not want to coordinate common objects. You might, for example, want to count different objects contained in the same object, as in:

Summary = COUNTabs (Header:Order:Message) + COUNTabs (Line Item:Order:Message)

If there are multiple **Orders** in your data, the **Summary** would not be evaluated correctly. This rule would only count the **Headers** of the first **Order** and add it to the count of all Line Items of the first **Order**. To count all the **Headers** and all the **Line Items** in all the **Orders**, use IN:

```
Summary = COUNTabs ( Header IN Message) + COUNTabs ( Line Item IN Message )
```

Using IN to decouple different partitions in the same rule

If data objects in an expression are different partitions of the same type, the expression might evaluate to "none".

For example:

MyMap (Good<>Design , Best<>Design)

Good and **Best** are partitions of the same type, **Design**. A given **Design** could never be both a **Good<>Design** and a **Best<>Design**; therefore, the second argument of **MyMap**, **Best<>Design**, evaluates to "none".

To reference both the Good and Best partitions, use IN:

```
MyMap ( Good IN Design , Best IN Design )
```

Operators

Operators are used for arithmetic functions and text functions on items. If an operator requires two operands, the operator symbol appears between them. For example, in the expression $\mathbf{a} + \mathbf{b}$, the operator symbol "+" appears between the operands \mathbf{a} and \mathbf{b} .

Operators are reserved symbols that cannot be used in type names.

Arithmetic operators

Operator

Description

÷

addition

-

subtraction

*

multiplication

```
1
```

division

Text operators

Operator

Description

÷

concatenation

Logical operators

Logical operators are used in expressions that evaluate to "true" or "false".

```
Operator
Description

current exclusive or

current exclusive or
```

Comparison operators

Operator

Description

```
=
```

equal to

>

greater than

<

less than

>=

greater than or equal to

<=

less than or equal to

!=

not equal to

NOT=

alternative for not equal to

The results of comparison operators are based on the native collating sequence of the machine used to run the map.

Order of operator evaluation

Use parentheses to group operations. Expressions within parentheses are evaluated before performing other operations. For example:

(UnitPrice - Discount) * Tax

The expression UnitPrice - Discount is evaluated before the rest of the expression.

Some operators are evaluated before others according to standard rules of precedence. Operators are evaluated in the following order:

Precedence	Operators	Description
first	()	Operations within parentheses
second	+ and -	unary plus and minus
		The sign indicates a positive or negative expression, for example:
		- quantity*rate
third	=, <, >, <=, >=, !=	comparative operators
fourth	٨	logical operator "exclusive or"
fifth	&	logical operator "and"
sixth	I	logical operator "or"
seventh	* and /	multiplication and division
eighth	+ and -	addition and subtraction

Operators of equal precedence are evaluated left to right.

Operands

Operands are the arguments for an operator. For example, in the expression **a** + **b**, the + is the operator symbol, and **a** and **b** are the operands.

An operand can be any of the following types:

- a literal
- a data object name
- a function
- another operator

Using functions in expressions

Functions perform a particular action on its input arguments. A function is written like this:

FUNCTION (argument1, argument2, ... argumentn)

The arguments of the function appear inside the parentheses, separated by commas. A function might require a fixed number of arguments or might allow a varying number of arguments. You can use functions anywhere in an expression.

Function arguments

Input arguments themselves can be expressions. Some functions limit the type of expression that can be used as an input argument. The syntax specification tells you the number of data objects that can be used for one function evaluation.

There is *always* one output argument for a function. The specification of the output argument tells you: 1) the type of the result produced by a function and 2) the number of objects that can be produced when the function evaluates once.

You need to know the type of the output argument because functions can be used as other arguments. The result of a function can also be used to directly produce an output data object contained in an output destination.

When the map designer analyzes the interfaces of expressions in rules during the build process, it ensures that the output argument of a function matches the input argument it is used for. The analysis also checks the type of the output argument when that function is used to directly produce an output data object.

The output argument of a function specifies the result that the function produces for one evaluation. For example, one evaluation of the ABS function produces one positive number. One function evaluation might produce multiple outputs. If it does, the expression that contains that function might produce multiple evaluation sets.

Input arguments

The input arguments for a function specify the information the function uses to return a result. Some functions require an exact number of input arguments. For other functions, the number of input arguments can vary. Optional arguments for a function are shown in brackets [].

To correctly use a function, you must use the correct arguments in the correct order.

Each argument can, itself, be an expression. In general, an input argument might be any of the following:

- an object name
- a literal
- · a function-name and its arguments
- an operator and its arguments
- an enumerated series of literals, such as {a, b, c}
- · a map name and its arguments

For example, some valid expressions that use the ABS function are:

```
ABS ( Quantity:LineItem )
ABS ( UNIQUE ( Quantity:LineItem )
ABS ( Quantity:LineItem - 300 )
```

Each function has its own expression syntax for its input arguments. For example, the ABS function cannot use a map as an argument. See Syntax of a Function on page 903 for notation used to specify valid expression syntax.

Nested input arguments

When a function, operator, or map is used as an input argument, each of these has arguments of its own. Arguments of other arguments are said to be *nested*. For example, in the use of the ABS function, you can use a function as an argument:

```
ABS ( UNIQUE ( Quantity:LineItem ) )
```

The output of the UNIQUE function becomes the input argument to the ABS function.

Output arguments

The output argument of a function indicates the type of object the function produces and the number of objects a function can produce. An output argument is specified as one of the following object types or values:

- · A single data object of a type
- · A series of data objects of the same type
- "True" or "False"

If the output of a function is a series, that function can be used only in a map rule in the map designer. It cannot be used in a component rule in the schema designer. For example, you cannot use the CLONE, EXTRACT, REJECT, SORTDOWN, SORTUP or UNIQUE functions in the schema designer.

Function arguments and evaluation

When a function is evaluated, the number of argument objects used for one evaluation depends on the function. In the specification of the syntax for a function, the number of input objects that can be used for each argument for one function evaluation is expressed as "single" or "series".

Some functions use a single object as the value of an argument for one evaluation. For example, the ABS function uses a single object as the value of its argument for one evaluation.

```
ABS ( Quantity:LineItem )
```

When a single object is used for one evaluation, the function itself can evaluate many times if there is more than one data object that fits the argument definition. For example, if there were ten **Quantity:LineItem** data objects, the ABS function could evaluate ten times.

Some functions use an entire series of objects as the value of an argument for one evaluation. For example, the COUNT function uses an entire series of data objects as the value of its argument for one evaluation.

COUNT (LineItem:PO)

When a series of data objects is used for one evaluation, the function evaluates just once when there is more than one data object that fits the argument definition. For example, if there are ten **LineItem:PO** data objects, the COUNT function would evaluate only once.

Some functions use an entire series as input and produce a series as output. For example, the evaluation set for the EXTRACT function produces a series from an input series. When a function produces a series, each output can be selected for different evaluation sets of the expression that contains that function.

Consider the following expression:

Line Item(s) = EXTRACT (Line Item:Order, Qty:Line Item:Order > 1000)

Each **Line Item** that fits the specified criteria produces a **Line Item** of **Order**. In this example, the map rule is evaluated many times, once for each **Line Item** produced by the EXTRACT function.

When functions are part of other expressions, the number of evaluation sets for that function depends on the object names used in the entire expression. For example:

Debit (s) = ABS (Debit:Account:Input)

There might be many evaluation sets for the above expression. The ABS function might be evaluated many times, once for each **Debit** of each **Account** of **Input**. However, if the ABS function is part of a more complex expression, common objects of the expression might determine the number of ABS evaluations.

Expressions that evaluate to NONE

The following discussion explains how the map designer evaluates an expression when expressions within it evaluate to "none".

When an operand evaluates to NONE

The following table explains how an operator expression evaluates when an operand evaluates to none.

The symbol **A** represents one operand of the expression and **B** represents the other operand. The symbol **!=** means *"not equal to"*.

Operator Expression	Condition	Evaluates to:
A / B	A = NONE B = NONE	NONE
A*B	A = NONE B = NONE	NONE
A / B	A != NONE B = NONE	0
A*B	A != NONE B = NONE	0
A + B	A = NONE B = NONE	NONE
A - B	A = NONE B = NONE	NONE
A + B	A = NONE B != NONE	В
A - B	A = NONE B != NONE	-В
A + B	A != NONE B = NONE	А
A - B	A != NONE B = NONE	Α
A > B	A = NONE B = NONE	FALSE
A < B	A = NONE B = NONE	FALSE
A = B	A = NONE B = NONE	TRUE
A > B	A = NONE B != NONE	FALSE
A < B	A = NONE B != NONE	TRUE
A = B	A = NONE B != NONE	FALSE
A > B	A != NONE B = NONE	TRUE
A < B	A != NONE B = NONE	FALSE
A = B	A != NONE B = NONE	FALSE

For example, in this operator expression:

Total = #Guests + 1

if #Guests evaluates to "none", the value for Total will be 1.

When an input argument of a function evaluates to NONE

If any input argument of a function evaluates to "none", the function might not evaluate to "none". For example, ABS (NONE)=NONE, but COUNT (NONE)=0.

When an input argument of a functional map evaluates to NONE

If any argument of a functional map evaluates to "none", the functional map will not be evaluated for that evaluation set.

For example:

MakeForm (EntryForm:Input , GroupInfo:Input)

Where the object **GroupInfo** is optional; it has a component range of (0:3). If there are no occurrences of **GroupInfo** in the **Input** data object, the map **MakeForm** will not be evaluated at all.

Here is another example:

OrderMap (OrderRecord:Order:Input , SummaryRecord:Order:Input)

If **SummaryRecord** has a component range of (0:1) and it is missing in a particular **Order**. The map **OrderMap** will not be evaluated for that **Order**.

If you want **OrderMap** to be evaluated even when **SummaryRecord** is missing, use the entire **Order** as an input argument, rather than **SummaryRecord**. This will ensure that **OrderMap** will be evaluated, even if **SummaryRecord** is missing. Then, in the map **OrderMap**, you can still map from **SummaryRecord**.

The rule you should use is this:

OrderMap (OrderRecord:Order:Input , Order:Input)

When an input of an executable map evaluates to NONE

The evaluation of a map referenced in an expression differs from the evaluation of that map when it is executed as a functional map and the evaluation of a function because of how the NONE is treated.

The evaluation of a map used as a function is different from the evaluation of that map when it is run as an executable map. When a map is run as an executable, if any input card data object has no content, the map will still run. This is not true when that map is referenced as a function. If any input argument of a functional map evaluates to "none", the map will not evaluate.

Impact of track setting on order of output

This property setting determines whether objects are tracked according to content or according to their position within a series. This setting will determine the sequence in which those objects are evaluated when referenced.

For example, assume that **RunsByInning** is a component of **BallGame**. **BallGame** is defined as an explicit format, delimited (by a colon) group. The data for **BallGame** is as follows:

2::1:1::1::3

• Track Content. If BallGame has a Track setting of Content, all instances of RunsByInning with content will be mapped before any empty instances. So, if BallGame was mapped to itself, the output would be:

2:1:1:1:3

• **Track Places**. If **BallGame** has a **Track** setting of Places, instances of **RunsByInning** will be mapped in the sequence in which they occur, including those instances that are empty. So, if **BallGame** was mapped to itself, the output would match the input.

2::1:1::1::3

Track Places will only have an impact on the sequence of the output when *both* the input group object and output group object are defined as **Track Places**.

However, **Track Places** will have an impact in situations in which an input defined with **Track Places** is referenced by index. For instance, in the above example,

- If **RunsByInning** was defined as Track Places, **RunsByInning[2]:BallGame** would have a value of **2** because the value in the second "place" in **BallGame** is a **2**.
- On the other hand, if **RunsByInning** was defined as **Track Content**, **RunsByInning[2]:BallGame** would have a value of **1** because the second instance of **BallGame** with content has a value of **1**.

Evaluated expressions assigned to output items

NONE assigned to an output number

When an output item is defined as a number, its value is determined from the result of the evaluated expression that is then converted to its output form as follows:

	Output is specified as:		Evaluated value		Output value
Required		0		0	
Required		NONE		0	
Optional		0		0	
Optional		NONE		NONE	

Automatic item format conversions

When an item is assigned an output value, the map designer will automatically convert an item with the same interpretation (either number, text, date, or time) from one presentation to another. For example, if you want to map an item that is a number and whose presentation is integer to an item that is also a number but whose presentation is decimal, the map designer will automatically convert it.

The map designer fills in missing information in date and time conversions in the following way:

- Dates with a year, but no century. The century will be determined using the CenturyDerivation map setting.
- Missing part of an output date format. If a portion of the format of an output date cannot be derived from the input date, the missing part will have pound characters (#) in its place. For example, if 09/98 is the date for an

input with a format string of MM/YY and that date was mapped to an output date with a format of MM/DD/YY, the output date would be built as **09/##/98**.

• **Missing part of an output time format**. If a portion of the format of an output time cannot be derived from the input time, the missing part will have zeroes (0) in its place. For example, if 12:14 is the data for an input with a format string of HH12:MM and that time was mapped to an output time with a format of HH:MM:SS, the output date would be built as **12:14:00**.

To convert a number to text, a date or time, or vice versa, you must use a function to perform the conversion. For example, to convert a date to text, use the function DATETOTEXT.

Numeric precision

All numbers in the input and numeric literals in map rules are converted to multiple precision and converted to the format required at output time.

- If the multiple precision number does not overflow but does not fit into the maximum size of a numeric item, that item is filled with the number sign character (#) up to its maximum size.
- An arithmetic overflow is recognized when an arithmetic expression includes:
 - Divide by zero
 - A multiple precision number greater than 1.0E254

Arithmetic overflow is designated in the output object with up to a maximum of ten number sign (#) characters.

Generating line numbers in test data

You can generate index line numbers for the CSV or excel format test data.

- If you want line numbers in the text output, apply =TEXT(COUNTER)
- If you want line numbers in the numeral output, apply, = COUNTER

Using functions

A function is an expression that generates an output by performing a certain operation on one or more inputs. Most functions can be used in both component rules and map rules. Those that produce a series can only be used in map rules.

Functions in a component rule

For example, the object **TotalQty** in your data is the sum of all the **Qty** objects in your data; in a component rule for **TotalQty**, you can use the SUM function to verify this relationship.

Functions in a map rule

Suppose you want to map your data differently according to the presence of a certain input data object. In your map rule, to check the presence of the data object, use the function PRESENT. To create the output according to whether

the input data was present, use the function IF. Examples of the IF function can be found in "Logical Functions" on page 1011. Examples of the PRESENT function can be found in "Inspection Functions" on page 996.

Syntax of a function

The following is an example of a function:

FUNCTION (argument1, argument2, ... argumentn)

When you use a function, substitute the name of a specific function for FUNCTION and substitute a specific expression for each input argument. Each input argument is separated by a comma and the set of arguments is surrounded by parentheses.

Function argument syntax

Arguments typically have some restrictions on the expression used for that argument. For example, the input argument to the INDEX function can only be an object name. Depending on the function, one or many data objects can be used for an input argument for one function evaluation.

For each function listed in this documentation, the input argument has a syntax definition that indicates:

 the number of objects that can be used for each argument for one function evaluation, expressed as either single or series

followed by

• the type of expression that can be used for each argument.

For the output argument, the syntax specification is similar to the input argument syntax, except that the output is always used as a specific type of object, not an expression.

For example, single-item-expression means one evaluation operates on a single item that can be defined as an item expression. Series-item-expression means one evaluation operates on one or more input argument items that can be defined as an item expression.

In this documentation, the terms listed in the following table are used to describe the syntax of function arguments.

Term

Explanation

general-expression

Any valid combination of object names, literals, operators, function names, and map names.

condition-expression

Any valid combinations of object names, literals, conditional operators, and functions whose output arguments are specified as true or false.

item-expression

Any valid combination of object names, literals, operators, and functions whose output argument is specified as an item.

If an item must be interpreted as a date, time, or number, the item is referenced by its interpretation. For example, if an item-expression must be text, it is specified as text-expression.

object-expression

An object name or a series producing function.

If an object expression is further limited to be an item, it is specified as item-object-expression.

object-name

The name of a data object, as defined in Data Object Names on page 884. If an object name is further limited, it is specified as a prefix. For example, simple-object-name refers to a simple type name.

•••

Indicates that the function can take on any number of additional similar arguments.

[]

Indicates that the argument is optional.

{ literal , literal ...}

An enumerated series of literals.

The syntax specification shows each input argument, using terms as described in the previous table, preceded by the word single or series. For example:

Syntax:

ALL (series-condition-expression)

The arguments are defined using a name that describes its use by the function. A simple example is:

Meaning:

```
DATETONUMBER ( date_to_convert )
```

Function names are shown in uppercase letters in this documentation. However, function names are not case sensitive.

There is also a description of what each function returns.

Returns:

A single integer

Functions that convert character-set encoding to the native code page

Functions that use the EXIT architecture convert data to the native character set of the platform as part of the function call. These functions use the EXIT architecture:

- DBLOOKUP
- DBQUERY
- DDEQUERY
- EXIT
- JEXIT
- GET
- PUT
- RUN
- XQUERY
- XSLT
- MATHLIB functions
- XMLLIB functions (except XPATH and XPATHEX)
- RESOURCELIB functions
- Customer-developed functions that use the EXIT architecture

Maps that use these functions must take the data conversion into account. For example, a map that uses the EXIT architecture converts non-EBCDIC data to EBCDIC when the map runs on a z/OS® platform. To prevent the data conversion, the map must use a function like:

CTEXT(object, "Native")

If the function returns the data from the z/OS® platform to another platform, the map must specify that the data to return is non-EBCIDIC by using a function like:

CTEXT(object, "data language")

General functions

ASFUNCTION

When you run a functional map with the ASFUNCTION function, the output of the functional map returns to the map rule that invoked the functional map. The invoking rule can work with the output from the functional map. The type of the output card must be an item.

Without ASFUNCTION, a functional map writes to the output card before the rest of the invoking rule is evaluated.

If ASFUNCTION runs a functional map that calls a second functional map, the output of the second map also returns to the map rule, as if the second map had been invoked by ASFUNCTION. If the output of each map is a number and the outputs are concatenated, ASFUNCTION adds the numbers instead of concatenating them.

Syntax:

ASFUNCTION (general-expression)

Meaning:

ASFUNCTION (FunctionalMapName (argument-1 , argument-2 , ... argument-n))

Returns:

item

Example 1

Rule:

```
Output_name = FMAP1 (rule) + " and " + Fmap2 (rule) + "."
```

Result:

Output_of_FMap1Output_of_FMap2 and .

Rule:

```
Output_name = ASFUNCTION(FMAP1 (rule)) + " and " + Fmap2 (rule) + "."
```

Result:

Output_of_FMap1 and Output_of_FMap2.

Example 2

Rule:

Output_name = IF (FMap1 (rule) = "abc", "equal", "not equal")

Result:

• If FMap1 produces abc:

abcnot equal

• If FMap1 produces def:

defnot equal

Rule:

```
Output_name = ASFUNCTION(IF (FMap1 (rule) = "abc", "equal", "not equal"))
```

Result:

• If FMap1 produces abc:

equal

• If FMap1 produces def:

not equal

Example 3

Rule:

```
Output_name = ASFUNCTION(FMAP1(rule1)) + FMAP2(rule2)
```

Result:

• If FMAP1 produces 1 and FMAP2 produces 2:

3

- If FMAP1 produces ${\tt A}$ and FMAP2 produces ${\tt B}$:

AB

CLONE

The CLONE function creates a specified number of copies of some object.

This function can be useful when the number of output objects to be built depends on a data value, rather than the number of objects that exist in the data.

Syntax:

CLONE (single-object-name, single-integer-expression)

Meaning:

CLONE (object_to_copy , number_of_copies)

Returns:

A series-object

The CLONE function returns a series of the object specified by *object_to_copy*. The output series consists of as many copies of the object as specified by *number_of_copies*. The value of each member of the resulting output series is the same as *object_to_copy*.

Examples

• LineItem Segment (s) = LotsOf (CLONE (Detail Row , Quantity:Detail Row))

In this example, the input contains an object named **Detail Row** that has a **Quantity** item component. You want to create multiple **Line Item Segments** for every **Detail Row** in your input based on the value of **Quantity**. So, if **Quantity** has the value 5, you want to build five **Line Item Segments** for that **Detail Row**.

DEFAULT

The DEFAULT function allows a predefined value to be introduced into an expression.

DEFAULT, which is typically used with the EITHER function, returns the value assigned as the default value when the type was defined.

Syntax:

DEFAULT(single-type-expression)

Meaning:

DEFAULT(type_whose_defined_default_value_is_desired)

Returns:

A single-object

Examples

DEFAULT(ZipCode)

In this example, the defined default value for ZipCode is returned. When used with EITHER, DEFAULT might appear like this:

EITHER(ZipCode, DEFAULT(ZipCode))

If the first argument evaluates to a value other than "none", that value is used. If the first argument evaluates to "none", the default value for **ZipCode** is used.

ECHOIN

The ECHOIN function returns a command (or property) to be used in a RUN function argument.

Syntax:

ECHOIN (single-integer-expression, single-text-expression)

Meaning:

ECHOIN (card#, item_or_group_interpreted_as_text)

Returns:

A single object

Examples

Before ECHOIN was introduced, the RUN function was used in this way:

```
RUN ("Mymap", "-IE1S"+NUMBERTOTEXT (SIZE(Data))+ " " + TEXT(Data)))
```

You can use ECHOIN with RUN, similar to the following example:

```
RUN ("Mymap", ECHOIN(1,(Data)))
```

Related functions

HANDLEIN

HANDLEIN

The HANDLEIN function returns a command (or property) to be used in a RUN function argument.

You can use the HANDLEIN function when deriving large amounts of data from a parent map for use in a RUN map. The HANDLEIN function works by using the same instance of the parent map's data set in the RUN map, instead of duplicating it as the ECHOIN function does.

The result of the HANDLEIN function is a text object that defines the characteristics of the data to be used. This includes an internal handle, offset, and length of the data. The result of this can be seen in an execution audit log:

You cannot use a GETANDSET function against an input that is passed using HANDLEIN.

Syntax:

HANDLEIN (single-integer-expression, single-text-expression)

Meaning:

HANDLEIN (card_to_override, data_object)

Returns:

A character text item

When the HANDLEIN function returns a character text item, the string is prefixed with: **IH***x*, where *x* is the first parameter.

String format:

-IHx <internal-handle>.<offset>.<length>

Example:

-IH1 4.4096.512

A *single-integer-expression* is the number item that specifies the card number to override. A *single-text-expression* specifies the data object to use for the override.

In a RUN map rule, you can override a source card with a handle of a current map's card by specifying the card to override and the object to override it with.

Examples

In the following rule, the data is object c:b:a for input card 2 of the RUN map:

HANDLEIN(2, c:b:a)

The second parameter can be more complex if needed. For example,

```
HANDLEIN(2, SUBSTITUE(c:b:a, "a", "A"))
```

Any data in object **c:b:a** that contains a lowercase "a" would change it to an uppercase "A" for the call to the RUN map. In cases such as this, where the data cannot be expressed contiguously within the original card or cards, a scratch file is used to hold the expression and the calling map's handle is that of the scratch file.

There is no correlation between the handle returned in the output of HANDLEIN and the actual card number of the second parameter.

Related functions

Generally, the ECHOIN function is used to return a command or property to be used in a RUN function argument. However, for large amounts of data, using the HANDLEIN function can be more efficient.

For best results, use the ECHOIN function for small quantities of data, such as less than 100K, and the HANDLEIN function for larger quantities of data of more than 100K.

PARSE

The PARSE function analyzes a data object and validates it against the metadata of a component type. The resulting data structure is available to the calling map for further processing.

The input to the PARSE function is any data that can be processed as a text blob, for example, the result of a functional map invocation, a GET function, or a RUN map.

Syntax

PARSE (general_expression)

Meaning

PARSE (data_to_parse)

Returns

A mapped data object in a work file

Examples

The data structure that results from the PARSE function is available to the calling map. When you use a RUN map to parse data, the resulting data structure is available to the RUN map rather than to the calling map. By using the PARSE function instead of the RUN map implementation, you have fewer maps to configure and maintain.

The following examples:

- 1. Receive an input document from the SPE adapter
- 2. Extract the data objects from the document envelope
- 3. Return a response

Example 1: RUN map implementation

In this example, the DEENVELOPE map calls the RUN map named DUMPRESPONSE to extract the data from the document.

The DUMPRESPONSE map has two input cards:

- SpeResponse (Response global XSD)
- Test Root (text root)

The output card of the DUMPRESPONSE map has the following rule:

```
=WriteDocument(Document:sequence:Documents:sequence:SpeResponse,
TestRoot;
TEXT(INDEX(Document:sequence:Documents:sequence:SpeResponse))) + "<NL>"
```

The DEENVELOPE map has two input cards:

- Dataln (text root)
- Test Root (text root)

The DEENVELOPE map has two output cards:

• DOCOUTPUT:

```
= RUN ("DumpResponse", ECHOIN( 1 , Deenvelope ) + ECHOIN( 2 , TestRoot ) + " -OE1" )
```

• DEENVELOPE:

```
=VALID(GET("SPE", "-DURL jdbc:derby://localhost:1527/spe2
-DBUSER derbyuser -DBPSWD derbypw
-DBDRIVER org.apache.derby.jdbc.ClientDriver -DENV", DataIn),
FAIL ("SPE Deenvelope failed: " + LASTERRORMSG() ))
/*
=VALID(GET("SPE", "-DURL jdbc:db2://bobdb9.bcr.ibm.com:50000/spetest
-DBDRIVER com.ibm.db2.jcc.DB2Driver -DBUSER spetest -DBPSWD Seer5r12
-DENV -T ", DataIn),
FAIL ("SPE Deenvelope failed: " + LASTERRORMSG() ))
*/
/*
=VALID(GET("SPE", "-DURL jdbc:db2://localhost:60000/SPETEST
-DBDRIVER com.ibm.db2.jcc.DB2Driver -DBUSER fred -DBPSWD org13asd
-DENV -T ", DataIn),
FAIL ("SPE Deenvelope failed: " + LASTERRORMSG() ))
*/
```

Example 2: PARSE function implementation

In this example, a single map uses the PARSE function to perform the processing of the two maps in Example 1.

The DEENVELOPE_PARSE map has two input cards:

- Dataln (text root)
- Test Root (text root)

The DEENVELOPE_PARSE map has two output cards:

• RESPONSEINFO:

```
= WriteDocument( Document:sequence:Documents:sequence:SpeResponse,
TestRoot,
TEXT( INDEX( Document:sequence:Documents:sequence:SpeResponse ) ) ) + "<NL>"
= "Response - Status: " + Status:sequence:SpeResponse + ",
```

- Advanced status: " + AdvancedStatus:sequence:SpeResponse + "<NL>"
- SPERESPONSE (Response Global XSD):

```
=PARSE( VALID(GET("SPE", "-DURL jdbc:derby://localhost:1527/spe2
-DBUSER derbyuser -DBPSWD derbypw
-DBDRIVER org.apache.derby.jdbc.ClientDriver -DENV", DataIn),
FAIL ("SPE Deenvelope failed: " + LASTERRORMSG() )) )
```

REFORMAT

The REFORMAT function returns a type object that results from replacing the syntax of the input type with the syntax of the output type.

The initiator and terminator of the output type are built. The content result rules are determined based on the Input type and the Output type. Groups and Items can be used with REFORMAT.

REFORMAT cannot be used as an argument to a function, operator, or functional map.

Syntax:

REFORMAT (single-object-expression)

Meaning:

REFORMAT (type-to-convert)

Returns:

A type object

REFORMAT returns a type object whose content matches the input type object, but whose syntax matches the output type object. The following table details the expected results based on the input and output.

Input Type	Output Type	Result
Group	Group	The content for each output component results from the content of the cor- responding input group component content. For example, output compo- nent 1 is matched with input component 1, output component 2 is matched with input component 2, and so on. The components of the groups must be items, not another group. If there is no matching input component for an out- put component, the output component's required occurrences are built as "none"S. If there is no matching output component for an input component, the data of that input component is ignored.
		When a component occurrence is built, the delimiter (if any) of the contained output group is built and an object of the component's output type is built from the corresponding input type using the REFORMAT algorithm.
Group	ltem	The text of a corresponding input group content.
ltem	Group	The input item content is applied as though it were the first component of the output group.
Item	ltem	The input item content is applied to the output item content.

Examples

MyXMLPurchaseOrder = REFORMAT(MyCOBOL_PurchaseOrder)

This function is useful when the same type structure might come from different type trees, such as different versions of the same EDI, or when converting traditional formats to XML.

RESOLVETYPE

The RESOLVETYPE function resolves the provided component path to a specific type tree reference when the map is being compiled.

This function returns the type of the component for the component path that you provided as an argument. It is used only with the IN keyword, to resolve the provided component path to a specific type tree reference. Use it when more than one type that has the same name occurs within (IN) the containing component or card. Specify this function only in map rules, not in component rules.

Syntax:

RESOLVETYPE (single-text-expression)

Meaning:

RESOLVETYPE (component_path_to_resolve)

Returns:

A single type reference

For more information about using the IN keyword to reference all occurrences of an object contained in another object, see Component paths separated by IN on page 887.

Example

NetWorth = SUM (RESOLVETYPE (Price:Cars:East:Regions) IN Inventory)

In the example, you have an inventory of cars and trucks in dealerships in different geographic regions: **East**, **West**, **North**, and **South**. The price of the cars and trucks are represented by two different types in the type tree with the same name, **Price**. You want to determine the net worth of the inventory of just cars from all of the dealerships in all of the regions.

The RESOLVETYPE function is used to return the type of the component path. In this example, the function is set up to return the type, **Price**, for **Cars**, for the component path, <u>Price:Cars:East:Regions</u>, specified in the argument of the function. This function also returns the same type, **Price**, for **Cars**, if the argument of the function specifies any of the **Regions** in the following component paths: <u>Price:Cars:West:Regions</u>, <u>Price:Cars:North:Regions</u>, and <u>Price:Cars:South:Regions</u>. Then **Price**, for **Cars**, is used as the criteria for the selection process in your total **Inventory**. The mapping process calculates the net worth by summing the values of **Price** for all **Cars** in all of the **Regions** in the total **Inventory**.

If you do not specify the RESOLVETYPE function, and instead, specify a rule such as <u>NetWorth = SUM (Price IN</u> Inventory), the mapping process uses either one of the types, **Price** for **Cars**, or **Price** for **Trucks**, as the criteria for the selection process in your total **Inventory**. If you do specify the RESOLVETYPE function, the mapping process uses the returned type of the component path, specified in the argument of the function, as the criteria for the selection process in your total **Inventory**.

If you want to determine the net worth of just **Trucks** in the **Inventory** from all of the dealerships in all of the **Regions**, you can specify the RESOLVETYPE function in the following way: <u>NetWorth = SUM (RESOLVETYPE</u>) (Price:Trucks:North:Regions) IN Inventory). Again, the function also returns the same type, **Price**, for **Trucks**, if the argument of the function specifies any of the **Regions** in the following component paths: <u>Price:Trucks:West:Regions</u>, **Price:Trucks:East:Regions**, and <u>Price:Trucks:South:Regions</u>.

Bidirectional functions

Bidirectional languages such as Arabic and Hebrew are languages in which the text is presented to the user ordered from right to left, but numbers and Latin alphabetic strings within the text are presented left to right. In addition, the order in which characters appear within program variables can vary. The text is usually stored in logical order, the order in which the characters are entered in the input field. These differences in ordering and in other associated presentation characteristics require the program to have the ability to convert bidirectional text strings from one format to another.

Use the SETLOGICALORDER, SETVISUALORDER, SETORIENTATIONLTR, SETORIENTATIONRTL, SETTEXTSHAPING, and SETTEXTSHAPINGOFF functions for specific transformation needs when dealing with bidirectional data.

About the order of text

The order of text generally corresponds with way it is stored in memory or on disk. In general, the order of text is displayed, on the window for example, in visual order so that a person can read it the way it is subjectively meant to be read. That is, left-to-right characters are displayed from left-to-right, and right-to-left characters are displayed with the first character of the text block beginning from the right.

Storage in memory or on disk generally occurs in a logical manner so that the left-to-right characters are stored left-to-right (that is, one after another), and require no processing to display properly. However, when right-to-left characters are stored in a logical manner, they are also stored one after another from left-to-right. These text blocks, when in Logical order, are usually enclosed by markers that identify the start and end positions of the right-to-left text blocks.

Logical to visual reordering

To display these logical sequences on a window would require that any left-to-right text is simply read and displayed. When right-to-left text is encountered, it must be turned around to the appropriate direction. This is logical-to-visual reordering.

Examples

In the following example, lowercase characters are considered left-to-right (LTR) and uppercase characters are considered right-to-left (RTL).

 Text=
 a
 b
 c
 F
 E
 D
 g
 h
 i

 Visual order
 0x61
 0x62
 0x63
 0x46
 0x45
 0x44
 0x67
 0x68
 0x69

 Logical or 0x61
 0x62
 0x63
 0x44
 0x45
 0x46
 0x67
 0x68
 0x69

 der

SETLOGICALORDER

Use this function to convert a bidirectional data object from visually ordered (characters ordered as they are presented for reading) to logically ordered (the order in which text is typed on a keyboard or phonetic order).

This function is only for use with text objects that have bidirectional properties. The function will have no affect on objects that have no bidirectional properties.

Syntax:

SETLOGICALORDER (single-text-expression, single-text-expression)

Meaning:

SETLOGICALORDER (visually_ordered_text_object , TRUE_or_FALSE_text_object)

Returns:

A logically ordered text object.

The SETLOGICALORDER function changes the order of the data as held in memory (order scheme) of a text object that is being passed as a parameter. The function returns a text object that reflects the order scheme change.

The output of the function will be the data from the original bidirectional item, transformed to match the specified layout (as it would be if it were assigned to a bidirectional item with the specified characteristics). This allows you to use text manipulation functions, such as LEFT or MID, on bidirectional data using the proper understanding of the bidirectional data. For example, LEFT of the logical ordering of a bidirectional item would actually take the rightmost characters of the visual ordering of that item.

Example

The properties of the text objects define the orientation and memory order of data objects found in the data stream.

Text objects defined as right-to-left would be considered as starting from the right character and progressing to the left, until the end of the data. However, the data can be held in memory with the start character (the right most character) being held in the left most position. This memory ordering is defined by the ordering scheme of the object.

SETORIENTATIONLTR

The SETORIENTATIONLTR function converts the orientation of a text object from right-to-left (RTL) to left-to-right (LTR).

Syntax:

SETORIENTATIONLTR (single-text-expression, Boolean-expression)

Meaning:

SETORIENTATIONLTR (right_to_left_oriented_text_object, true_or_false_text_object)

Returns:

A text object with left-to-right orientation.

The second parameter, a Boolean expression, indicates whether symmetric swapping should be applied.

Exemple

Example

SETORIENTATIONRTL(VLTRData:In1, "FALSE"))

SETORIENTATIONRTL

Use the SETORIENTATIONRTL function to convert the orientation of a text object from left-to-right (LTR) to right-to-left (RTL).

Syntax:

SETORIENTATIONRTL (left_to_right_oriented_text_object, true_false_text_object, TRUE_or_FALSE_text_object)

Meaning:

SETORIENTATIONRTL (XML fragment)

Returns:

A text object with right-to-left orientation.

Exemple

Example

SETORIENTATIONRTL (VLTRData:In1, "FALSE")

SETTEXTSHAPING

The SETTEXTSHAPING function converts a bidirectional text object from non-shaped to shaped.

Syntax:

SETTEXTSHAPING (single-text-expression)

Meaning:

SETTEXTSHAPING (unshaped_text_object)

Returns:

A shaped text object.

SETTEXTSHAPINGOFF

The SETTEXTSHAPINGOFF function removes the shaping from a bidirectional text object.

Syntax:

SETTEXTSHAPINGOFF (single-text-expression)

Meaning:

SETTEXTSHAPINGOFF (shaped_text_object)

Returns:

A text object with no shaping.

SETVISUALORDER

The SETVISUALORDER function converts a bidirectional data object from logically ordered to visually ordered.

This function can only be used with bidirectional data.

Syntax:

SETORDERVISUAL (single-text-expression, single_text_expression)

Meaning:

SETORDERVISUAL (text_object, text_object)

Returns:

A visually ordered text object.

When HCL® OneTest[™] Data processes bidirectional data, this function changes the order scheme of the text object that is passed as a parameter.

Exemple

Example

Exemple

SETVISUALORDER(SETORIENTATIONRTL(LSRTLData:In1,"FALSE"), "FALSE")

True or false indicates whether the text object has symmetric swapping enabled. A visual ordering scheme would have the data being read and stored with the start character in the rightmost position in both memory and visually.

Bit manipulation and testing functions

SETOFF

The SETOFF function sets to zero a specified bit in a binary number. You can use this function to manipulate (turn off) a bit in a binary number.

Syntax:

SETOFF (single-binary-number-expression, single-integer-expression)

Meaning:

SETOFF (binary_number_to_change, bit_to_turn_off)

Returns:

A single binary number

The SETOFF function uses *bit_to_turn_off* to specify the bit of *binary_number_to_change* to be set to the value 0. The result is a binary number item of the same size as *binary_number_to_change*.

The value of *bit_to_turn_off* represents the position of the single bit in *binary_number_to_change* to be set off. (Bits are numbered from left to right, with the leftmost bit being bit 1.) If *bit_to_turn_off* is less than one or greater than the number of bits of *binary_number_to_change*, SETOFF returns *binary_number_to_change* unchanged.

Examples

• SETOFF (A , 16)

Assume **A** is the two-byte binary value of "1" (which is all zeros except for bit **16**). The binary representation of the value in **A** is 0001.

The result is the two-byte binary value, "0"

• SETOFF (A, 38)

Results in the two-byte binary value "1", the original value of A, because bit 38 does not exist in A.

SETON

You can use the SETON function to "turn on" a specific bit in a binary number. SETON sets the specified bit in the number to "1".

Syntax:

SETON (single-binary-number-expression, single-integer-expression)

Meaning:

SETON (binary_number_to_change, bit_to_turn_on)

Returns:

A single binary number

SETON uses the value of *bit_to_turn_on* to specify the bit of *binary_number_to_change* that should be set to the value 1. The result is a binary number item of the same size as *binary_number_to_change*.

Bit_to_turn_on represents the position of the single bit in *binary_number_to_change* to be set on. (Bits are numbered from left to right, with the leftmost bit being bit 1.) If *bit_to_turn_on* is less than one or greater than the number of bits of *binary_number_to_change*, SETON returns *binary_number_to_change*, unchanged.

Examples

• SETON (A, 15)

In this example, assume **A** is the two-byte binary value of 1 (which is all zeros except for bit 16). The binary representation of the value in **A** is 0001.

The function returns the two-byte binary value, 0011, which is the decimal value of 3.

• SETON (A , 40)

Returns the two-byte binary value of 1-the original value of A- because bit 40 does not exist in A.

TESTOFF

The TESTOFF function tests a specified bit in a binary number item to see whether it is off.

Syntax:

TESTOFF (single-binary-number-expression, single-integer-expression)

Meaning:

TESTOFF (binary_number_to_test , bit_to_test)

Returns:

"True" or "false"

The value of *bit_to_test* specifies which bit of *binary_number_to_test* should be tested for the value 0. If *bit_to_test* has the value 1, it refers to the leftmost bit of *binary_number_to_test*.

The TESTOFF function returns "true" if the specified bit is off and returns "false" if the specified bit is on.

If bit_to_test is less than one or greater than the number of bits of binary_number_to_test, TESTOFF returns "false".

Examples

• TESTOFF (A, 16)

Assume **A** is the two-byte binary value of "1", which is all zeros except for bit **16**. The binary representation of the value in **A** is 0001.

This example returns "false".

• TESTOFF (A, 20)

Returns "false" because bit 20 does not exist.

TESTON

The TESTON function tests a specified bit in a binary number to see if it is on.

Syntax:

TESTON (single-binary-number-expression, single-integer-expression)

Meaning:

TESTON (binary_number_to_test ,bit_to_test)

Returns:

"True" or "false"

The value of *bit_to_test* specifies the bit of *binary_number_to_test* to test for the value 1. If *bit_to_test* has the value 1, it refers to the leftmost bit of *binary_number_to_test*.

The function returns "true" if the specified bit is on; it has the value 1. It returns "false" if the specified bit is off; it has the value 0.

If bit_to_test is less than one or greater than the number of bits of binary_number_to_test, TESTON returns "false".

Examples

• TESTON (A , 16)

Assume **A** is the two-byte binary value of "1", which is all zeros except for bit **16**. The binary representation of the value in **A** is 0001.

This example returns "true".

• TESTON (A , 20)

Returns "false" because bit 20 does not exist in a two-byte value.

Conversion functions

BASE64TOTEXT

Use the BASE64TOTEXT decoding function to convert previously encoded data from BASE64 back to the original text. The data is converted to the character set of the output object used. For example, if the output object is EBCDIC the output will be EBCDIC.

Syntax:

BASE64TOTEXT (single-object-expression)

Meaning:

BASE64TOTEXT (BASE64_object_to_convert)

Returns:

A single-text-item

This function receives a text object in Base64-encoded format, converts the object to text, and returns a single data object that represents the original text object that was encoded. If an error occurs during conversion, no data is returned.

Example

BASE64TOTEXT("U29tZSBFeGFtcGxllERhdGE=")

Output: Some Example Data

BCDTOHEX

The BCDTOHEX function converts an item from binary coded decimal (BCD) format to hexadecimal format. The binary value that is returned always has the high-order byte first, regardless of the operating system. This is useful for testing a specific bit position for a specific value.

Syntax:

BCDTOHEX (single-text-expression, single-integer-expression)

Meaning:

BCDTOHEX (BCD_item_to_convert, length_of_output)

Returns:

A single binary bytestream

When using the BCDTOHEX function, the input argument is converted from BCD format to its binary value.

Numbers in BCD format have two decimal digits in each byte. Each half-byte, therefore, can contain a binary value from 0000 (which represents the digit 0) through 1001 (which represents the digit 9). Based on this definition, the following behavior applies:

- If any half-byte of the BCD number contains the binary values 1101 or 1111, that half-byte is ignored.
- If any half-byte contains the binary values 1010, 1011, 1100, or 1110, the output of the function is "none".

The length of the output argument is specified as the value of the second input argument. The length must be 1, 2, or 4. If it is any other value, the length is assumed to be 2.

Examples

- You can use BCDTOHEX to test a specific bit position for a specific value. For example, BCDTOHEX is useful when the BCD value represents flag bits. The conversion performed by BCDTOHEX results in a predictable location for the flag bits across operating systems where the bytes might otherwise be reversed.
- TESTON (BCDTOHEX (ProcessIndicator, 2) 10)

Tests for the x`0040' bit in a two-byte result.



Note: This same test, using BCDTOINT on a PC, tests the x`4000' bit.

Related functions

- BCDTOTEXT
- BCDTOINT
- TEXTTOBCD

BCDTOINT

The BCDTOINT function converts an item from BCD (binary coded decimal) format to integer format. The binary value that is returned has a form native to the machine on which the map is being run.

Syntax:

BCDTOINT (single-text-expression, single-integer-expression)

Meaning:

BCDTOINT (BCD_item_to_convert , length_of_output)

Returns:

A single-binary-number

BCD_item_to_convert is converted from BCD (binary coded decimal) format to its integer value.

Numbers in BCD format have two decimal digits in each byte. Each half-byte, therefore, can contain a binary value from 0000 (which represents the digit 0) through 1001 (which represents the digit 9). Based on this definition, the following behavior applies:

- If any half-byte of the BCD number contains the binary values 1101 or 1111, that half-byte is ignored.
- If any half-byte contains the binary values 1010, 1011, 1100, or 1110, the output of the function is "none".

The length of the output binary number is specified by *length_of_output*. The length must be 1, 2, or 4. If it is any other value, the length is assumed to be 2.

BCDTOINT returns a binary value of the form native to the machine on which the map is being run. The value can therefore be used in arithmetic operations or compared to other numeric values. It should *not* be used for bit manipulations, because the order of the bytes in the number is dependent on the operating system on which the map is being run. For example, on a personal computer, the low-order byte is first, while on a mainframe, the high-order byte is first.

Examples

• BCDTOINT (bcdAmount Field, 2)

If the **bcdAmount Field** contains x'37' in BCD format, this example returns the integer value of 37.

Related functions

- BCDTOTEXT
- BCDTOHEX
- TEXTTOBCD

BCDTOTEXT

The BCDTOTEXT function converts the digits in a BCD (Binary Coded Decimal) item to a text item containing the digits of the BCD-encoded item as a string of characters.

Syntax:

BCDTOTEXT (single-text-expression)

Meaning:

BCDTOTEXT (BCD_item_to_convert)

Returns:

A single text item

BCD_item_to_convert is converted from BCD format to a text string containing the digits of the BCD-encoded value as a string of characters.

Numbers in BCD format have two decimal digits in each byte. Each half-byte, therefore, can contain a binary value from 0000 (which represents the digit 0) through 1001, which represents the digit 9). Based on this definition, the following behavior applies:

- If any half-byte of the BCD number contains the binary value 1101 or 1111, that half-byte is ignored.
- If the BCD item contains the binary value 1010, 1011, 1100, or 1110, the output of the function is "none".

Examples

• BCDTOTEXT (Qty:Item)

If Qty is x`1234', the result is 1234.

• BCDTOTEXT (DiscountAmt)

If DiscountAmt is x`0123', the result is 0123.

BCDTOTEXT (TotalDollars)

If Total is x`F123', the result is 123.

Related functions

- BCDTOHEX
- BCDTOINT
- TEXTTOBCD

CONVERT

The CONVERT function replaces each byte of a byte stream or text expression with a byte from another byte stream or text expression. The decimal value of each byte of the first argument is used to locate the corresponding byte in the second argument that will replace it.

Syntax:

CONVERT (single-byte-stream-or-text-expression , single-byte-stream-or-text-expression)

Meaning:

CONVERT (bytes_to_replace , replacement_bytes)

Returns:

A single byte stream or text item

The CONVERT function replaces each byte of *bytes_to_replace* with a byte from *replacement_bytes*. The byte chosen from *replacement_bytes* is the one whose index is the decimal value of *bytes_to_replace*. The first byte of *replacement_bytes* has the index value of zero. If there is no corresponding byte in *replacement_bytes*, CONVERT returns "none".

You can use the CONVERT function to convert ASCII to EBCDIC or EBCDIC to ASCII data. See the **convert.mms** map source file in the **examples\general\portdata** folder of the product installation directory. One of the maps in **convert.mms** is **ASCII_TO_EBCDIC**, which converts ASCII to EBCDIC. The **EBCDIC_TO_ASCII** map converts EBCDIC to ASCII.

ASCII to EBCDIC conversion can be performed automatically by defining the appropriate data language (ASCII or EBCDIC) for each data item.

Examples

• CONVERT (SYMBOL (0),"AB")

Returns A

CONVERT (SYMBOL (1),"AB")

Returns B

• CONVERT (SYMBOL (2),"AB")

Returns "none"

• CONVERT (ASCII, ATOETable)

Converts ASCII text to EBCDIC based on values in a table named ATOETable

DATETONUMBER

Use DATETONUMBER to perform arithmetic on dates.

The DATETONUMBER function returns an integer that results from counting the number of days from December 31, 1864, to the specified date.

Syntax:

DATETONUMBER (single-date-expression)

Meaning:

DATETONUMBER (date_to_convert)

Returns:

A single integer

The DATETONUMBER function converts a date to an integer. The resulting integer represents the number of days since December 31, 1864, where using DATETONUMBER with a date of January 1, 1865 returns the integer value 1.

If the input argument is in error, the function returns the value "none".

If the date format specified by the input argument does not include century, the century is determined based on the **Century** map setting using the **CCLookup** parameter or the current century.

Examples

• DaysBetween = DATETONUMBER (StopDate) - DATETONUMBER (StartDate)

This expression could be used in a map rule to produce a value for **DaysBetween**. It converts the **StopDate** and the **StartDate** to integers, then subtracts the resulting two integers, and returns the result as **DaysBetween**.

Related functions

- ADDDAYS
- NUMBERTODATE

DATETOTEXT

The DATETOTEXT function converts a date object or expression to a text item.

Syntax:

DATETOTEXT (single-date-expression)

Meaning:

```
DATETOTEXT (date_to_convert)
```

Returns:

A single text item

If *date_to_convert* is a date object name, this returns the date as a text item formatted according to the presentation of the date object.

If *date_to_convert* is a date expression produced by a function, this returns the date as a text item formatted according to the presentation of the output argument of that function.

Examples

• DATETOTEXT (ShipDate)

In this example, **ShipDate** is converted from a date to text. If **ShipDate** has a CCYYMMDD presentation, the resulting text item will have that presentation, as well.

DATETOTEXT (CURRENTDATETIME ("{MM/DD/CCYY}"))

In this example, CURRENTDATETIME evaluates and returns a date in MM/DD/CCYY format. Then DATETOTEXT evaluates and returns a text string that is that date in MM/DD/CCYY format.

For example, use DATETOTEXT, to do text concatenation. The FROMDATETIME function provides greater flexibility in specifying the format of the resulting text item.

Related Functions

- FROMDATETIME
- NUMBERTOTEXT
- TEXT
- TEXTTODATE
- TEXTTONUMBER
- TEXTTOTIME
- TIMETOTEXT
- TODATETIME

FROMBASETEN

You can use FROMBASETEN when you need to convert numbers to a base other than 10.

The FROMBASETEN function converts an integer to a text item that can be interpreted as a number, using positional notation of the base specified.

Syntax:

FROMBASETEN (single-integer-expression, single-integer-expression)

Meaning:

FROMBASETEN (positive_integer_to_convert, base_to_convert_to)

Returns:

A single text item

FROMBASETEN returns a text item that results from converting *positive_integer_to_convert* to a text item that can be interpreted as a number using positional notation of the base specified by *base_to_convert_to*.

If *base_to_convert_to* is less than 2 or greater than 36, FROMBASETEN evaluates to "none". Resulting text item characters A-Z are interpreted as digits having decimal values from 10-35, respectively. The characters returned are uppercase.

Example

• FROMBASETEN (18, 2)

Returns the value 10010

• FROMBASETEN (123, 8)

Returns the value 173

Related function

TOBASETEN

FROMDATETIME

The FROMDATETIME function converts a date/time item to a text string of a specified format. For example, you can use FROMDATETIME to convert a date-time item into a string for parsing or concatenation. You can also use this function to access the individual parts of a date or time, such as the month, day, year, and so forth.

Syntax:

FROMDATETIME (single-character-date-time-item [, single-text-expression])

Meaning:

FROMDATETIME (date_time [, date_time_format_string])

Returns:

A single character text item

FROMDATETIME returns the date/time specified by *date_time* as a text item with the format specified by *date_time_format_string*. If *date_time_format_string* is not specified, *date_time* will be returned in the same format as the *date_time*.

The date_time_format_string must conform to the date/time format strings as described in the "Format strings" topic.

Examples

• HeaderLine="Today is" + FROMDATETIME (CURRENTDATE (),"{MON DD, CCYY}")

If the current system date is March 3, 1999, this rule evaluates to Today is Mar 03, 1999.

• FROMDATETIME (TransactionTimeStamp Column:.:TransHistory)

If the value of **TransactionTimeStamp Column** is 10:14 A.M. on February 3, 2000 and its format is defined as "{CCYYMMDDHH24MM}", this rule evaluates to 200002031014.

• EXTRACT (Expense:Report, FROMDATETIME (Date:Expense:Report, "{MM}") = "03")

In this example, the FROMDATETIME function is used in the condition expression of the EXTRACT function to identify all expenses in the month of March.

Related functions

- CURRENTDATE
- CURRENTDATETIME
- CURRENTTIME
- DATETOTEXT
- TODATETIME

FROMNUMBER

The FROMNUMBER function converts a number to a text string of a specified format.

Use FROMNUMBER when you need to convert a number item into a string for parsing or concatenation.

Syntax:

FROMNUMBER (single-character-number-item

[, single-text-expression])

Meaning:

FROMNUMBER (number_to_convert [, number_format_string])

Returns:

A single character text item

FROMNUMBER returns the number specified by *number_to_convert* as a text item with the format specified by *number_format_string*. If *number_format_string* is not specified, *number_to_convert* will be returned in the same format as the *number_to_convert*.

The number_format_string must conform to the number format strings as described in the "Format strings" topic.

Examples

• Greeting = "You are caller number " + FROMNUMBER (SeqNo:.:History, "{#';###}") + "!"

If the value of SeqNo is 2348192, this rule evaluates to "You are caller number 2,348,192!"

• "\$" + FROMNUMBER(CurrentRate Field:.:Schedule, "{#', ###'.'2##2}")

If the value of CurrentRate Field is 15.875, "\$15.88".

Related functions

- DATETONUMBER
- NUMBERTODATE
- NUMBERTOTEXT
- TONUMBER

HEXTEXTTOSTREAM

HEXTEXTTOSTREAM is the reverse of STREAMTOHEXTEXT. You can use the HEXTEXTTOSTREAM function to assign a binary text value to a character text item represented by hexadecimal pairs.

HEXTEXTTOSTREAM returns a binary text stream whose value is the evaluation of input character text represented by hexadecimal pairs.

Syntax:

HEXTEXTTOSTREAM (single-text-expression)

Meaning:

HEXTEXTTOSTREAM (series_of_hex_pairs)

Returns:

A single byte stream item

This function returns a binary text stream item whose value is the evaluation of input character text in *series_of_hex_pairs*, ignoring <WSP> characters between the hexadecimal pairs. White space characters include space, horizontal tab, carriage return, and line feed characters.

Input formats

The following table shows an example of input in its character text representation as viewed through the character editor, and in its ASCII code representation (binary text stream) as viewed through the hex editor. Each pair of binary text in the hex view represents one character in the character view of the character text.

Input ("41 42 43 44")	Editor View	Value
Character text (hex pairs)	Character	"41 42 43 44"
ASCII code representation (binary text stream)	Hex	0x3431203432203433203434

Examples

• HEXTEXTTOSTREAM ("41 42 43 44")

Returns the evaluated value of the input (ASCII) character text string "41 42 43 44" as the output (ASCII) character text string "ABCD" as viewed in the character editor. (The hex view of the input is 0x3431203432203433203434. The hex view of the output is 0x41424344.)

• HEXTEXTTOSTREAM ("OD 0A 00")

Returns the evaluated value of the input (ASCII) character text string "0D 0A 00" as the output (ASCII) character text string "<CR><LF><NULL>" as viewed in the character editor. (The hex view of the input is 0x3044203041203030. The hex view of the output is 0x0D0A00.)

See Design Studio Introduction documentation for a list of special symbols.

Related functions

- SYMBOL
- STREAMTOHEXTEXT

INT

You can use the INT function when you need only the integer portion of a number.

Syntax:

INT (single-number-expression)

Meaning:

INT (number_to_convert)

Returns:

A single integer

INT returns the integer portion of a number. The result is the integer part of *number_to_convert*. Any fractional part after the decimal point is dropped.

Examples

• INT (1.45)

Returns 1

• INT (3.6)

Returns 3

INT (Purchase:Amt - Discount:Amt)

Subtracts Discount:Amt from Purchase:Amt and returns the result as a whole number.

Related functions

- MOD
- ROUND
- TRUNCATE

NUMBERTODATE

.

You can use the NUMBERTODATE function to perform a calculation on a date.

NUMBERTODATE converts an integer to a date, where the integer is the number of days from December 31, 1864, to the specified date. Only positive, non-zero values can be specified as valid parameters.

Syntax:

NUMBERTODATE (single-integer-expression)

Meaning:

NUMBERTODATE (integer_to_convert)

Returns:

A single date

After converting an integer to a date, if the result is being assigned to a date object, the resulting date is in the presentation for that output. If the resulting date is not being assigned to an object, it has a CCYYMMDD presentation.

When the year exceeds four digits, the output will display hash characters (#) for the CCYY values because the field is defined to be only four digits in length.

Examples

NUMBERTODATE (StartDate)

This example converts the StartDate value from an integer to a date that is in CCYYMMDD format.

Related functions

- ADDDAYS
- DATETONUMBER
- FROMDATETIME
- TODATETIME

NUMBERTOTEXT

The NUMBERTOTEXT function converts a character number to a text item that looks like the original object.

You can use NUMBERTOTEXT when you need an object that is defined as a number converted to an object defined as text. This is useful when you need to concatenate text, however, the FROMNUMBER function provides greater flexibility in specifying the format of the resulting text item.

Syntax:

NUMBERTOTEXT (single-number-expression)

Meaning:

NUMBERTOTEXT (number_to_convert)

Returns:

A single text item

The resulting text looks like the input argument. The result is truncated, if necessary.

Examples

• NUMBERTOTEXT (ROUND (1000 - 24.75, 3))

This example converts the result of the calculation (rounded to 3 decimal places) to text, resulting in 975.250.

NUMBERTOTEXT (PurchaseNumber)

This example converts PurchaseNumber from a number to text.

Related functions

- FROMNUMBER
- TEXTTONUMBER
- TODATETIME
- TONUMBER

PACK

The PACK function converts an integer to a text item that can be interpreted as a packed decimal number.

The sign values for packed data are as follows:

- C for positive (+)
- D for negative (-)
- F for unsigned, which is read as positive

Syntax:

PACK (single-integer-expression)

Meaning:

PACK (integer_to_conver)

Returns:

A single text item

In a packed decimal number, each half-byte is a digit, except for the last half-byte of the rightmost byte, which contains a sign.

Examples

• PACK (314)

Returns "1L" and results in the hex value 31 4C (which, in ASCII, looks like 1L)

• PACK ((Unit Price * Quantity) * 100)

In this example, the packed number has two implied decimal places. Because PACK does not accept decimal places, including implied ones, the nested arithmetic expression, **Unit Price * Quantity**, is multiplied by 100 before rounding.

Define items as having a packed decimal number presentation. Then, when mapping to or from these items, the conversion to and from packed decimal is automatically performed as needed.

Related function

• UNPACK

PACKAGE

The PACKAGE function converts a group or item object to a text item, including its initiator, terminator, and any delimiters it contains.

Syntax:

PACKAGE (single-object-expression)

Meaning:

PACKAGE (object_to_convert)

Returns:

A single text item

The PACKAGE function converts *object_to_convert*, which must be a type reference to a text item, including the type reference's initiator, terminator, and all delimiters. PACKAGE differs from TEXT in that it includes the initiator and terminator of the specified type reference.

Examples

PACKAGE (Record:Card)

Returns: #1339X10A,491.38,Green,42x54@

For this example, the group **Record** has an initiator of "#", a terminator of "@" and a delimiter of ",". The data looks like this: "#1339X10A,491.38,Green,42x54@".

Related functions

- DATETOTEXT
- NUMBERTOTEXT
- SERIESTOTEXT
- TIMETOTEXT

• TEXT

PACKAGE differs from TEXT because it includes the initiator and terminator of the input object.

QUOTEDTOTEXT

The QUOTEDTOTEXT decoding function converts a single (text or binary) data object in Quoted-Printable format to a single data object that represents the original text or binary object.

Syntax:

QUOTEDTOTEXT (single-object-expression)

Meaning:

QUOTEDTOTEXT (quoted_printable_object_to_convert)

Returns:

A single-text-item

You can use this function to decode data that was previously encoded to RFC 1767 Quoted-Printable encoding. Any hexadecimal representations are decoded to the appropriate ASCII character and any soft breaks are removed.

If an error occurs during conversion, no data is returned.

Example

QUOTEDTOTEXT("Unencoded data=0CEncoded")

Output: Unencoded data<FF>Encoded

SERIESTOTEXT

You can use the SERIESTOTEXT function to project your input data as a series and to interpret it as a text item for output.

SERIESTOTEXT converts a contiguous or non-contiguous series to a text item.

Syntax:

SERIESTOTEXT (series-object-expression)

Meaning:

SERIESTOTEXT (series_to_convert)

Returns:

A single text item

SERIESTOTEXT returns a text item containing the concatenation of the series of the input argument, including nested delimiters but excluding initiators and terminators.

Examples

In this example, you have the following data that represents bowler information for a bowling league:

Andrews, Jessica:980206:JBC:145:138:177:159

Little, Randy:980116:BBK:175:168

Wayne, Richard:980102:JBC:185:204:179:164:212

Each record consists of the bowler's name, the date of their last game played, a team code and one or more bowling scores. **Record** is defined as a group that is infix-delimited by a colon.

Using the rule:

= SERIESTOTEXT (Score Field:Bowler:Input)

the following results are produced, which is the concatenation of all of the scores for all of the bowlers, even though the scores are not all contiguous within the data:

145138177159175168185204179164212

However, if the rule was changed, for instance, to concatenate the list of scores to the bowler's name:

= BowlerName Field:Bowler:Input + " ->" + SERIESTOTEXT (Score Field:Bowler:Input)

the following output would be produced:

Andrews, Jessica -> 145138177159

Little, Randy -> 175168

Wayne, Richard -> 185204179164212

In this example, you have an input number that is of variable size, followed by a name. There is no syntax that separates the number from the name. You can define the number as a group with **Byte(s)** as a component and provide a component rule for **Byte(s)**, such as:

ISNUMBER (\$)

Related functions

- PACKAGE
- TEXT

STREAMTOHEXTEXT

Use STREAMTOHEXTEXT to assign a character text value to a binary text stream item.

The STREAMTOHEXTEXT function returns a character text string represented by hex pairs whose value is the evaluation of an input binary text stream.

This function is the reverse of the HEXTEXTTOSTREAM function.

Syntax:

STREAMTOHEXTEXT (single-byte-stream-item)

Meaning:

STREAMTOHEXTEXT (single-byte-stream-item)

Returns:

A series of hex pairs

STREAMTOHEXTEXT returns a string of hex pairs whose value is the evaluation of input binary text in series_of_hex_pairs.

Input formats

The following table shows an example of input in its ASCII code representation (binary text stream) as viewed through the hex editor, and in its character text representation as viewed through the character editor. Each four-character grouping of binary text in the hex view represents one character in the character view.

Input (0x41424344)	Editor View	Value
ASCII code representation (binary text stream)	Hex	0x41424344
	Character	"ABCD"

Examples

STREAMTOHEXTEXT (0x41424344)

Returns the evaluated value of the input (ASCII) binary text stream **0x41424344** as the output (ASCII) binary text stream 0x3431343234333434 as viewed in the hex editor. (The character view of the input is "ABCD". The character view of the output is "41424344".)

STREAMTOHEXTEXT (0x0D0A00)

Returns the evaluated value of the input binary text stream **0x0D0A00** as the output 0x304430413030 as viewed in the hex editor. (The character view of the input is "<CR><LF><NULL>". The character view of the output is "0D0A00".)

- HEXTEXTTOSTREAM
- SYMBOL

SYMBOL

You can use SYMBOL to include a symbol in your output.

The SYMBOL function returns a one-byte character that is the ASCII character equivalent of a specified decimal value.

Syntax:

SYMBOL (single-integer-expression)

Meaning:

SYMBOL (decimal_value)

Returns:

A single one-byte text item

The value of the resulting item is the ASCII character equivalent of *decimal_value*. Valid input values are 0 to 255. Values outside of this range return "none".

A listing of decimal values (0-127) and their ASCII character equivalents is included in the Design Studio Introduction documentation.

Examples

• SYMBOL(13)

Produces a carriage return

• SYMBOL (13) + SYMBOL (10)

Produces a carriage return/linefeed

You can accomplish the same result using the angle-brackets around the decimal value. For example, the second example above would be equivalent to <CR><LF> or <<0D>><<0A>>

Related functions

- HEXTEXTTOSTREAM
- STREAMTOHEXTEXT

TEXTTOBASE64

The TEXTTOBASE64 encoding function converts a text item to Base64 format.

Syntax:

TEXTTOBASE64 (single-object-expression)

Meaning:

TEXTTOBASE64 (text_object_to_convert)

Returns:

A single-text-item

The TEXTTOBASE64 function receives a text object and uses the MIME implementation to convert the text to Base64 format. The MIME implementation adds the <CR><LF> character sequence after every 76 bytes and also at the end of the output string.

TEXTTOBASE64 returns a single data object that represents the Base64 encoding of the original text object. If an error occurs during conversion, no data is returned.

Example

TEXTTOBASE64("Some Example Data")

Output: U29tZSBFeGFtcGxlIERhdGE=

TEXTTOBCD

The TEXTTOBCD function converts a text item from decimal digits to BCD (Binary Coded Decimal) format.

Syntax:

TEXTTOBCD (single-integer-text-expression)

Meaning:

TEXTTOBCD (text_to_be_converted)

Returns:

A single BCD-formatted text item

TEXTTOBCD converts *text_to_be_converted* (which consists of decimal digits) to BCD format. In this format, each byte contains two decimal digits represented as binary numbers. If there is an odd number of decimal digits in the input, the high-order half-byte of the leftmost output byte will contain the decimal value 15 (hex "F").

If anything other than a decimal digit is encountered in the input, TEXTTOBCD returns "none".

Examples

• TEXTTOBCD ("1234")

Returns the hexadecimal value x'1234'

• TEXTTOBCD ("123A")

Returns "none"

• TEXTTOBCD ("123")

Returns the hexadecimal value x'F123'

In this example, the values shown as input ("123") are meant to represent character items in the native character set to the machine on which the map is running. On a personal computer, "123" would contain the ASCII characters for the digits that have the hexadecimal values "31", "32", and "33". The output, described as "the hexadecimal value `F123''', consists of the two binary bytes "F1" and "23".

On an IBM mainframe the input string would contain EBCDIC characters for the digits that have the hexadecimal values "F1", "F2", "F3", \hat{A}^{o} , but the output would be the same as the personal computer output.

Related functions

- BCDTOHEX
- BCDTOINT
- BCDTOTEXT

TEXTTODATE

The TEXTTODATE function converts text item from CCYYMMDD or YYMMDD format to a date.

You can use the TEXTTODATE to convert a text item to a date, however, the TODATETIME function provides greater flexibility for specifying the resulting date-time format.

Syntax:

TEXTTODATE (single-text-expression)

Meaning:

TEXTTODATE (text_to_convert_to_date)

Returns:

A single date

The text_to_convert_to_date must be in either CCYYMMDD or YYMMDD format. If the text_to_convert_to_date is in error (for example, it is not a valid date), the result is "none".

If text_to_convert_to_date is in YYMMDD format and is being assigned to a date format that includes a century, the century is determined based on the century run option setting using the **CCLookup** parameter or the current century.

Examples

```
• TEXTTODATE ( "990114" )
```

Returns a single date item with the value of January 14 in the year 99

• TEXTTODATE (OrderDate)

Returns OrderDate as a single date item.

Related functions

• DATETOTEXT	TEXTTOTIME
• NUMBERTO- TEXT	• TIMETOTEXT
• TEXTTONUM- BER	• TO- DATETIME

TEXTTONUMBER

Use TEXTTONUMBER to convert text to a number.

The TONUMBER function provides greater flexibility for specifying the format of the text item that is to be converted to a number.

Syntax:

TEXTTONUMBER (single-text-expression)

Meaning:

TEXTTONUMBER (text_to_convert_to_number)

Returns:

A single character number

The text_to_convert_to_number must be in integer or ANSI-formatted (floating point) presentation. The resulting number looks like the input argument, however, nonsignificant zeroes to the right of the decimal separator will be truncated. If the input argument is in error (for example, it is not a recognizable as a valid number), the result is "none".

When specified as in ANSI-formatted presentation, the text string must meet the following requirements:

- The decimal point can be a period, a comma, or "none".
- The leading sign can be a plus sign, a minus sign, or "none".
- No thousands separator is allowed.

Examples

TEXTTONUMBER (OrderQty)

Returns OrderQty as a character number item

Related functions

- DATETOTEXT
- FROMNUMBER
- NUMBERTOTEXT
- TEXTTODATE
- TEXTTOTIME
- TIMETOTEXT

TEXTTOQUOTED

The TEXTTOQUOTED encoding function converts a text or binary item to Quoted-Printable format.

Syntax:

TEXTTOQUOTED (single_object_expression)

Meaning:

TEXTTOQUOTED (object_to_convert)

Returns:

A single text or binary item

You can use this function to encode data that largely consists of octets that correspond to printable characters in the US-ASCII character set. It encodes the data in such a way that the resulting octets are unlikely to be modified by mail transport.

Quoted-Printable lines cannot be longer than 76 characters. Data with lines greater than 76 characters are broken up and indicated with soft breaks of "=<CR><LF>".

If an error occurs during conversion, no data is returned.

Example

This example converts the <FF> (form feed) character, into a hexadecimal representation, and indicates the end of data with a soft break.

TEXTTOQUOTED("Unencoded data<FF>Encoded")

Output: Unencoded data=0CEncoded=

The data is converted using the Quoted-Printable encoding as per RFC 1767.

TEXTTOTIME

Use TEXTTOTIME when you want to convert an object defined as text that is in HHMM or HHMMSS presentation, to an item defined as time. For greater flexibility, use the TODATETIME function for specifying the format of the text item that is to be converted to a date/time.

Syntax:

TEXTTOTIME (single-text-expression)

Meaning:

TEXTTOTIME (text_to_convert_to_time)

Returns:

A single time

The text_to_convert_to_time must be in HHMM or HHMMSS presentation. HH is a two-digit hour in a 24-hour format. If the result is being assigned to a time object, the resulting time looks like the output object. Otherwise, the resulting time looks like the input argument. If the input argument is in error (for example, it is not a valid time), the result is "none".

Examples

• TEXTTOTIME (CallTime)

Returns CallTime as a time item

Related functions

• DATETOTEXT	• TEXTTONUM- BER
• FROMDATETIME	• TIMETOTEXT
• NUMBERTO- TEXT	• TODATETIME

TEXTTODATE

TIMETOTEXT

You can use the TIMETOTEXT function to perform text concatenation. For greater flexibility, use the FROMDATETIME function for specifying the format of the resulting text item.

TIMETOTEX converts a time object or expression to a text item.

Syntax:

```
TIMETOTEXT ( single-time-expression )
```

Meaning:

TIMETOTEXT (time_to_convert_to_text)

Returns:

A single text item

If *time_to_convert_to_text* is a time object name, this returns the time as a text item formatted according to the presentation of the input date object.

If *time_to_convert_to_text* is a time expression produced by a function, this returns the time as a text item formatted according to the presentation of the output argument of that function.

Examples

• TIMETOTEXT (LeadTime)

In this example, **LeadTime** is converted from a time to text. If **LeadTime** has an HH:MM presentation, the resulting text item will be of that presentation.

• TIMETOTEXT (CURRENTDATETIME ("{HH:MM:SS}"))

Here, CURRENTDATETIME evaluates and returns a time in HH:MM:SS format. Then, TIMETOTEXT evaluates and returns a text string that is that time in HH:MM:SS format.

Related functions

- DATETOTEXT
- FROMDATETIME
- NUMBERTOTEXT
- TEXTTODATE
- TEXTTONUMBER
- TEXTTOTIME
- TODATETIME

TOBASETEN

The TOBASETEN function converts a text item that can be interpreted as a number, using positional notation of the base specified, to a base 10 number.

Syntax:

TOBASETEN (single-text-expression, single-integer-expression)

Meaning:

TOBASETEN (text_to_convert, base_to_convert_from)

Returns:

A single integer

TOBASETEN returns a number that results from converting *text_to_convert* that can be interpreted as a number, using positional notation of the base specified by *base_to_convert_from*, to its base 10 representation. Text item characters A-Z are interpreted as digits having decimal values from 10-35, respectively.

If base_to_convert_from is less than 2 or greater than 36, TOBASETEN evaluates to "none". If text_to_convert contains a character that is not alphanumeric or is not in the range specified by base_to_convert_from, TOBASETEN returns "none".

Examples

• TOBASETEN ("A", 16)

Returns the value 10

• TOBASETEN ("10", 36)

Returns the value 36

• TOBASETEN ("A0", 15)

Returns the value 150

• TOBASETEN ("A0", 5)

Returns the value "none"

Related functions

FROMBASETEN

TODATETIME

The TODATETIME function converts a text string of a specified format to a date-time item.

Syntax:

TODATETIME (single-character-text-expression

[, single-text-expression])

Meaning:

TODATETIME (text_to_convert [, date_time_format_string])

Returns:

A single character date item

TODATETIME returns the date-time that corresponds to the value specified by *text_to_convert*, which is in the format specified by *date_time_format_string*. If *date_time_format_string* is not specified, it will be assumed that *text_to_convert is* in [CCYYMMDDHH24MMSS] format.

The date_time_format_string must conform to the date-time format strings as described in "Format strings".

Examples

• TODATETIME ("05/14/1999@10:14pm" , "{MM/DD/CCYY}@{HH12:MMAM/PM}")

In this example, a text string containing a date and time is converted to a date-time item.

• RptDate = TODATETIME (RIGHT (GETRESOURCENAME() , 8) , "CCYYMMDD")

Assume that you receive a file that contains historical data. The name of the file identifies the date of the historical data. For example, a filename of **19960424** indicates that the data was produced on April 24, 1996. To map this date to **RptDate**, the TODATETIME function could be used with the RIGHT and GETRESOURCENAME functions.

Related functions

- CURRENTDATE
- CURRENTDATETIME
- CURRENTTIME
- TEXTTODATE
- TEXTTOTIME

TONUMBER

The TONUMBER function converts a text string of a specified format to a number.

Syntax:

TONUMBER (single-character-text-expression

[, single-text-expression])

Meaning:

TONUMBER (text_to_convert [, number_format_string])

Returns:

A single character number item

TONUMBER returns the number that corresponds to the value specified by *text_to_convert*, which is in the format specified by *number_format_string*. If *number_format_string* is not specified, it will be assumed that *text_to_convert* is in ANSI decimal format (for example, "{L-####['.'##]}").

The number_format_string must conform to the number format strings as described in the "Format strings" topic.

Examples

TONUMBER(text_to_convert, "{L+'\$'#',###}")

L+'\$' indicates the leading dollar sign is positive. That leading sign and the comma separators are removed when the text is converted to a number.

Input String: \$123,000,000

Output: 123000000

TONUMBER(text_to_convert, "{####T-}")

Four number signs are required for each whole number, regardless of the actual number of digits in the number.

Input string:	Output:	Note:
12345-	-12345	The output becomes a negative number.
67890	67890	No change occurs.
345-	-345	The output becomes a negative number.

TONUMBER(text_to_convert, "{####T+'K'-}")

If an invalid character, such as an X, is encountered, nothing is returned.

If a K is encountered, it is treated as a positive indicator.

Input string:	Output:	Note:
11212-	-11212	The output becomes a negative number.
67890X		The X is an invalid character. No number is returned.
54354	54354	No change occurs.
34567K	34567	The K is recognized as a positive sign. The character is re- moved and the number is returned as a positive.
345-	-345	The output becomes a negative number.

TONUMBER(text_to_convert, "{L-'('#', ###T-')'}")

The parentheses indicating a negative number are removed and replaced with a negative sign.

Comma separators are removed when the text is converted to a number.

Input string:	Output:	Note:
(12,345)	-12345	The output becomes a negative number. The comma sepa- rator is removed.
67,890	67890	The comma separator is removed.
(345)	-345	The output becomes a negative number.

• TONUMBER(text_to_convert, "{#[',']###['.'##5]T+'K'-}")

The optional comma separators are removed, but the decimal points and decimal values are retained.

Input string:	Output:	Note:
54,345.098	54354.098	The comma separator is removed.
67890.0X		The X is an invalid character. No number is returned.
11213-	-11213	The output becomes a negative number.
34567K	34567	The K is recognized as a positive sign. The character is removed and the number is returned as a positive.
345.1-	-345.1	The output becomes a negative number.

Related functions

- DATETONUMBER
- FROMNUMBER
- NUMBERTODATE
- NUMBERTOTEXT

UNPACK

You can use the UNPACK function to do arithmetic with a packed decimal number or to move a packed decimal value into a numeric item.

UNPACK converts text that can be interpreted as a packed decimal number to a signed integer item.

The sign values for packed data are as follows:

- C for positive (+)
- D for negative (-)
- F for unsigned, which is read as positive

Syntax:

UNPACK (single-fixed-size-text-expression)

Meaning:

UNPACK (text_to_unpack)

Returns:

A single signed integer

UNPACK returns a signed integer representing the value *text_to_unpack*, which is a packed decimal number. If the *text_to_unpack* cannot be interpreted as a valid packed decimal, UNPACK evaluates to "none".

In a packed decimal number, each half-byte is a digit, except for the last half-byte of the rightmost byte, which contains a sign.

Examples

• UNPACK ("1L") returns 314

The ASCII string "1L" in hex is 31 4C, which, when interpreted as a packed number, results in (positive) 314. This example returns the value "+314".

The hexadecimal representation of the value "1L" is x`14C', where C in the rightmost half-byte represents a positive sign.

• UNPACK (UnitPrice) / 100 * QuantityOrdered

UnitPrice is unpacked and divided by 100 (to convert it from an integer to a number with two decimal places) and then multiplied by the *QuantityOrdered*.

You can define items as having a packed decimal number presentation. Then, when mapping to or from these items, the conversion to and from packed decimal is automatically performed as needed.

Related functions

• PACK

UNZONE

You can use the UNZONE function to convert a text item that represents a zoned (signed) number to an integer.

UNZONE converts a text item that can be interpreted as a number with a super-imposed sign in the rightmost byte (called zoned or signed data) to a signed integer item.

Syntax:

```
UNZONE (single-text-expression)
```

Meaning:

```
UNZONE (text_to_unzone)
```

Returns:

A single integer

UNZONE returns a signed integer representing the value *text_to_unzone* that is an integer in zoned (signed) format. If the *text_to_unzone* cannot be interpreted as a valid zoned number, UNZONE evaluates to "none".

Zoned integers have a series of digits except for the rightmost byte. The rightmost byte is a digit with a superimposed sign. See "Positive zoned values" for a list of rightmost byte values.

Examples

• UNZONE ("123D")

Returns 1234

• UNZONE ("1234")

Returns 1234

UNZONE (TaxRate) / 1000 * Income

TaxRate is converted from zoned format to a signed decimal and divided by 1000 (to convert it to a number with three decimal places), and then multiplied by **Income**.

You can define items as having a zoned character number presentation. Then, when mapping to or from these items, the conversion to and from zoned decimal is automatically performed as needed.

Related functions

• ZONE

ZONE

Use ZONE to convert a number to a zoned (signed) number.

The ZONE function converts a signed integer item to a text item that can be interpreted as a number with a superimposed sign in the rightmost byte (called zoned or signed).

You can define items as having a zoned character number presentation. Then, when mapping to or from these items, the conversion to and from zoned decimal is performed automatically, as needed.

Syntax:

ZONE (single-integer-expression, single-integer-expression)

Meaning:

ZONE (integer_to_convert , sign_indicator)

Returns:

A single text item

ZONE returns a text string that represents a zoned (signed) number representing integer_to_convert.

Zoned integers have a sequence of digits except for the rightmost byte. The rightmost byte is a digit with a superimposed sign. The *sign_indicator* specifies whether a super-imposed sign is required for positive integers, where 0 specifies no sign is required and any other value specifies that a sign is required for positive integers. The following tables show positive and negative values of the numbers 1230 to 1239, with a sign indicator of 0 (no sign is required for positive values) or a sign of 1 (include a sign for both positive and negative values) in the rightmost byte.

Table 19. Positive Zoned Values

Integer Value	sign_indicator = 0	sign_indicator = 1
1230	1230	123{
1231	1231	123A
1232	1232	123B
1233	1233	123C
1234	1234	123D
1235	1235	123E
1236	1236	123F
1237	1237	123G
1238	1238	123H
1239	1239	1231

Table 20. Negative Zoned Values

Integer Value	sign_indicator = 0	sign_indicator = 1
-1230	123}	123}
-1231	123J	123J
-1232	123K	123K
-1233	123L	123L
-1234	123M	123M
-1235	123N	123N
-1236	1230	1230
-1237	123P	123P
-1238	123Q	123Q
-1239	123R	123R

Examples

• ZONE (1234,0)

Returns 1234

• ZONE (1234,1)

Returns 123D

• ZONE (-1234,1)

Returns 123M

• ZONE (INT (UnitPrice * 100) , 1)

UnitPrice is multiplied by 100 to move the first two decimal places to the left of the decimal sign. The result of this calculation is converted to an integer using the INT function. Finally, the result of the INT is converted to zoned format, using a sign for positive values.

Related function

• UNZONE

Date/time functions

ADDDAYS

The ADDDAYS function adds a specified number of days to a given date.

You cannot use ADDDAYS on a date/time object that does not specify the day of the month because an error will occur.

Syntax:

ADDDAYS (single-date-expression, single-integer-expression)

Meaning:

ADDDAYS (any_date, number_of_days_to_add)

Returns:

A single date

The ADDDAYS function returns the date, which results from adding *number_of_days_to_add* to *any_date*. If *any_date* has a presentation that does not contain a century, the century is determined based on the Century > CCLookup map setting (when the Century > Switch = ON), or the current century (when the Century > Switch = OFF).

When the year exceeds four digits, the output will display hash characters (#) for the CCYY values because the field is defined to be only four digits in length.

Examples

• You can use the ADDDAYS function to increment a date by a fixed number of days, such as to calculate a **DueDate** that is always 30 days after the **InvoiceDate**.

To produce a date in the output, such as a ship date, you might need to add a variable number of days to a date in the input. For example: ADDDAYS (PODate, LeadTime).

ADDDAYS (InvoiceDate, 10)

Returns the date, which results from adding 10 days to the value of InvoiceDate.

ADDDAYS (InvoiceDate, DaysTilDue)

Returns the date that results from adding the value of DaysTilDue to the InvoiceDate value.

• ADDDAYS (TODATETIME ("000101"), -1)

Returns 991231

• ADDDAYS (TODATETIME ("20000101"), 1)

Returns 20000102

• ADDDAYS (TODATETIME ("10/20/1996", "{MM/DD/CCYY}"), 5)

Returns 10/25/1996

In the examples containing TODATETIME, the text literal is first converted to a date, and then the specified number of days is added to that date.

Related functions

- ADDHOURS
- DATETONUMBER
- NUMBERTODATE
- TEXTTODATE
- TODATETIME

ADDHOURS

The ADDHOURS function returns a time value that is the result of adding a specified number of hours to a given time.

Syntax:

ADDHOURS (single-datetime-item-expression, hours-expressed-as-signed-integer-expression)

Meaning:

ADDHOURS (any_datetime, number_of_hours_to_add)

Returns:

A single datetime item

The ADDHOURS function returns a single datetime item that is advanced from the original value of the singledatetime-item-expression by the specified number of hours-expressed-as-signed-integer-expression.

Examples

• ADDHOURS(TODATETIME("Dec 31, 1999 23:59:00"), 2)

Returns: Jan 1, 2000 01:59:00

• ADDHOURS(TODATETIME("Dec 31, 1999 23:59:00"), -25)

Returns: Dec 30, 1999 22:59:00

• ADDHOURS(TODATETIME("23:59:00"), 2)

Returns: 01:59:00

If either argument is invalid, the result is "none". If the second argument is "none", the result is the first argument. If the first argument contains only a time portion, date changes are ignored. If the first argument contains only a date portion, the time portion 00:00:00 will be used in the calculation. If both arguments are "none", the result is "none".

Related functions

- ADDDAYS
- DATETONUMBER
- NUMBERTODATE
- TEXTTODATE
- TODATETIME

ADDMINUTES

The ADDMINUTES function returns a time value that is the result of adding a specified number of minutes to a given time.

Syntax:

ADDMINUTES (single-datetime-item-expression, minutes-expressed-as-signed-integer-expression)

Meaning:

ADDMINUTES (any_datetime, number_of_minutes_to_add)

Returns:

A single datetime item

The ADDMINUTES function returns a single datetime item, advanced from the original value of the single-datetimeitem-expression by the specified number of minutes-expressed-as-signed-integer-expression.

Examples

• ADDMINUTES(TODATETIME("Dec 31, 1999 23:59:00"), 2)

Returns: Jan 1, 2000 00:01:00

• ADDMINUTES(TODATETIME("Dec 31, 1999 23:59:00"), -25)

Returns: Dec 31, 1999 23:34:00

• ADDMINUTES(TODATETIME("23:59:00"), 2)

Returns: 00:01:00

If either argument is invalid, the result is "none". If the second argument is "none", the result is the first argument. If the first argument contains only a time portion, date changes are ignored. If the first argument contains only a date portion, the time portion 00:00:00 will be used in the calculation. If both arguments are "none", the result is "none".

Related Functions

- DATETONUMBER
- NUMBERTODATE
- TEXTTODATE
- TODATETIME

CURRENTDATE

You can use CURRENTDATE when you need the current date as a transaction processing date, an order received date, or other date that reflects when the data was mapped.

When you need to parse the system date, use CURRENTDATE with the TEXT or FROMDATETIME functions. The function returns the current system date.

Syntax:

```
CURRENTDATE()
```

Meaning:

```
CURRENTDATE ()
```

Returns:

A single date

CURRENTDATE has no arguments but it does require parentheses.

If being assigned to a date/time output item, the current date is returned in the format specified by that output item. Otherwise, the system date is returned in an MM/DD/YY presentation.

Examples

• StartDate = CURRENTDATE()

In this example, **StartDate** is assigned the value of the current **date**. In this example, because CURRENTDATE is assigned to an output, it is automatically converted to the presentation of **StartDate**.

If CURRENTDATE evaluates to 06/24/37 and StartDate has a YYMMDD presentation, the result is 370624.

• FROMDATETIME (CURRENTDATE (), "DD.MON.CCYY")

In this example, the current date is returned in DD.MON.CCYY format. If today's date is January 5, 1999, the date returned would be 05.JAN.1999.

Related functions

- CURRENTDATETIME
- CURRENTTIME
- FROMDATETIME
- DATETOTEXT

CURRENTDATETIME

CURRENTDATETIME returns the current system date and time. You can use this function when you need to map the current system date and time to an item that includes both a date and time portion.

Syntax:

```
CURRENTDATETIME ([single-text-expression])
```

Meaning:

```
CURRENTDATETIME ([date_time_format_string])
```

Returns:

A single date-time

CURRENTDATETIME has no arguments but it does require parentheses.

The CURRENTDATETIME function returns the system date and time in the format specified by *date_time_format_string* or with a CCYYMMDDHHMMSS presentation if no *date_time_format_string* is provided.

The date_time_format_string must conform to the date/time format strings as described in "Format strings".



Note: The output format for the native schema XML date/time field is always:

{CCYY-MM-DD}T{HH24:MM:SS.3-3+/-ZZ:ZZ}



To specify a different output format, use Xerces XML instead.

Examples

StartDateTime = CURRENTDATETIME ()

In this example, **StartDateTime** is assigned the value of the current date and time. Because CURRENTDATETIME is assigned to an output, it is automatically converted to the presentation of **StartDateTime**.

If CURRENTDATETIME evaluates to 3:04pm on 6/24/1999 and **StartDateTime** has a YYMMDDHH12MM presentation, the result is 9906240304.

• CURRENTDATETIME ("{MM.DD.CCYY HH24:MM}")

In this example, the current date is returned in MM.DD.CCYY HH24:MM format. If it is currently 4:12 pm on January 5, 1999, the date returned would be 01.05.1999 16:12.

Related Functions

- CURRENTDATE
- CURRENTTIME
- FROMDATETIME
- DATETOTEXT

CURRENTTIME

The CURRENTTIME function returns the current system time.

You can use CURRENTTIME when you need the system time as a transaction processing time, an order-received time, or a time that reflects when the data was mapped.

Syntax:

```
CURRENTTIME ()
```

Meaning:

```
CURRENTTIME ()
```

Returns:

A single time

The CURRENTTIME function returns the system time. If assigned to a date-time output item, the current time is returned in the format specified by that output item. Otherwise, the system time is returned in HH:MM:SS presentation.

Note: CURRENTTIME has no arguments but it does require parentheses.

Examples

• End Time = CURRENTTIME()

In this example, **End Time** is assigned the current time. Because CURRENTTIME is assigned to an output, it is automatically converted to the presentation of **End Time**.

If CURRENTTIME evaluates to 10:15:02 and End Time has an HH12:MM presentation, the result is 1015.

• FROMDATETIME (CURRENTTIME (), "{HH24MMSS}")

In this example, the current time is returned in HH24MMSS format. If the current time is 10:15:02 pm, the result is 221502.

Related functions

- CURRENTDATETIME
- FROMDATETIME
- DATETOTEXT

DATETONUMBER

Use DATETONUMBER to perform arithmetic on dates.

The DATETONUMBER function returns an integer that results from counting the number of days from December 31, 1864, to the specified date.

Syntax:

DATETONUMBER (single-date-expression)

Meaning:

DATETONUMBER (date_to_convert)

Returns:

A single integer

The DATETONUMBER function converts a date to an integer. The resulting integer represents the number of days since December 31, 1864, where using DATETONUMBER with a date of January 1, 1865 returns the integer value 1.

If the input argument is in error, the function returns the value "none".

If the date format specified by the input argument does not include century, the century is determined based on the **Century** map setting using the **CCLookup** parameter or the current century.

Examples

• DaysBetween = DATETONUMBER (StopDate) - DATETONUMBER (StartDate)

This expression could be used in a map rule to produce a value for **DaysBetween**. It converts the **StopDate** and the **StartDate** to integers, then subtracts the resulting two integers, and returns the result as **DaysBetween**.

Related functions

- ADDDAYS
- NUMBERTODATE

DATETOTEXT

The DATETOTEXT function converts a date object or expression to a text item.

Syntax:

DATETOTEXT (single-date-expression)

Meaning:

DATETOTEXT (date_to_convert)

Returns:

A single text item

If *date_to_convert* is a date object name, this returns the date as a text item formatted according to the presentation of the date object.

If *date_to_convert* is a date expression produced by a function, this returns the date as a text item formatted according to the presentation of the output argument of that function.

Examples

DATETOTEXT (ShipDate)

In this example, **ShipDate** is converted from a date to text. If **ShipDate** has a CCYYMMDD presentation, the resulting text item will have that presentation, as well.

DATETOTEXT (CURRENTDATETIME ("{MM/DD/CCYY}"))

In this example, CURRENTDATETIME evaluates and returns a date in MM/DD/CCYY format. Then DATETOTEXT evaluates and returns a text string that is that date in MM/DD/CCYY format.

For example, use DATETOTEXT, to do text concatenation. The FROMDATETIME function provides greater flexibility in specifying the format of the resulting text item.

Related Functions

- FROMDATETIME
- NUMBERTOTEXT
- TEXT
- TEXTTODATE
- TEXTTONUMBER
- TEXTTOTIME
- TIMETOTEXT
- TODATETIME

FROMDATETIME

The FROMDATETIME function converts a date/time item to a text string of a specified format. For example, you can use FROMDATETIME to convert a date-time item into a string for parsing or concatenation. You can also use this function to access the individual parts of a date or time, such as the month, day, year, and so forth.

Syntax:

FROMDATETIME (single-character-date-time-item [, single-text-expression])

Meaning:

FROMDATETIME (date_time [, date_time_format_string])

Returns:

A single character text item

FROMDATETIME returns the date/time specified by *date_time* as a text item with the format specified by *date_time_format_string*. If *date_time_format_string* is not specified, *date_time* will be returned in the same format as the *date_time*.

The date_time_format_string must conform to the date/time format strings as described in the "Format strings" topic.

Examples

• HeaderLine="Today is" + FROMDATETIME (CURRENTDATE (),"{MON DD, CCYY}")

If the current system date is March 3, 1999, this rule evaluates to Today is Mar 03, 1999.

• FROMDATETIME (TransactionTimeStamp Column:.:TransHistory)

If the value of **TransactionTimeStamp Column** is 10:14 A.M. on February 3, 2000 and its format is defined as "{CCYYMMDDHH24MM}", this rule evaluates to 200002031014.

• EXTRACT (Expense:Report, FROMDATETIME (Date:Expense:Report, "{MM}") = "03")

In this example, the FROMDATETIME function is used in the condition expression of the EXTRACT function to identify all expenses in the month of March.

Related functions

- CURRENTDATE
- CURRENTDATETIME
- CURRENTTIME
- DATETOTEXT
- TODATETIME

MAX

The MAX function returns the maximum value from a series of number, date, time, or text values.

Syntax:

MAX (series-item-expression)

Meaning:

MAX (series_of_which_to_find_max)

Returns:

A single number

The result is the maximum value in the input argument series: number, text, or date/time.

Examples

• MAX (UnitPrice:Input)

If the values for UnitPrice are {20, 10, 100}, MAX returns 100.

• MAX(EXTRACT(DueDate:Book:Library, CheckedOut:Book:Library = "Y"))

Returns the maximum (latest) DueDate for a book that is checked out from the library.

Related functions

• MIN

MIN

Use MIN when you need the minimum value from a series of number, date, time, or text values.

The MIN function returns the minimum value from a series.

Syntax:

MIN (series-item-expression)

Meaning:

MIN (series_of_which_to_find_min)

Returns:

A single number

The result is the minimum value of the input series: number, text, or date/time.

Examples

• MIN (UnitPrice:Input)

If the values for **UnitPrice** are {20,10,100}, MIN returns 10.

• MIN (StartTime:.:Schedule)

Returns the minimum (earliest) StartTime in Schedule.

Related functions

• MAX

NUMBERTODATE

You can use the NUMBERTODATE function to perform a calculation on a date.

NUMBERTODATE converts an integer to a date, where the integer is the number of days from December 31, 1864, to the specified date. Only positive, non-zero values can be specified as valid parameters.

Syntax:

NUMBERTODATE (single-integer-expression)

Meaning:

NUMBERTODATE (integer_to_convert)

Returns:

A single date

After converting an integer to a date, if the result is being assigned to a date object, the resulting date is in the presentation for that output. If the resulting date is not being assigned to an object, it has a CCYYMMDD presentation.

When the year exceeds four digits, the output will display hash characters (#) for the CCYY values because the field is defined to be only four digits in length.

Examples

NUMBERTODATE (StartDate)

This example converts the StartDate value from an integer to a date that is in CCYYMMDD format.

Related functions

- ADDDAYS
- DATETONUMBER
- FROMDATETIME
- TODATETIME

TEXTTODATE

The TEXTTODATE function converts text item from CCYYMMDD or YYMMDD format to a date.

You can use the TEXTTODATE to convert a text item to a date, however, the TODATETIME function provides greater flexibility for specifying the resulting date-time format.

Syntax:

TEXTTODATE (single-text-expression)

Meaning:

TEXTTODATE (text_to_convert_to_date)

Returns:

A single date

The *text_to_convert_to_date* must be in either CCYYMMDD or YYMMDD format. If the *text_to_convert_to_date* is in error (for example, it is not a valid date), the result is "none".

If text_to_convert_to_date is in YYMMDD format and is being assigned to a date format that includes a century, the century is determined based on the century run option setting using the **CCLookup** parameter or the current century.

Examples

```
• TEXTTODATE ( "990114" )
```

Returns a single date item with the value of January 14 in the year 99

• TEXTTODATE (OrderDate)

Returns OrderDate as a single date item.

- DATETOTEXT TEXTTOTIME
- NUMBERTO TIMETOTEXT
 TEXT

 TEXTTONUM- 	• TO-
BER	DATETIME

TEXTTOTIME

Use TEXTTOTIME when you want to convert an object defined as text that is in HHMM or HHMMSS presentation, to an item defined as time. For greater flexibility, use the TODATETIME function for specifying the format of the text item that is to be converted to a date/time.

Syntax:

TEXTTOTIME (single-text-expression)

Meaning:

TEXTTOTIME (text_to_convert_to_time)

Returns:

A single time

The text_to_convert_to_time must be in HHMM or HHMMSS presentation. HH is a two-digit hour in a 24-hour format. If the result is being assigned to a time object, the resulting time looks like the output object. Otherwise, the resulting time looks like the input argument. If the input argument is in error (for example, it is not a valid time), the result is "none".

Examples

• TEXTTOTIME (CallTime)

Returns CallTime as a time item

 DATETOTEXT 	 TEXTTONUM-
	BER

- FROMDATETIME TIMETOTEXT
- NUMBERTO- TODATETIME TEXT

• TEXTTODATE

TIMETOTEXT

You can use the TIMETOTEXT function to perform text concatenation. For greater flexibility, use the FROMDATETIME function for specifying the format of the resulting text item.

TIMETOTEX converts a time object or expression to a text item.

Syntax:

TIMETOTEXT (single-time-expression)

Meaning:

TIMETOTEXT (time_to_convert_to_text)

Returns:

A single text item

If *time_to_convert_to_text* is a time object name, this returns the time as a text item formatted according to the presentation of the input date object.

If *time_to_convert_to_text* is a time expression produced by a function, this returns the time as a text item formatted according to the presentation of the output argument of that function.

Examples

• TIMETOTEXT (LeadTime)

In this example, **LeadTime** is converted from a time to text. If **LeadTime** has an HH:MM presentation, the resulting text item will be of that presentation.

• TIMETOTEXT (CURRENTDATETIME ("{HH:MM:SS}"))

Here, CURRENTDATETIME evaluates and returns a time in HH:MM:SS format. Then, TIMETOTEXT evaluates and returns a text string that is that time in HH:MM:SS format.

- DATETOTEXT
- FROMDATETIME
- NUMBERTOTEXT
- TEXTTODATE
- TEXTTONUMBER
- TEXTTOTIME
- TODATETIME

TODATETIME

The TODATETIME function converts a text string of a specified format to a date-time item.

Syntax:

 ${\tt TODATETIME}\ (\ {\tt single-character-text-expression}$

[, single-text-expression])

Meaning:

TODATETIME (text_to_convert [, date_time_format_string])

Returns:

A single character date item

TODATETIME returns the date-time that corresponds to the value specified by *text_to_convert*, which is in the format specified by *date_time_format_string*. If *date_time_format_string* is not specified, it will be assumed that *text_to_convert is* in [CCYYMMDDHH24MMSS] format.

The date_time_format_string must conform to the date-time format strings as described in "Format strings".

Examples

• TODATETIME ("05/14/1999@10:14pm" , "{MM/DD/CCYY}@{HH12:MMAM/PM}")

In this example, a text string containing a date and time is converted to a date-time item.

• RptDate = TODATETIME (RIGHT (GETRESOURCENAME() , 8) , "CCYYMMDD")

Assume that you receive a file that contains historical data. The name of the file identifies the date of the historical data. For example, a filename of **19960424** indicates that the data was produced on April 24, 1996. To map this date to **RptDate**, the TODATETIME function could be used with the RIGHT and GETRESOURCENAME functions.

Related functions

- CURRENTDATE
- CURRENTDATETIME
- CURRENTTIME
- TEXTTODATE
- TEXTTOTIME

Error handling functions

CONTAINSERRORS

The CONTAINSERRORS function tests a valid object to see whether it contains any objects in error.

Syntax:

CONTAINSERRORS (single-object-expression)

Meaning:

CONTAINSERRORS (object_to_test)

Returns:

True or false

The CONTAINSERRORS function returns "true" if any object contained in *object_to_test* is in error; it returns "false" if the *object_to_test* is completely valid.

The input object, itself, is a *valid* input object. This function does *not* evaluate for invalid objects. Therefore, if you have map rule:

CONTAINSERRORS (Invoice:InputFile)

and **Invoice**[1] is valid, **Invoice**[2] is invalid, and **Invoice**[3] is valid, then CONTAINSERRORS evaluates only twice-once for each *valid* instance of **Invoice**.

Examples

Msg (s) = IF (CONTAINSERRORS (Msg:MailBag) & Type:Msg:MailBag = "PRIORITY", Msg:MailBag, "none")

In this example, if **Msg:MailBag** contains any object in error and **Type:Msg:MailBag** has a value of "PRIORITY", **Msg:MailBag** is mapped; otherwise, "none" is returned for this occurrence of **Msg**. This map rule returns all valid messages (**Msg**) that contain errors with a **Type** of "PRIORITY".

Related functions

- ISERROR
- REFORMAT

FAIL

You can use the FAIL function to abort a map based on map or application specific logic.

Syntax:

FAIL (single-text-expression)

Meaning:

FAIL (message_to_return)

Returns:

"None"

The FAIL function returns "none" to the output to which the function is assigned, aborts the map, and returns *message_to_return* as the map completion error message included in the execution audit. The map return code will be "30", indicating that the map failed through the FAIL function.

Examples

AcctID = EITHER (LOOKUP (CustomerID:.:Xref, MyKey:.:Xref = ID:.:Input), FAIL ("Unknown Customer (" + ID:.:Input + "). Processing Terminated."))

In this example, the FAIL function is being used in conjunction with the EITHER function to conditionally fail the map if a record in the customer cross-reference file does not exist for a given **CustomerID**.

For example, the **ID** in **Input** is ABC123. If the LOOKUP succeeds, the **CustomerID** result is assigned to **AcctID** and the map continues.

If the LOOKUP fails, **AcctID** is assigned a value of "none", the map aborts, and the message Unknown Customer (ABC123). Processing Terminated.is written to the execution audit log.

 Message = VALID (RUN ("Map1Msg.mmc", "-AE -OMMSMQ1B `-QN .\aqueue -CID 2001""), FAIL ("Failure on RUN (" + TEXT (LASTERRORCODE ()) + "):" + LASTERRORMSG ()))

In this example, the FAIL function is being used in conjunction with the VALID, LASTERRORCODE, and LASTERRORMSG functions to fail (abort) the map if the map executed by the RUN function (**Map1Msg.mmc**) fails. In this example, the map fails and returns the error code and error message reported by the RUN function using the LASTERRORCODE and LASTERRORMSG functions.

If **Map1Msg** fails because one or more of its inputs was invalid, **Message** is assigned a value of "none". The map aborts and the following message is reported in the execution audit log:

"Failure on RUN (8): One or more inputs was invalid."

Related functions

- LASTERRORCODE
- LASTERRORMSG
- QUIT
- VALID

GETXMLERRORMSG

Use this function on an output card to return an XML validation error message when a map runs against invalid XML input.

Create the input card with either a native XML schema or an XML-based type tree, and specify the Restart attribute. On the output card, use the GETXMLERRORMSG function, passing the number of the input card as the parameter. When the map runs and the input contains invalid XML data, the output card returns a standard XML error message. For example: Error (-1), "XMLParser: Input XML data is invalid." SAXParseException, Error [line: 162 column: 36] Datatype error: Type:SchemaDateTimeException, Message:Incomplete Date ! '2006-09-' .

See the Type Designer documentation or the Map Designer documentation for details about the Restart attribute.

Syntax

GETXMLERRORMSG (single-number-expression)

Meaning

GETXMLERRORMSG (input_card_number)

Returns

A text string

Related functions

VALIDATE

ISERROR

The ISERROR function tests an object to see if it is in error

You can use ISERROR to output your data in exactly the same order as it occurs in your input, both the valid data and the data in error. You can also use ISERROR to produce error messages for bad data in the same file in which you map your good data.

Syntax:

ISERROR (single-object-name)

Meaning:

ISERROR (object_to_test)

Returns:

"True" or "false"

ISERROR returns "true" when object_to_test is in error and returns "false" when object_to_test is completely valid.

Examples

 InfoRec (s) = IF (ISERROR (Record:SomeFile), "Bad --> " + REJECT (Record:SomeFile), "Ok --> " + TEXT (Record:SomeFile))

In this example, ISERROR is used to produce a report for *all* **Record** objects in **SomeFile**. If the record is in error, the **InfoRec** will have the text Bad --> followed by the data from the input **Record**. If the record is valid, the **InfoRec** will have the text Ok --> followed by the data from the input **Record**, such as:

```
Ok --> SZ-68839,486 Upgrade Microprocessor,186.86,100,W200
Bad --> MK-19309,,369.43,417,W100
Ok --> KL-20349,PCMCIA Network Adaptor,174.82,29,N300
Ok --> WP-37679,AC Adaptor,39.48,245,E100
Bad --> IL-39890,8MB Memory PCMCIA,390.48,0,S100
```

Related functions

CONTAINSERRORS

ONERROR

Use ONERROR in component rules to add user-defined error messages to the data section of the audit log.

The ONERROR function adds a user-defined error message to the data section of the audit log. This function is relevant only in Type Designer Component rules.

Syntax:

ONERROR (single-condition-expression, single-text-expression)

Meaning:

ONERROR (condition_to_evaluate, message_to_display)

Returns:

"True" or "false"

If condition_to_evaluate evaluates to "true", the function returns "true".

If condition_to_evaluate evaluates to "false", the function returns "false".

If data audit is enabled and the object to which the component rule applies will result in a failed component rule message (status E09), *message_to_display* is written to the data audit section of the audit log with an entry type of U, representing user-defined.

If the failed component rule message (E09) appears in the data section of the audit log, one or more user-defined error messages can also be included in the data section of the audit log. If a component rule has one ONERROR function, one user-defined error message or none is included in the audit log. If a component rule has two ONERROR functions, two user-defined error messages at most are included in the audit log, and so on.

Examples

• Here is a component rule without ONERROR:

Claim Date Field > Accident Date Field &

Claim Date Field < ADDDAYS (Accident Date Field, 365)

If the component rule fails, the data section of the audit log shows the following information:

```
<DataLog>
<input card="1">
<object ... status="E07">InsuranceClaim</object>
<object ... status="E09">Claim Date Field</object>
<Text>980725</Text>
<object ... status="E07">InsuranceClaim</object>
<object ... status="E09">Claim Date Field</object>
</br/>
```

Status code E09 for the **Claim Date Field** indicates that the data for that object failed its component rule, but does not provide any further detail.

• Using ONERROR, one or more error messages can be added to the data section of the audit log to provide more information as to how or why the component rule failed. For example,

ONERROR (Claim Date Field > Accident Date Field , "Claim date before accident.") &

ONERROR (Claim Date Field < ADDDAYS (Accident Date Field , 365) , "Claim is more than one year old.")

If the component rule fails and ONERROR is used, the data section of the audit log can show the following messages:

```
<DataLog>
<input card="1">
<object ... status="E07">InsuranceClaim</object>
<object ... status="E09">Claim Date Field</object>
<Text>980725</Text>
<User>Claim date before accident.</User>
<object ... status="E07">InsuranceClaim</object>
<object ... status="E07">InsuranceClaim</object>
<object ... status="E09">Claim Date Field</object>
```

REJECT

The REJECT function returns the content of an object in error as a text item. Use REJECT in conjunction with the restart attribute. You can use the REJECT function in map rules only, not in component rules.

See the schema designer and map designer documentation for information about the restart attribute.

Syntax:

REJECT (series-object-expression)

Meaning:

REJECT (series_to_look_for_bad_objects)

Returns:

A series text item

REJECT evaluates to a series of text items consisting of all the input series members in error.

Examples

• REJECT (Record:File)

This example extracts all Records that are in error.

• IF (COUNT (REJECT (Msg IN Batch))) = 0, "OK", "ERROR")

In this example, the total number of invalid (rejected) Msg objects is counted. If the total number of invalid Msg objects is equal to zero, it indicates that there were no invalid Msg objects counted and a message of OK results. Otherwise, a message of ERROR results.

Related functions

- CONTAINSERRORS
- ISERROR
- VALID

QUIT

You can use the QUIT function to stop a map at a specific point during map execution. The QUIT function logs a successful return code and a custom message in the map audit log.

Syntax:

QUIT (single-text-expression)

Meaning:

QUIT (message_to_return)

Returns:

"None"

The QUIT function returns "none" to the output, stops the map, and logs map return code 41 and the message QUIT function terminated map successfully: message_to_return in the map audit log.

- FAIL
- LASTERRORCODE
- LASTERRORMSG
- VALID

VALID

You can use the VALID function to perform conditional processing based on whether an external interface function executes successfully.

VALID returns the result of the first argument if it is valid; otherwise, returns the second argument.

Syntax:

VALID (single-text-expressions, single-general-expression)

Meaning:

```
VALID (function_that_can_fail, return_value_if_function_fails)
```

Returns:

A single text expression

VALID returns the result of the evaluation of *function_that_can_fail* if it is valid. If the function fails, VALID returns *return_value_if_function_fails*.

The following functions can fail:

- DBLOOKUP GET
- DBQUERY PUT
- DDEQUERY
 RUN
- EXIT

Examples

• SomeObject = VALID (RUN ("mymap.mmc" , "-OF1 mydata.txt") , FAIL ("My RUN failed!"))

If the RUN function returns an error return code, the VALID functions returns none, the map aborts, and the message My RUN failed! is reported under Execution Summary in the execution audit log.

Related functions

- DBLOOKUP
- DBQUERY
- DDEQUERY

External interface functions

DBLOOKUP

The DBLOOKUP function executes an SQL statement against a database. The SQL statement can be any permitted by your database management system or ODBC driver.

When the DBLOOKUP function is used in a map, the default **OnSuccess** action is adapter specific. The default **OnFailure** action is to rollback any changes made during map processing. The default **Scope** will be integral unless the map is defined to run in bursts (which is the case when one or more inputs have the **FetchAs** property set to **Burst**).

There are two ways to specify arguments for DBLOOKUP.

You can use DBLOOKUP to execute an SQL statement when you want to execute a SELECT statement to retrieve a specific column value in a large table in a database using the value of another input, rather than defining the entire table as an input card and using the LOOKUP, SEARCHDOWN, or SEARCHUP functions.

You can use DBLOOKUP to execute an SQL statement when you want to execute a SELECT statement to retrieve a specific column value from a table or database that might vary based on a parameter file. Using Meaning 2 of the DBLOOKUP function allows these parameters to be dynamically specified at run time.

Syntax:

DBLOOKUP (single-text-expression, single-text-expression, [single-text-literal])

Meaning:

- 1. DBLOOKUP (SQL_statement , mdq_filename , database_name)
- 2. DBLOOKUP (SQL_statement, parameters)

Returns:

A single text item

The DBLOOKUP function returns the results of the query in the same format as a query specified for a map input card, except that it does not include the last carriage return/linefeed. Because this information is removed, it is easier to make use of a single value extracted from a database.

Arguments for meaning 1

DBLOOKUP (SQL_statement , mdq_filename , database_name)

SQL_statement

The first argument is an SQL statement as a text string. This can be any valid SQL statement permitted by your database management system and supported by your database-specific driver. In addition to a fixed SQL

statement, this argument can be a concatenation of text literals and data objects, enabling the concatenation of data values into your SQL statement.

mdq_filename

The second argument is the name of a database query file (.mdq) produced by the Database Interface Designer. It contains the definition of the database that the SQL statement is to be executed against. If the .mdq file is in a directory other than the directory of the map, the path must be specified.

Note: The .mdq file is accessed at map build time and is not needed at run time.

database_name

The third argument is the name of a database in the database query file (**.mdq**) as defined in the Database Interface Designer.

If used in this way, both the .mdq filename and database name must be literals.

Arguments for meaning 2

DBLOOKUP (SQL_statement, parameters)

SQL_statement

The first argument is an SQL statement as a text string. This can be any valid SQL statement permitted by your database management system and supported by your database-specific driver. In addition to a fixed SQL statement, this argument can be a concatenation of text literals and data objects, enabling the concatenation of data values into your SQL statement.

parameters

The second argument is a set of parameters, either:

- -MDQ mdqfilename -DBNAME dbname
 - -or-
- -DBTYPE database_type [database specific parameters]

The keyword -MDQ is followed by the name of the database query file (**.mdq**) produced by the Database Interface Designer. This **.mdq** file contains the definition of the database. If the **.mdq** file is in a directory other than the directory of the map, the path must be specified. The **.mdq** filename is followed by the keyword -DBNAME and the database name as specified in the Database Interface Designer.

Using this syntax, the .mdq file is accessed at run time and must be present.

The keyword -DBTYPE is followed by a keyword specifying the database type (for example, ODBC or ORACLE) followed, optionally, by database-specific parameters.

This syntax does not use an **.mdq** file, because the database-specific parameters provide the information required to connect to the database. See the Resource Adapters documentation for detailed information about the database-specific parameters that can be specified.

When used with Meaning 2, DBLOOKUP must conform to these rules:

- All keywords (for example, -DBTYPE) can be upper or lowercase, but not mixed.
- A space is required between the keyword and its value (for example, -DBTYPE ODBC).
- The order of the keywords is not important.
- All database-specific parameters are optional.

Examples

Assume that you have a table named "PARTS" that contains the following data:

	PART_NUMBER	PART_NAME	
1		1/4" x 3" Bolt	
2		1/4" x 4" Bolt	

Assume that this database has been defined using the Database Interface Designer in a file named **mytest.mdq** and that the name of the database, as specified in the **.mdq** file, is **PartsDB**.

• DBLOOKUP ("SELECT PART_NAME from PARTS where PART_NUMBER =1", "mytest.mdq", "PartsDB")

Returns: ¼" x 3" Bolt

Using Meaning 2, you can specify the DBLOOKUP this way:

• DBLOOKUP("SELECT PART_NAME from PARTS where PART_NUMBER =1", "-MDQ mytest.mdq -DBNAME PartsDB")

where both the .mdq file name and database name is specified.

Using Meaning 2, you can also specify the database type and the appropriate database-specific parameters:

• DBLOOKUP("SELECT PART_NAME from PARTS where PART_NUMBER =1", "-DBTYPE ORACLE -CONNECT MyDB -USER janes ")

Related functions

- DBQUERY
- EXTRACT
- FAIL
- LASTERRORCODE
- LASTERRORMSG
- LOOKUP
- SEARCHDOWN
- SEARCHUP
- VALID

For more examples using the DBLOOKUP function, see the Database Interface Designer documentation.

DBQUERY

The DBQUERY function executes an SQL statement against a database. The SQL statement can be any permitted by your database management system or ODBC driver.

When the DBQUERY function is used in a map, the default **OnSuccess** action is adapter specific. The default **OnFailure** action is to rollback any changes made during map processing. The default **Scope** will be integral unless the map is defined to run in bursts (which is the case when one or more inputs have the **FetchAs** property set to **Burst**).

There are two ways to specify the arguments for DBQUERY. You can use DBQUERY [*Meaning 1*] to execute an SQL statement when you want to look up information in a database using a parameterized query that is based on another value in your data. If your SQL statement is a SELECT statement, the DBQUERY function might be used in conjunction with the RUN function to issue dynamic SELECT statements whose results can be used as input to another map.

You can also use the DBQUERY function [*Meaning 2*] to execute an SQL statement when the database, table, or other database parameters might vary; perhaps being supplied by a parameter file.

Syntax:

DBQUERY (single-text-expression , single-text-expression , [single-text-literal])

Meaning:

- 1. DBQUERY (SQL_statement , mdq_filename , database_name)
- 2. DBQUERY (SQL_statement, parameters)

Returns:

A single text item

If your SQL statement is a SELECT statement, the results of the query in the same format as a query specified as a map input card, including row delimiters and terminators, and so on.

If your SQL statement is anything other than a SELECT statement, "none".

Arguments for meaning 1

DBQUERY (SQL_statement , mdq_filename , database_name)

SQL_statement

The first argument is an SQL statement as a text string. This can be any valid SQL statement that is permitted by your database management system and supported by your database-specific driver. In addition to a fixed SQL statement, this argument can be a concatenation of text literals and data objects, enabling the concatenation of data values into your SQL statement.

mdq_filename

The second argument is the name of a database query file (**.mdq**) produced by the Database Interface Designer. It contains the definition of the database that the SQL statement is to be executed against. If the **.mdq** file is in a directory other than the directory of the map, the path must be specified.

Note: The .**mdq** file is accessed at map build time and is not needed at run time.

database_name

The third argument is the name of a database in the database query file (**.mdq**) as defined in the Database Interface Designer.

If used in this way, both the .mdq filename and database name must be literals.

Arguments for meaning 2

DBQUERY (SQL_statement, parameters)

- The first argument is an SQL statement as a text string. This can be any valid SQL statement that is permitted by your database management system and supported by your database-specific driver. In addition to a fixed SQL statement, this argument can be a concatenation of text literals and data objects, enabling the concatenation of data values into your SQL statement.
- The second argument is a set of parameters, either:
 - -MDQ mdqfilename -DBNAME dbname

-or-

• -DBTYPE database_type [database specific parameters]

The keyword -MDQ is followed by the name of the database query file (.**mdq**) produced by the Database Interface Designer. This .**mdq** file contains the definition of the database. If the .**mdq** file

is in a directory other than the directory of the map, the path must be specified. The **.mdq** filename is followed by the keyword -DBNAME and the database name as specified in the Database Interface Designer.

Note: Using this syntax, the .mdq file is accessed at run time and must be present.

The keyword -DBTYPE is followed by a keyword specifying the database type (for example, ODBC or ORACLE) followed, optionally, by database-specific parameters.

Note: This syntax does not use an **.mdq** file, because the database-specific parameters provide the information required to connect to the database. See the appropriate database adapter documentation for detailed information about database-specific parameters.

When used with Meaning 2, DBQUERY must conform to these rules:

- All keywords (for example, -DBTYPE) can be upper or lower case, but not mixed.
- A space is required between the keyword and its value (for example, -DBTYPE ODBC).
- The order of the keywords is not important.

All database-specific parameters are optional.

Examples

Assume that you have a table named "PARTS" that contains the following data:

	PART_NUMBER	PART_NA	ME
1		1/4" x 3" Bolt	
2		1/4" x 4" Bolt	

Also assume that this database has been defined using the Database Interface Designer in a file named **mytest.mdq** and that the name of the database, as specified in the **.mdq** file, is **PartsDB**.

DBQUERY ("SELECT * from PARTS" , "mytest.mdq" , "PartsDB")

Returns 1|1/4" x 3" Bolt<cr><lf>2|1/4" x 4" Bolt<cr><lf>

where <cr><lf> is a carriage return followed by a line feed.

Using Meaning 2, you can also specify the DBQUERY this way:

DBQUERY ("SELECT * from PARTS" , "-MDQ mytest.mdq -DBNAME PartsDB")

where both the .mdq file name and database name are specified.

Or, specify it this way, using Meaning 2 by specifying the database type and the appropriate database-specific parameters:

DBQUERY ("SELECT * from PARTS" , "-DBTYPE ORACLE -CONNECT MyDB -USER janes")

Assume that you have an input file containing one order record. To map that order to another proprietary format, you also have a parts table with pricing information for every part for every customer, a very large table. Rather than using the entire parts table as the input to your map, you might use the RUN function with a DBQUERY to dynamically select only those rows from the parts table corresponding to the customer in the order file, as follows:

```
RUN ( "MapOrder.MMC" ,
    "IE2" + DBQUERY ( "SELECT * FROM Parts WHERE CustID = "
    + CustomerNo:OrderRecord:OrderFile + " ORDER BY PartNo" ,
    "PartsDB.MDQ", "PartsDatabase" ) )
```

Related functions

- DBLOOKUP
- EXTRACT
- FAIL
- LASTERRORCODE
- LASTERRORMSG
- LOOKUP
- SEARCHUP
- SEARCHDOWN
- VALID

DDEQUERY

The DDEQUERY function allows you to interface to other Windows applications such as Trading Partner PC, Excel, and so forth, provided that certain criteria are met. For example, if you receive an Excel spreadsheet file, you must have the appropriate version of the Excel application installed (that is compatible with the file received) and the application must be open.

Syntax:

DDEQUERY (single-text-expression, single-text-expression, single-text-expression)

Meaning:

DDEQUERY (application_name, topic, text)

Returns:

A single text item from an application

Examples

DDEQUERY ("excel", "[MKTPRICE.XLS]Sheet1", "R8C1:R14C3")

In this example, DDEQUERY is used to get data from an Excel spreadsheet. The third argument, **R8C1:R14C3**, specifies the location of the data in the spreadsheet. (In Excel, the 8th row, 1st column to the 14th row, 3rd column is A8:C14.) The content of this spreadsheet range is returned as a single text item.

This example assumes that the application, the map, and the spreadsheet all reside in the same directory. If they are not in the same directory you must add the path. For example:

DDEQUERY ("excel", "c:\spreadsheet[MKTPRICE.XLS]Sheet1", "R8C1:R14C3")

DDEQYUERY ("tppc","PartnerX","BGyourEDIode")

In this example, DDEQUERY is used as a request to Trading Partner PC.

Related functions

- EXIT
- FAIL
- GET
- LASTERRORCODE
- LASTERRORMSG
- PUT
- RUN
- VALID

EXIT

The EXIT function allows you to interface with a function in an external library or application.

You can use EXIT when you need information from an existing function in a library or a program or when you need to use a general function that is not available.

Depending on the execution operating system, there are two different methods for the EXIT function: 1) the library method and 2) the program method. The program method is not supported on Windows operating systems.

Syntax:

EXIT (single-text-expression, single-text-expression, single-text-expression)

Meaning:

- 1. EXIT (library_name, function_name, input_to_the_function)
- 2. EXIT (program_name , command_line_arg1 , command_line_arg2)

Returns:

A single text item

Meaning 1 - library method

At run time, the *function_name* function will execute in the library specified by *library_name* passing *input_to_the_function* as a text string. The result of *function_name* is returned as a text item by means of **lpep- > lpdataFromApp**.

Set Ipep- > nReturn equal to 0 if the function is to succeed or set it equal to 1 to fail.

For detailed information about the requirements of the library function that is executed by the EXIT, see Implementing a library EXIT function on page 984.

AIX operating system

On the AIX operating system, the shared library that contains *library_function* must also contain an *entry_point* function. The *entry_point* function must be prototyped in the same manner as *library_function*. The server will invoke the *entry_point* function before invoking *library_function*. The server passes the name of the *library_function* to the *entry_point* function by way of the *szFile* EXITPARAM structure member. The *entry_point* function must then determine the address of the *library_function* and pass this address back to the server by way of the *lpv* EXITPARAM structure member. The server by way of the *lpv* EXITPARAM structure member.

The following example depicts a shared library called **mcshex.so** which contains the *entry_point* function and the *library_function*.

```
#include <stdio.h>
#include <string.h>
#include "runmerc.h"
void AIXEntry(LPEXITPARAM);
void bin2hex(LPEXITPARAM);
unsigned int i;
char *syms[] = { "bin2hex", "AIXEntry" };
void *adr[] = { (void *)bin2hex, (void *)AIXEntry};
void AIXEntry(LPEXITPARAM lpInputStruct)
{
    printf("AIXEntry called\n");
    for (i = 0; i < (sizeof(syms)) / (sizeof(char *)); i++)</pre>
       if ( !(strcmp(lpInputStruct->szFile, syms[i])) ) {
           lpInputStruct->lpv = adr[i];
           break;
       }
 }
void bin2hex(LPEXITPARAM lpInputStruct)
  {
    printf("bin2hex called\n");
printf("argument to library function: %s\n",lpInputStruct->lpszCmdLine);
lpInputStruct->nReturn = 0;
}
```

To build this shared library, run the following commands:

cc -c share1.c

```
cc -o mcshex.so share1.o -bE:shrsub.exp -bM:SRE -eAIXEntry
```

Meaning 2 - program method

The program method of the EXIT function is not supported on Windows operating systems.

At execution time, the program specified by *program_name* executes and passes the concatenation of *command_line_arg1* + " " + *command_line_arg2* as a text string.

Whatever is returned by program_name to the standard output device is returned as text.

Examples

• EXIT (program_name , command_line_arg1 , command_line_arg2)

Returns a text string from the function or application that is executed. If the EXIT function is not available for a particular operating system, EXIT returns none.

• EXIT ("mydll.dll" , "myfunction" , "12")

This Windows library example passes the value 12 to **myfunction**, a function in **mydll.dll**. The value of the item returned depends on what **myfunction** does with the 12 passed to it.

 IF (EXIT ("mylib.sl", "ckCust", CustID Column:Row:DB) = "OK", MapKnownCust (Row:DB), MapUnknownCust (Row:DB))

Similarly, this UNIX library example passes the value of **CustID** Field to ckCust, a function in a UNIX shared library called **mylib.sl**. If the value returned by ckCust is OK, a functional map is called to map **Row** for a known customer. Otherwise, another functional map is executed to map **Row** for an unknown customer.

• EXIT ("pwd" , " " , " ")

This UNIX program example executes the UNIX print working directory (pwd) command to determine the current directory. The name of the current working directory is then returned as a text string. Notice that although the pwd command does not require additional command line arguments, *command_line_arg1* and *command_line_arg2* must be included as a space enclosed in double quotation marks (" ").

• TEXTTONUMBER ((EXIT ("GetIncome" , Applicant:Form , "*Mortgage"))

This program example passes the value of Applicant concatenated to the text literal *Mortgage to an application called GetIncome. The result is converted to a number.

Related functions

- DDEQUERY
- FAIL
- GET
- LASTERRORCODE
- LASTERRORMSG
- PUT

- RUN
- VALID

Implementing a library EXIT function

You can develop a function in a library to be executed from an EXIT function.

EXIT function's library interface

Library functions are used within an EXIT function using information contained in the EXITPARAM structure. This method provides great flexibility for data passed to and from a map. For example, the map can pass binary data containing nulls, and there is no limitation on the length of the returned data. The method also allows functions to report additional information by providing a return code and error message.

Using the EXITPARAM Structure

Function prototype

The function to be executed must be a function in a library with the following prototype:

void MyFunc(LPEXITPARAM lpep);

Definition of the EXITPARAM structure

The definition of the EXITPARAM structure is as follows:

struct	tagExi	tPar	amStruct
{			
DWOR	D		dwSize;
DWOR	D		dwToLen;
DWOR	D		dwFromLen;
DWOR	D		dwMapInstance;
void	FAR *		lpv;
LPST	R		lpszCmdLine;
BYTE	HUGE	*	lpDataToApp;
BYTE	HUGE	*	lpDataFromApp;
UINT			uRetryCount;
UINT			uRetryInterval;
BOOL			bRollback;
BOOL			bCleanup;
int			nReturn;
char			<pre>szErrMsg[100];</pre>
char			<pre>szFile[260];</pre>
void	FAR *		lpMapHandle;
void	FAR *		lpInternal;
void	FAR *		lpCmdStruct;
void	FAR *		lpAdaptParms;
void	FAR *		lpContext;
void	FAR *		lpWildcard;
void	FAR *		lpfnMS;
void	FAR *		lpMS;
DWOR	D		dwWildcardSize;
LPST	R		<pre>lpszMapDirectory;</pre>
WORD)		wCardNum;

	WORD	wCleanupAction;
	WORD	wScope;
	UINT	uUnitSize;
	BOOL	bBurst;
	BOOL	bFromRule;
	BOOL	bSource;
	DWORD	dwRecords;
]	;	
1	<pre>typedef struct tagExitParamStruct EXITPARAM;</pre>	
1	ypedef struct t	agExitParamStruct FAR * LPEXITPARAM;

The engine environment sets up the EXITPARAM structure and the function should fill in the result. The engine will allocate and free the memory associated with **IpDataToApp**. The function must allocate the memory for **IpDataFromApp**. For all Windows operating systems, use the Windows macro **GlobalAllocPtr** defined in **windowsx.h**. For all other operating systems, use the c-runtime malloc function. The engine will free this memory.

Component	Used as	Usage
dwSize	Input	Size (in bytes) of EXITPARAM to assure correct compati- bility
dwToLen	Input	Length (size in bytes) of lpDataToApp
dwFromLen	Output	Length (size in bytes) of lpDataFromApp
dwMapInstance		Not used
lpv		Not used
LpszCmdLine		Not used
lpDataToApp	Input	Data sent to the function. This is the third parameter of the EXIT function
IpDataFromApp	Output	Data sent back to the server from the function
uRetryCount		Not used
uRetryInterval		Not used
bRollback		Not Used
bCleanup		Not used
nReturn	Output	Return code based on the outcome of the function
szErrMsg	Output	String message based on nReturn
szFile		Not used
lpInternal		Not used
lpCmdStruct		Not used
lpAdaptParms		Not used

Table 21. Components of EXITPARAM as used with the EXIT function.

Component	Used as	Usage
lpContext	Not used	
lpWildcard	Not used	
dwWildcardSize	Not used	
IpszMapDirectory	Not used	
wCardNum	Not used	
wCleanupAction	Not used	
wScope	Not used	
uUnitSize	Not used	
bBurst	Not used	
lpfnMS	Not used.	
lpMS	Not used	
dwRecords	Not used	

Table 21. Components of EXITPARAM as used with the EXIT function. (continued)

There is no interaction with the nReturn or szErrMsg fields. However, this might change in a future release.

GET

You can use the GET function to retrieve data using one of the source adapters, such as a messaging system, a database, a file, and so forth, within the course of your map.

When the GET function is used in a map, the default **OnSuccess** action is adapter specific. The default **OnFailure** action is to rollback any changes made during map processing. The default **Scope** will be integral unless the map is defined to run in bursts (which is the case when one or more inputs have the **FetchAs** property set to **Burst**).

GET can also be used for adapters that support request and reply, such as Socket.

Syntax:

GET (single-text-expression , single-text-expression [, single-text-expression])

Meaning:

GET (adapter_alias, adapter_commands [, data_request_to_send_to_adapter])

Returns:

A single character text item

GET returns the data that is returned by the source adapter. The adapter identified by *adapter_alias* is called using the specified *adapter_commands* and passing *data_request_to_send_to_adapter* as data to the adapter. See the Resource Adapters documentation.

You cannot use the GET function to retrieve a file that was built by an earlier output card within the same map. Instead, map the output of the earlier card to the later card.

To identify whether the function was successful, you can generally use the VALID function with the GET function. However, for certain adapters such as E-mail and FTP, the success state is not known until after map completion and using the VALID function in such cases might consistently return "success".

Examples

• Reply (s) = GET ("SOCKET", "-HOST localhost -PORT 8015 -EOF -LSN 10 -T", PACKAGE (Request Object..:Input))

In this example, the GET function would connect to the socket-based server on localhost using port 8015. The Socket Adapter would submit the "Input" data to the server, and then wait up to 10 seconds for a reply to that message.

 Acct# = GET ("DB", "-dbtype ORACLE -connect shasta -user rjc -pw vm70" + "SELECT Acct# FROM CustMaster WHERE CustID = "" + SenderID Field:Identification Segment:Msg + """)

In this example, the GET function could be used instead of a DBLOOKUP or DBQUERY function to retrieve data from a database from within in a map rule.

Related functions

- FAIL
- LASTERRORCODE
- LASTERRORMSG
- PUT
- VALID

JEXIT

The JEXIT function provides a means to interface with a method in an external Java class. Using this function, you can manipulate simple primitive types, simple objects, and complex objects.

There are two required text parameters for a JEXIT function. The first text parameter is the class name or key, depending on which meaning you use. The second text parameter is the method name. There are two optional text parameters for the data.

The first use of the JEXIT function creates an object that is based on the specified class name. Then, it invokes the named Java method, with any specified parameters, on that object. After the Java objects method is invoked, then JEXIT automatically destroys the Java object. If multiple invocations on the same Java object are required, then the

predefined "<init>" function can be used in the second parameter of Meaning 1. The returned key from the "<init>" function now references a specific Java object and can then be used multiple times as the first parameter in Meaning 2 function calls.

The second use of the JEXIT function invokes the named Java method, with any specified parameters, on a specific Java object. The method is invoked by using the specified key. This method allows Java objects to be manipulated throughout the map's execution cycle. These Java objects are stored in the HCL® OneTest[™] Data object pool and are referenced during map execution by using the specified key. The specified key can be returned from either a JEXIT meaning 1 or meaning 2 invocation, particularly when a non-scalar, complex Java object must be returned.

JEXIT is not supported on CICS, Batch, or MVS.

Prerequisites

To use JEXIT, do the following configuration steps, depending on the HCL® OneTest[™] Data product you are using.

For HCL® OneTest[™] Data with Command Server or HCL® OneTest[™] Data with Launcher, either add the Java classes to your system class path or add the JAR files to the *install_dir/dtx.ini* file.

Add the JAR files to the jar statements under the **[External Jar Files]** section of the dtx.ini file. For each JAR file, uncomment a jar statement and add the fully qualified path and JAR file name, including the file extension. If a jar statement is already set to a value, add the JAR file to the next jar statement in the sequence. As an example, if the jar1 statement is set to a value, and the jar2 statement is not set to a value, add your JAR file to the jar2 statement.

For HCL® OneTest[™] Data, on Windows operating systems, copy the JAR file to the classes folder in the path where version of application is installed. As an example, copy the JAR file to %MQSI_WORKPATH%\shared-classes. On UNIX operating systems, copy the JAR file to the \$MQSI_WORKPATH/shared-classes.

If you are using Meaning 1, a public default constructor must be declared in the external Java class. If the default constructor is not available or needed, you can use the "<init>" method to instantiate the Java object, but only when there is a class constructor that is defined with one or two string-type parameters.

Syntax

```
JEXIT ("single-text-expression" , "single-text-expression" , ["single-text-expression"] , ["single-text-
expression"])
```

Returns

A single text item.

Meaning 1

JEXIT (class_name, method_name, [input_to_the_function_or_key], [input_to_the_function_or_key])

Using this approach, you provide a Java class and method name, and two optional inputs to the function.

When JEXIT is used in a map rule, at run time this function instantiates a Java virtual machine (JVM). The JVM reads your .class or .jar file and creates an object that is based on the defined Java class. The method, along with any specified parameters, is then invoked on the object.

When the returned object is a complex object, a unique identifier (key) is created that can be used to reference the object in the object pool.

All JEXIT parameters are text strings. Class name and method name are the two required parameters. The two optional parameters are generally input data. At run time, the strings are converted to UTF-8 and passed to the Java method, and the output from Java method is a UTF-8 text string.

The following simple Java class objects are internally converted to strings and returned to the map:

```
java.lang.Void
java.lang.Short
java.lang.Number
java.lang.Long
java.lang.Integer
java.lang.Float
java.lang.Double
java.lang.Byte
java.lang.Boolean
java.lang.String
java.lang.Character
```

Meaning 2

JEXIT (key, method_name, [input_to_the_function_or_key], [input_to_the_function_or_key])

The second use of JEXIT is similar to Meaning 1. The difference is that it assumes that you already have a key that references an object in the object pool. In this scenario, you use JEXIT to invoke a method on an object by using the key as the first required parameter instead of the class name.

Whenever the JEXIT function returns a key, the associated Java object must be deleted before the map completes processing. The object can be deleted by using the predefined JEXIT "<destroy>" method. Failure to invoke the "<destroy>" method results in a JVM memory leak. To prevent the JVM heap from getting fragmented, exhausted, or both, make sure that all object references returned from the JEXIT function are deleted. To delete those object references, use the JEXIT function in the following way:

```
JEXIT("key", "<destroy>")
```

Troubleshooting

To retrieve error messages for JEXIT, you can use the VALID and FAIL functions in your map rule. For example:

```
=VALID(JEXIT("key", "method_name", "data"), FAIL(LASTERRORMSG()))
```

JEXIT Examples

The JEXIT examples are based on the following defined Java classes.

```
class :
package com.ibm.websphere.dtx.test;
```

```
public class TestJExit {
 Person person = new Person();
 public TestJExit() {
 }
 public String toUpper(String test) {
 return test.toUpperCase();
 }
 public String Concat(String test1, String test2) {
 return test1 + test2;
 }
 public Integer toNumber(String test1) {
 return new Integer(test1);
 }
 public Double toDouble(String test1) {
 return new Double(test1);
 }
 public void toNothing() {
 }
 public int returnint() {
 return 9;
 }
 public byte returnbyte() {
 return 8;
 }
 public Person getPerson() {
    return person;
 }
}
class :
package com.ibm.websphere.dtx.test;
public class Person{
 private String ext = new String("DTX");
 private String name = new String("Websphere");
```

- - JEXIT ("com.ibm.websphere.dtx.test.TestJExit " , "toUpper" , "HCL")

Returns HCL

public Person() {

return name;

return ext;

public String getName() {

public String getExt() {

}

}

} }

• JEXIT ("com.ibm.websphere.dtx.test.TestJExit", "Concat", "HCL Transformation", "Extender")

Returns HCL Transformation Extender

Simple primitive types and simple objects

• JEXIT ("com.ibm.websphere.dtx.test.TestJExit", "toDouble", "12")

Returns 12.0

• JEXIT ("com.ibm.websphere.dtx.test.TestJExit", "toNumber", "12")

Returns 12

• JEXIT ("com.ibm.websphere.dtx.test.TestJExit", "returnint")

Returns 9

• JEXIT ("com.ibm.websphere.dtx.test.TestJExit", "returnbyte")

Returns 8

Complex objects

When the function is returning a complex object, the returning object is added to the object pool and the key is returned to the map rule.

• JEXIT ("com.ibm.websphere.dtx.test.TestJExit ", "getPerson")

Returns a key (as a string)

JEXIT ("key", "getName")

Returns Websphere

• JEXIT ("key", "<destroy>")

Deletes the Person object from the JVM memory. The "<destroy>" method must be invoked before the map completes processing.

PUT

The PUT function passes data to a target adapter.

Use PUT to route data within your map using one of the target adapters such as to a messaging system, a database, a file, and so forth.

When the PUT function is used in a map, the default **OnSuccess** action is adapter specific. The default **OnFailure** action is to rollback any changes made during map processing. The default **Scope** will be integral unless the map is defined to run in bursts (which is the case when one or more inputs have the **FetchAs** property set to **Burst**).

Syntax:

PUT (single-text-expression, single-text-expression, single-text-expression)

Meaning:

PUT (adapter_alias , adapter_commands , data_to_send_to_adapter)

Returns:

"None"

The adapter identified by *adapter_alias* is called using the specified *adapter_commands* and passing *data_to_send_to_adapter* as data to the adapter.

The PUT function is not processed if the third argument is zero-sized data or NONE.

To identify whether the function was successful, you can generally use the VALID function with the PUT function. However, for certain adapters such as E-mail and FTP, the success state is not known until after map completion and using the VALID function in such cases might consistently return "success".

Examples

This example illustrates a mapping situation in which a set of messages is being produced in the output (output card #1). However, the ultimate target for these messages is a message queue and the messages need to be placed on the queue one at a time.

To accomplish this, the first output card builds the set of messages and its **Target** is defined as **Sink**. So, this set of messages is constructed in memory, but is discarded after the map completes. A second output card, uses the following **PUT** function to put each output message (from output card# 1), individually, on the output queue.

Message(s) = PUT ("MQS", "-QMN myqueuemgr -QN chips_queue -T", PACKAGE (PaymentMessage:CHIPS_Payment_Message))

- The first argument, MQS, identifies that the data is to be routed using the IBM WebSphere MQ (server) adapter.
- The second argument, "-QMN myqueuemgr -QN chips_queue -T", provides the adapter commands needed by the adapter to put the message on the queue.
- The third argument, PACKAGE, passes the data that is to be sent as the body of the message.

Related functions

- FAIL
- GET
- LASTERRORCODE
- LASTERRORMSG
- VALID

RUN

The RUN function allows you to execute another compiled map from a component or map rule.

You can use RUN to dynamically name source or destination files, or both, or to dynamically pass data to a map. You can also use the RUN function to split the output data into separate files based on some value in the input.

Syntax:

RUN (single-text-expression [, single-text-expression])

Meaning:

RUN (map_to_run [, command_option_list])

Returns:

A single text item

The first argument, map_to_run, is an expression identifying the name of the compiled map (.mmc) to be run.

The *command_option_list* argument is an optional argument that you can use to specify execution commands applicable to the map to be run. *Command_option_list* is a text item containing a series of execution commands separated by a space. Any execution command can be used as part of the *command_option_list* argument. For example, you can send data to another map by using the echo command option (-IEx).

See the Execution Commands documentation for a list of command options.

The result of the RUN function depends on the command options in command_option_list.

Echo command option

- If you use the Echo command option for an output card, the data from that card will be passed back as a text item to the object in the map from which it was run.
- If you use the Echo command option for more than one output card, the data from all echoed cards will be concatenated together and passed back as a text-item to the object in the map from which it was run.
- If you do not use the Echo command option, the return code indicating the status of the map that was run will be passed back to the object in the map from which it was run.

Examples

• RUN ("MyMap", "-IE1s502 " + Invoice:File + " -OF1 install_dir\" + CustomerID:Invoice)

This example runs the **MyMap** map, sending 502-byte fixed-size **Invoice** data as the data source for input card **1**, overriding the filename of output card **1** based on **Customer** data and returns the map return code as the result.

• RUN ("GetDbOpt" , " ")

This example runs the **GetDbOpt** map (with no command options specified) and returns the map return code as the result.

RUN ("DoOneSet", "-A -GR" + ECHOIN(1, Set:InFile)) + " -OF1 OUT_SET." + NUMBERTOTEXT (INDEX (\$)) + " -OE2")

This example runs the DoOneSet map. Command options include the following choices:

• "-A -GR"

The DoOneSet map will produce no Audit Log and restrictions will be ignored.

• ECHOIN(1, Set:InFile)

The ECHOIN function creates the -IE command option for echoing the data represented by Set:InFile to input **1** of the RUN map.

• "-OF1 OUT_SET." + NUMBERTOTEXT (INDEX (\$))

The output file for card **1** of the **DoOneSet** map will be called "OUT_SET." plus a sequence number based on the index of the Set in **InFile**. For example, the first output set will be OUT_SET.1, and so forth.

• " -0E2"

Using the output echo command option, the data built for output card **2** of the **DoOneSet** map will be returned as the result of the RUN function.

An alternative to using the ECHOIN function shown above is using the long version. For example, replace ECHOIN(1, Set:InFile) with:

"-IE1S" + NUMBERTOTEXT (SIZE (Set:InFile) + " " + TEXT (Set:InFile)

Using the Echo input command option (-IE) with the sizing method (Sn) or the ECHOIN function, one Set object of InFile is passed to input card 1 for the DoOneSet map.

Related functions

DDEQUERY

RENAMEFILE

The RENAMEFILE function renames the source file to that of the destination file. If the operation succeeds, the returned value is 0; if it fails, then an operating system-specific error number is returned.

Syntax:

RENAMEFILE (single-text-expression, single-text-expression, single-text-expression, single-text-expression)

Meaning:

RENAMEFILE (source, destination, number_of_retries (max 100), pause_between_retries_in_ms (max 100000))

Returns:

A single number

Related reference

COPYFILE on page 996

HARDLINKFILE

A hard link points or references to a specific space on the hard drive. Multiple files can be hard linked to the same space in the hard drive. If some data is changed on one of the hard linked files, all the other files reflect that change. The HARDLINKFILE function returns the hard link file's command status. On successful execution of this function: 0 is returned; on failure: an operating system-specific error code is returned.

Syntax:

HARDLINKFILE(single-text-expression, single-text-expression, single-text-expression, single-text-expression)

Meaning:

HARDLINKFILE [oldpath, newpath, number_of_retries (max 100), pause_between_retries_in_ms (max 100000)]

Returns:

A single number

Related reference

SOFTLINKFILE on page 995

SOFTLINKFILE

A soft link points to a specific file, which in turn, references to a particular location on the hard drive. The soft link, also known as symbolic link is a second file that exists independently of its target. The SOFTLINKFILE function returns the soft (symbolic) link file's command status. On successful execution of this function: 0 is returned; on failure: an operating system-specific error code is returned.

Syntax:

SOFTLINKFILE(single-text-expression, single-text-expression, single-text-expression, single-text-expression)

Meaning:

SOFTLINKFILE [(oldpath, newpath, number_of_retries (max 100), pause_between_retries_in_ms (max 100000)]

Returns:

A single number

Related reference

HARDLINKFILE on page 995

COPYFILE

The COPYFILE function copies the source file to the destination file. It returns the copy file command status. On successful execution of this function: 0 is returned; on failure: an operating system-specific error code is returned.

Syntax:

COPYFILE(single-text-expression, single-text-expression, single-text-expression)

Meaning:

COPYFILE [source, destination, number_of_retries (max 100), pause_between_retries_in_ms (max 100000)]

Returns:

A single number

Related reference RENAMEFILE on page 994

SLEEP

The SLEEP function suspends the execution of the current map until the time-out interval elapses. The time-out or sleep interval is represented in milliseconds. On successful execution of this function: 0 is returned; on failure: -1 is returned.

Syntax:

```
SLEEP(single-number-expression)
```

Meaning:

SLEEP (the sleep time is in milliseconds)

Returns:

A single number

Inspection functions

ABSENT

The ABSENT function tests for the absence of an object.

Syntax:

ABSENT (single-object-expression)

Meaning:

ABSENT (object_to_test)

Returns:

True or false

ABSENT returns "true" if the object_to_test evaluates to "none". If the object_to_test does not evaluate to "none", the function returns "false".

Examples

- You can use this function to map an object only if another object is absent. For example, you might want to map **BillTo** information to the **ShipTo** fields if the **ShipToName** is absent.
- ABSENT (AreaCode:Phone)

This example evaluates to "true" when **AreaCode:Phone** evaluates to "none" or evaluates to "false" when **AreaCode:Phone** does not evaluate to "none".

Related Functions

• PRESENT

CONTAINSERRORS

The CONTAINSERRORS function tests a valid object to see whether it contains any objects in error.

Syntax:

CONTAINSERRORS (single-object-expression)

Meaning:

CONTAINSERRORS (object_to_test)

Returns:

True or false

The CONTAINSERRORS function returns "true" if any object contained in *object_to_test* is in error; it returns "false" if the *object_to_test* is completely valid.

The input object, itself, is a *valid* input object. This function does *not* evaluate for invalid objects. Therefore, if you have map rule:

CONTAINSERRORS (Invoice:InputFile)

and **Invoice**[1] is valid, **Invoice**[2] is invalid, and **Invoice**[3] is valid, then CONTAINSERRORS evaluates only twice-once for each *valid* instance of **Invoice**.

Examples

• Msg (s) = IF (CONTAINSERRORS (Msg:MailBag) & Type:Msg:MailBag = "PRIORITY", Msg:MailBag, "none")

In this example, if **Msg:MailBag** contains any object in error and **Type:Msg:MailBag** has a value of "PRIORITY", **Msg:MailBag** is mapped; otherwise, "none" is returned for this occurrence of **Msg**. This map rule returns all valid messages (**Msg**) that contain errors with a **Type** of "PRIORITY".

Related functions

- ISERROR
- REFORMAT

DELETEFILE

The DELETEFILE function returns the status of a file deletion command as a single number. DELETEFILE returns 0 for successful file deletion or the appropriate error code if file deletion was not successful.

Syntax:

resourcelib->DELETEFILE (single-text-expression, single-text-expression)

Meaning:

DELETEFILE (filename, number_of_retries, pause_between_retries)

Returns:

A single number

number_of_retries

The number of times the DELETEFILE function is to check for the deleted file. The maximum is 100 retries.

pause_between_retries

The amount of time, in milliseconds, that the function waits between checking for the deleted file. The maximum is 100,000.

Example

```
(resourcelib->DELETEFILE(GETDIRECTORY () + "myfile1.txt","10","1000")
```

ISALPHA

You can use ISALPHA when you need to know whether a text string is all alphabetic characters.

Syntax:

ISALPHA (single-text-expression)

Meaning:

ISALPHA (text_to_test)

Returns:

This function evaluates to a Boolean "true" or "false" and should only be used as a conditional expression within a logical function.

The ISALPHA function tests a text object to see if it is contains all alphabetic characters.

If text_to_test contains only alphabetic characters (for example, A-Z and a-z), ISALPHA evaluates to "true".

If text_to_test contains other than just alphabetic characters, ISALPHA returns "false".

Examples

• IF(ISALPHA ("AnywhereUSA"))

Returns "true"

• IF(ISALPHA ("Anywhere USA"))

Returns "false"

• IF(ISALPHA ("Mr. Brown"))

Returns "false"

Related functions

- ISLOWER
 IEAVEAL PHANUM
- ISNUMBER
 LEAVENUM
- ISUPPER LEAVEPRINT
- LEAVEAL-PHA

ISERROR

The ISERROR function tests an object to see if it is in error

You can use ISERROR to output your data in exactly the same order as it occurs in your input, both the valid data and the data in error. You can also use ISERROR to produce error messages for bad data in the same file in which you map your good data.

Syntax:

ISERROR (single-object-name)

Meaning:

ISERROR (object_to_test)

Returns:

"True" or "false"

ISERROR returns "true" when object_to_test is in error and returns "false" when object_to_test is completely valid.

Examples

 InfoRec (s) = IF (ISERROR (Record:SomeFile), "Bad --> " + REJECT (Record:SomeFile), "Ok --> " + TEXT (Record:SomeFile))

In this example, ISERROR is used to produce a report for *all* **Record** objects in **SomeFile**. If the record is in error, the **InfoRec** will have the text Bad --> followed by the data from the input **Record**. If the record is valid, the **InfoRec** will have the text Ok --> followed by the data from the input **Record**, such as:

```
Ok --> SZ-68839,486 Upgrade Microprocessor,186.86,100,W200
Bad --> MK-19309,,369.43,417,W100
Ok --> KL-20349,PCMCIA Network Adaptor,174.82,29,N300
Ok --> WP-37679,AC Adaptor,39.48,245,E100
Bad --> IL-39890,8MB Memory PCMCIA,390.48,0,S100
```

Related functions

CONTAINSERRORS

ISLOWER

The ISLOWER function tests a text object to see if it contains all lowercase alphabetic characters.

Syntax:

```
ISLOWER (series-text-expression)
```

Meaning:

ISLOWER (text_to_test)

Returns:

This function evaluates to a Boolean "true" or "false" and should only be used as a conditional expression within a logical function.

If text_to_test contains only lowercase alphabetic characters (for example, a-z), ISLOWER evaluates to "true".

If text_to_test contains other than lowercase alphabetic characters, ISLOWER returns "false".

Examples

IF(ISLOWER ("company"))

Returns "true"

• IF(ISLOWER ("pots and pans"))

Returns "false"

IF(ISLOWER ("Andrew"))

Returns "false"

Related functions

- ISALPHA LEAVEAL-
 - PHANUM
- ISNUMBER
 LEAVENUM
- ISUPPER LEAVEPRINT
- LEAVEAL-PHA

ISNUMBER

The ISNUMBER function tests a text object to determine whether it contains all numeric characters.

Syntax:

ISNUMBER (single-text-expression)

Meaning:

ISNUMBER (text_to_test)

Returns:

This function evaluates to a Boolean "true" or "false" and should only be used as a conditional expression within a logical function.

If text_to_test contains only digits (for example, 0-9), ISNUMBER evaluates to "true".

If text_to_test contains other than digits, ISNUMBER evaluates to "false".

Examples

• IF(ISNUMBER("1")

Returns "true"

Related functions

- ISALPHA
 IEAVEAL PHANUM
 ISLOWER
 LEAVENUM
- ISUPPER LEAVEPRINT
- LEAVEAL-PHA

ISUPPER

The ISUPPER function tests a text object to determine whether it contains all uppercase alphabetic characters.

Syntax:

ISUPPER (series-text-expression)

Meaning:

ISUPPER (text_to_test)

Returns:

This function evaluates to a Boolean "true" or "false" and should only be used as a conditional expression within a logical function.

If text_to_test contains only uppercase alphabetic characters (for example, A-Z), ISUPPER evaluates to "true".

If text_to_test contains other than uppercase alphabetic characters, ISUPPER returns "false".

Examples

• IF(ISUPPER ("BOMBAY"))

Returns "true"

• IF(ISUPPER ("CD-ROM"))

Returns "false"

• IF(ISUPPER ("Map Designer"))

Returns "false"

Related functions

• LEAVEAL- PHANUM
• LEAVENUM
LEAVEPRINT

• LEAVEAL-PHA

MEMBER

Use MEMBER when you need to know whether an object occurs within a series.

The MEMBER function searches a series, looking for a single specified object in the series. If any object in the series matches the specified object, MEMBER returns "true". If there is no match, MEMBER returns "false".

Syntax:

MEMBER (single-object-expression, series-object-expression)

MEMBER (single-object-expression , { literal, literal ... })

Meaning:

MEMBER (object_to_look_for , series_of_objects_to_look_at)

Returns:

"True" or "false"

MEMBER returns "true" if object_to_look_for matches one of the values in series_of_objects_to_look_at.

It returns "false" if object_to_look_for does not match at least one of the values in series_of_objects_to_look_at.

The two arguments, *object_to_look_for* and *series_of_objects_to_look_at*, must be objects of the same item interpretation or the same group type. For example, if *object_to_look_for* is a date/time item, *series_of_objects_to_look_at* must be a series of date/time items.

Examples

• MEMBER (EntityIDCode:Name, {"BT", "ST"})

This example tests whether EntityIDCode has one of a particular set of literal values.

• MEMBER (Store#, EntityIDCode:Name)

This example tests whether Store# has the same value as any EntityIDCode:Name.

Related functions

- EXTRACT
- LOOKUP

NOT

Use the NOT function to test a condition and have it return the inverse of its "true" or "false" result. For example, you want the function to return "true" if the condition results in "false".

Syntax:

NOT (single-condition-expression)

Meaning:

NOT (condition_to_evaluate)

Returns:

"True" or "false"

NOT returns "true" if the condition evaluates to "false" and returns "false" if the condition evaluates to "true".

Examples

• NOT (Qty:::InputFile = 0)

This example returns "false" if the **Qty** equals 0 (the condition is true) and returns "true" if **Qty** does not equal 0 (the condition is false).

• IF (NOT (PRESENT (StartDate)), "Unknown", "none")

This example returns "unknown" if StartDate is not present and returns "none" if StartDate is present.

Another way to test that an object is not present is to use the ABSENT function.

OFFSET

Use the OFFSET function when you need to know the position of a particular data object within its card object.

OFFSET returns an integer representing the offset of the specified object within the data.

Syntax:

OFFSET (single-object-expression)

Meaning:

OFFSET (object_whose_offset_is_needed)

Returns:

A single integer

OFFSET returns the offset, in bytes, of the specified object within its card object, beginning at offset 0. For an object that has an initiator, the offset will apply to the first byte of the data. For an object that is right-justified with pad characters, OFFSET will return the offset of the first byte of data.

The OFFSET function works the same for output objects as it does for input objects.

Examples

OFFSET (Application:LoanData)

In this example, if the first character of the first occurrence of the object **Application** occurs 210 bytes from offset 0 within **LoanData**, the OFFSET function returns 210.

Related function

SIZE

OR

Use the OR function to test whether one of a series of conditions is true.

OR evaluates a series of conditions and returns "true" if at least one evaluates to "true"; otherwise returns "false".

Syntax:

OR (series-condition-expression)

Meaning:

OR (conditions_to_evaluate)

Returns:

"True" or "false"

OR evaluates to "true" if *any* member of the argument evaluates to "true" and evaluates to "false" if *all* members of the argument evaluate to "false".

Examples

Order(s)=IF (OR (Store:Table = Store#:Order:Input), Order:Input)

This example produces an Order if the Store# of an Order in Input matches any Store in Table.

Related function

• ALL

PARTITION

The PARTITION function checks to see if an occurrence of an object belongs to a certain partition. If the object is that partition, "true" is returned. Otherwise, "false" is returned.

Syntax:

PARTITION (single-object-expression, single-simple-object-name)

Meaning:

PARTITION (partitioned_object, simple_name_of_partition_to_check_for)

Returns:

"True" or "false"

PARTITION returns "true" if the data object of *partitioned_object* belongs to the partition represented by *simple_name_of_partition_to_check_for*. Otherwise, PARTITION returns "false".

Examples

• Assume that **Transaction** has been partitioned into three partitioned subtypes: **Invoice**, **Order**, and **Remittance**, as shown.

The following rule could be used to detect whether a given Transaction is an Invoice:

PARTITION (Transaction:.:Batch, Invoice)

If the **Transaction** is an **Invoice**, PARTITION returns "true". If the **Transaction** is not an **Invoice** (for example, it is an **Order** or a **Remittance**), PARTITION returns "false" for that **Transaction**.

Related function

GETPARTITIONNAME

PRESENT

The PRESENT function tests for the presence of an object.

PRESENT is commonly used with the IF function in a map rule to provide conditional logic. For example, if the object is present, do this; otherwise, do something else.

Similarly, PRESENT is commonly used with the WHEN function in component rules to provide conditional validation logic.

Syntax:

PRESENT (single-object-expression)

Meaning:

PRESENT (object_to_look_for)

Returns:

"True" or "false"

PRESENT returns "true" if the input argument does *not* evaluate to "none"; the object is present. It returns "false" if the input argument evaluates to "none"; the object is not present.

Examples

• PRESENT (Trailer:File)

This example returns "true" if Trailer is present and returns "false" if Trailer is absent.

• IF (PRESENT(MiddleInitial:.:Input), MiddleInitial:.:Input, "***")

This example in a map rule maps **MiddleInitial** if it is present. If **MiddleInitial** is not present, three asterisks are mapped.

• WHEN (PRESENT (AreaCode Field), PRESENT (PhoneNo Field))

In this example, PRESENT is being used in conjunction with the WHEN function in a component rule to determine whether a particular object is valid.

Related functions

- ABSENT
- IF
- WHEN

SIZE

The SIZE function returns an integer representing the size of a specified object, exclusive of any pad characters.

Syntax:

SIZE (single-object-expression)

Meaning:

SIZE (object_whose_size_is_needed)

Returns:

A single integer

The SIZE function returns the size, in bytes, of *object_whose_size_is_needed*. The byte size returned does not include any pad characters that might be in the object, but does include separators and signs.

The size of a group is the size, beginning with the first character of the first component and ending with the last character of the last component, of the group. If the group has delimiters, the infix delimiters are included in the size.

Examples

• SIZE (Transaction)

Returns 8000 if the size of Transaction (without pad characters) is 8000 bytes

Using SIZE with NORMXML

If the SIZE function is used with the NORMXML function to determine the size of the specified object after NORMXML has removed the XML formatting from the input XML fragment, the SIZE operation calculates the size of the data in Unicode, since the NORMXML function converts the input data to Unicode before it removes the XML formatting. The returned size does not match the size that would have been calculated if the data remained in its original character set, unless the original character set was Unicode.

TESTOFF

The TESTOFF function tests a specified bit in a binary number item to see whether it is off.

Syntax:

TESTOFF (single-binary-number-expression, single-integer-expression)

Meaning:

TESTOFF (binary_number_to_test , bit_to_test)

Returns:

"True" or "false"

The value of *bit_to_test* specifies which bit of *binary_number_to_test* should be tested for the value 0. If *bit_to_test* has the value 1, it refers to the leftmost bit of *binary_number_to_test*.

The TESTOFF function returns "true" if the specified bit is off and returns "false" if the specified bit is on.

If bit_to_test is less than one or greater than the number of bits of binary_number_to_test, TESTOFF returns "false".

Examples

• TESTOFF (A, 16)

Assume **A** is the two-byte binary value of "1", which is all zeros except for bit **16**. The binary representation of the value in **A** is 0001.

This example returns "false".

• TESTOFF (A, 20)

Returns "false" because bit 20 does not exist.

TESTON

The TESTON function tests a specified bit in a binary number to see if it is on.

Syntax:

TESTON (single-binary-number-expression, single-integer-expression)

Meaning:

TESTON (binary_number_to_test ,bit_to_test)

Returns:

"True" or "false"

The value of *bit_to_test* specifies the bit of *binary_number_to_test* to test for the value 1. If *bit_to_test* has the value 1, it refers to the leftmost bit of *binary_number_to_test*.

The function returns "true" if the specified bit is on; it has the value 1. It returns "false" if the specified bit is off; it has the value 0.

If bit_to_test is less than one or greater than the number of bits of binary_number_to_test, TESTON returns "false".

Examples

• TESTON (A, 16)

Assume **A** is the two-byte binary value of "1", which is all zeros except for bit **16**. The binary representation of the value in **A** is 0001.

This example returns "true".

• TESTON (A , 20)

Returns "false" because bit 20 does not exist in a two-byte value.

VALID

You can use the VALID function to perform conditional processing based on whether an external interface function executes successfully.

VALID returns the result of the first argument if it is valid; otherwise, returns the second argument.

Syntax:

VALID (single-text-expressions, single-general-expression)

Meaning:

```
VALID (function_that_can_fail, return_value_if_function_fails)
```

Returns:

A single text expression

VALID returns the result of the evaluation of *function_that_can_fail* if it is valid. If the function fails, VALID returns *return_value_if_function_fails*.

The following functions can fail:

- DBLOOKUP
 GET
- DBQUERY PUT
- DDEQUERY
 RUN
- EXIT

Examples

• SomeObject = VALID (RUN ("mymap.mmc" , "-OF1 mydata.txt") , FAIL ("My RUN failed!"))

If the RUN function returns an error return code, the VALID functions returns none, the map aborts, and the message My RUN failed! is reported under Execution Summary in the execution audit log.

Related functions

- DBLOOKUP
- DBQUERY
- DDEQUERY

Logical functions

ALL

The ALL function evaluates a series of conditions and returns "true" if they all evaluate to "true"; otherwise returns "false".

Syntax:

ALL (series-condition-expression)

Meaning:

ALL (conditions_to_evaluate)

Returns:

True or false

The ALL function evaluates to "true" if *all* members of the input argument evaluate to "true".; it evaluates to "false" if *any* member of the input argument is "false".

Examples

- You can use ALL when you want to test whether all conditions of a series are true.
- PO (s)=IF (ALL(PO#:Line:Order = PO#:Line:Order[1]), Order, "none")

If each and every **PO#** matches the **PO#** of the first **Order**, ALL evaluates to "true". Otherwise, ALL evaluates to "false".

Related functions

- NOT
- OR

BINDABS

Use this function in a component rule for the implementation of binding and iterative evaluation. The implementation of binding ensures that when there are multiple references to a component in a rule, all references are to the same instance of that component. The implementation of iterative evaluation ensures that the rule is evaluated using all possible combinations of type references.

Do not use this function unless you have a clear understanding of the behavior.

Syntax:

BINDABS (Boolean_expression)

Meaning:

BINDABS (component rule)

Returns:

A Boolean "true" or "false"

Note: It is not necessary to use the BINDABS function for iterative behavior with the following functions because these functions already iterate: COUNT, COUNTABS, INDEX, MEMBER, MAX, MIN, SUM, and SERIESTOTEXT.

How it works

When the evaluation starts and the BINDABS function is encountered at the beginning of the component rule, binding is enforced and the rule is iterated across all valid combinations of objects specified in the rule.

BINDABS must be positioned first in the component rule and the entire component rule must be enclosed. Any other use of this function will have no effect.

When using BINDABS, the evaluation order is the same as mapping. Rules that contain both a normal instance and a last instance for the first instance of the type are not evaluated.

Example

BINDABS (Qty:LineItem:Order * Price:LineItem:Order = ExtendedPrice:LineItem:Order)

As a result of binding, the Qty, Price, and ExtendedPrice elements in this example are all in the same LineItem of the same Order. As a result of iteration, all line items of all orders are checked.

EITHER

The EITHER function returns the result of the first argument that does not evaluate to "none".

Syntax:

EITHER (single-general-expression {, single-general-expression })

Meaning:

EITHER (try_this { , if_none_try_this })

Returns:

A single object

The EITHER return methods work in the following ways:

Returns...

When...

try_this

try_this does not evaluate to "none"

if_none_try_this

try_this evaluates to "none"

the next if_none_try_this

the first if_none_try_this evaluates to "none"

Note: The Design Studio compiler does not validate the second argument or subsequent arguments against the type tree.

Examples

• EITHER (OrderDate Field , CURRENTDATE ())

If **OrderDate Field** does not evaluate to "none", it is returned. If **OrderDate Field** evaluates to "none", the current system date (using CURRENTDATE) is returned.

• EITHER (LOOKUP (PriorityCd:Msg , CustID:Msg = "93X") , 8)

This example returns the result of the LOOKUP if that result does not evaluate to "none"; otherwise, it returns the second argument of 8.

 EITHER (IF (SomeCode = "C", CustomerID:Input), IF (SomeCode = "S", SupplierID:Input), IF (SomeCode = "O", Reference#:Input), "####")

If SomeCode is C and CustomerID:Input has a value, EITHER returns the value of CustomerID. Otherwise, if SomeCode is S and CustomerID:Input has a value, EITHER returns the value of SupplierID. Otherwise, if SomeCode is O and Reference#:Input has a value, EITHER returns the value of Reference#. If none of those conditions result in a value, EITHER returns "####".

• You can use EITHER when you want a default value when an expression evaluates to "none" and the expression might cause common arguments to produce an unintended result. For example, use:

EITHER (LOOKUP (PriorityCd:Msg, CustID:Msg = "93X"), 8)

-instead of-

IF (PRESENT (LOOKUP (PriorityCd:Msg, CustID:Msg = "93X")), LOOKUP (PriorityCd:Msg, CustID:Msg = "93X"), 8)

IF

You can use the IF function for conditional logic. For example, to return one of two objects depending on the evaluation of a condition.

IF evaluates a conditional expression, returning one value if true, another if false.

Syntax:

 ${\sf IF}\ ({\sf single-condition-expression}\ ,\ {\sf single-general-expression}\)$

[, single-general-expression])

Meaning:

IF (test_this , result_if_true [, result_if_false])

Returns:

A single item or single group

If test_this evaluates to "true", the result is result_if_true.

Otherwise, if *test_this* evaluates to "false", the result is *result_if_false*. If no *result_if_false* is specified, this evaluates to "none".

The *result_if_true* and *result_if_false* arguments must correspond to the same item interpretation or the same group type or either can be "none". For example, if *result_if_true* evaluates to a number, *result_if_false* must also evaluate to a number. If *result_if_true* evaluates to a **LineItem** group, *result_if_false* must also evaluate to a **LineItem** group.

Examples

```
• IF (Quantity:LineItem:PO > 500, "PRIORITY", "REGULAR")
```

This example tests the **Quantity** value. If that **Quantity** is > 500, the IF function evaluates to the value PRIORITY. If that **Quantity** is <= 500, the IF function evaluates to the value, REGULAR.

```
• IF (Status:Order = "Special", "SPCL")
```

This example tests the **Status** value. If the **Status** is Special, the IF function evaluates to the value, SPCL. Otherwise, it evaluates to "none". Notice that this rule is equivalent to

IF (Status:Order = "Special", "SPCL", "none")

ISALPHA

You can use ISALPHA when you need to know whether a text string is all alphabetic characters.

Syntax:

ISALPHA (single-text-expression)

Meaning:

ISALPHA (text_to_test)

Returns:

This function evaluates to a Boolean "true" or "false" and should only be used as a conditional expression within a logical function.

The ISALPHA function tests a text object to see if it is contains all alphabetic characters.

If text_to_test contains only alphabetic characters (for example, A-Z and a-z), ISALPHA evaluates to "true".

If text_to_test contains other than just alphabetic characters, ISALPHA returns "false".

Examples

• IF(ISALPHA ("AnywhereUSA"))

Returns "true"

• IF(ISALPHA ("Anywhere USA"))

Returns "false"

• IF(ISALPHA ("Mr. Brown"))

Returns "false"

Related functions

- ISLOWER • LEAVEAL-PHANUM ISNUMBER LEAVENUM • ISUPPER LEAVEPRINT
- LEAVEAL-PHA

ISLOWER

The ISLOWER function tests a text object to see if it contains all lowercase alphabetic characters.

Syntax:

ISLOWER (series-text-expression)

Meaning:

ISLOWER (text_to_test)

Returns:

This function evaluates to a Boolean "true" or "false" and should only be used as a conditional expression within a logical function.

If text_to_test contains only lowercase alphabetic characters (for example, a-z), ISLOWER evaluates to "true".

If text_to_test contains other than lowercase alphabetic characters, ISLOWER returns "false".

Examples

• IF(ISLOWER ("company"))

Returns "true"

• IF(ISLOWER ("pots and pans"))

Returns "false"

• IF(ISLOWER ("Andrew"))

Returns "false"

Related functions

- ISALPHA LEAVEAL-PHANUM
- ISNUMBER
 LEAVENUM
- ISUPPER LEAVEPRINT
- LEAVEAL-PHA

ISNUMBER

The ISNUMBER function tests a text object to determine whether it contains all numeric characters.

Syntax:

ISNUMBER (single-text-expression)

Meaning:

ISNUMBER (text_to_test)

Returns:

This function evaluates to a Boolean "true" or "false" and should only be used as a conditional expression within a logical function.

If text_to_test contains only digits (for example, 0-9), ISNUMBER evaluates to "true".

If text_to_test contains other than digits, ISNUMBER evaluates to "false".

Examples

• IF(ISNUMBER("1")

Returns "true"

Related functions

- ISALPHA LEAVEAL-PHANUM
- ISLOWER
 LEAVENUM
- ISUPPER LEAVEPRINT

• LEAVEAL-PHA

ISUPPER

The ISUPPER function tests a text object to determine whether it contains all uppercase alphabetic characters.

Syntax:

ISUPPER (series-text-expression)

Meaning:

ISUPPER (text_to_test)

Returns:

This function evaluates to a Boolean "true" or "false" and should only be used as a conditional expression within a logical function.

If text_to_test contains only uppercase alphabetic characters (for example, A-Z), ISUPPER evaluates to "true".

If text_to_test contains other than uppercase alphabetic characters, ISUPPER returns "false".

Examples

• IF(ISUPPER ("BOMBAY"))

Returns "true"

• IF(ISUPPER ("CD-ROM"))

Returns "false"

• IF(ISUPPER ("Map Designer"))

Returns "false"

Related functions

• ISALPHA	• LEAVEAL- PHANUM
• ISLOWER	• LEAVENUM
• ISNUMBER	• LEAVEPRINT

• LEAVEAL-PHA

NOT

Use the NOT function to test a condition and have it return the inverse of its "true" or "false" result. For example, you want the function to return "true" if the condition results in "false".

Syntax:

```
NOT (single-condition-expression)
```

Meaning:

NOT (condition_to_evaluate)

Returns:

"True" or "false"

NOT returns "true" if the condition evaluates to "false" and returns "false" if the condition evaluates to "true".

Examples

• NOT (Qty:::InputFile = 0)

This example returns "false" if the **Qty** equals 0 (the condition is true) and returns "true" if **Qty** does not equal 0 (the condition is false).

• IF (NOT (PRESENT (StartDate)), "Unknown", "none")

This example returns "unknown" if StartDate is not present and returns "none" if StartDate is present.

Another way to test that an object is not present is to use the ABSENT function.

OR

Use the OR function to test whether one of a series of conditions is true.

OR evaluates a series of conditions and returns "true" if at least one evaluates to "true"; otherwise returns "false".

Syntax:

OR (series-condition-expression)

Meaning:

OR (conditions_to_evaluate)

Returns:

"True" or "false"

OR evaluates to "true" if *any* member of the argument evaluates to "true" and evaluates to "false" if *all* members of the argument evaluate to "false".

Examples

Order(s)=IF (OR (Store:Table = Store#:Order:Input), Order:Input)

This example produces an Order if the Store# of an Order in Input matches any Store in Table.

Related function

• ALL

WHEN

You can use the WHEN function in a component rule to test for the validity of one object based on another object.

WHEN evaluates a condition. Then, based on that evaluation, evaluates another condition and returns "true" or "false".

Syntax:

WHEN (single-condition-expression, single-condition-expression[, single-condition-expression])

WHEN (condition1, condition2[, condition3])

Returns:

"True" or "false"

The following statements summarize how the WHEN function works:

- Returns "true" if condition1 and condition2 both evaluate to "true".
- Returns "true" if condition1 evaluates to "false" and there is no condition3 or if condition1 evaluates to "false" and condition3 evaluates to "true".
- Returns "false" if condition1 evaluates to "true" and condition2 evaluates to "false".
- Returns "false" if both condition1 and condition3 evaluate to "false".

Evaluation of the three arguments:

Condition 1	Condition 2	Condition 3	WHEN returns:
True	True		True
False			True
False		True	True
True	False		False
False		False	False

Examples

• WHEN (ABSENT(CatalogueField), ABSENT (QuantityField))

Returns "true" when CatalogueField and QuantityField are both absent

• WHEN (PRESENT(ShipDate), PRESENT(InStock), PRESENT(BackOrderDate))

Returns "false" when ShipDate and BackOrderDate are both absent

Lookup and reference functions

CHOOSE

The CHOOSE function returns the object within a series whose position in the series corresponds to a specified number.

Syntax:

CHOOSE (series-object-name, single-integer-expression)

CHOOSE (from_these_objects , pick_the_nth_one)

Returns:

A single object whose index within the from_these_objects series matches the number specified by pick_the_nth_one. If that member of the series does not exist, CHOOSE returns "none".

You can use CHOOSE to use a variable value to specify the index for a particular object from a series. The CHOOSE function does not operate on a series object that was returned by another function, such as EXTRACT.

Examples

CHOOSE (Row:DBSelect, 2)

Returns the second Row

CHOOSE (Set:Claim , INDEX (Row:Header))

Returns the Set within the Claim that corresponds to the index of the Row of Header.

Related function

LOOKUP

DBLOOKUP

The DBLOOKUP function executes an SQL statement against a database. The SQL statement can be any permitted by your database management system or ODBC driver.

When the DBLOOKUP function is used in a map, the default **OnSuccess** action is adapter specific. The default **OnFailure** action is to rollback any changes made during map processing. The default **Scope** will be integral unless the map is defined to run in bursts (which is the case when one or more inputs have the **FetchAs** property set to **Burst**).

There are two ways to specify arguments for DBLOOKUP.

You can use DBLOOKUP to execute an SQL statement when you want to execute a SELECT statement to retrieve a specific column value in a large table in a database using the value of another input, rather than defining the entire table as an input card and using the LOOKUP, SEARCHDOWN, or SEARCHUP functions.

You can use DBLOOKUP to execute an SQL statement when you want to execute a SELECT statement to retrieve a specific column value from a table or database that might vary based on a parameter file. Using Meaning 2 of the DBLOOKUP function allows these parameters to be dynamically specified at run time.

Syntax:

DBLOOKUP (single-text-expression, single-text-expression, [single-text-literal])

- 1. DBLOOKUP (SQL_statement, mdq_filename, database_name)
- 2. DBLOOKUP (SQL_statement, parameters)

Returns:

A single text item

The DBLOOKUP function returns the results of the query in the same format as a query specified for a map input card, except that it does not include the last carriage return/linefeed. Because this information is removed, it is easier to make use of a single value extracted from a database.

Arguments for meaning 1

DBLOOKUP (SQL_statement, mdq_filename, database_name)

SQL_statement

The first argument is an SQL statement as a text string. This can be any valid SQL statement permitted by your database management system and supported by your database-specific driver. In addition to a fixed SQL statement, this argument can be a concatenation of text literals and data objects, enabling the concatenation of data values into your SQL statement.

mdq_filename

The second argument is the name of a database query file (**.mdq**) produced by the Database Interface Designer. It contains the definition of the database that the SQL statement is to be executed against. If the **.mdq** file is in a directory other than the directory of the map, the path must be specified.



Note: The .mdq file is accessed at map build time and is not needed at run time.

database_name

The third argument is the name of a database in the database query file (**.mdq**) as defined in the Database Interface Designer.

If used in this way, both the .mdq filename and database name must be literals.

Arguments for meaning 2

DBLOOKUP (SQL_statement, parameters)

SQL_statement

The first argument is an SQL statement as a text string. This can be any valid SQL statement permitted by your database management system and supported by your database-specific driver. In addition to a fixed SQL

statement, this argument can be a concatenation of text literals and data objects, enabling the concatenation of data values into your SQL statement.

parameters

The second argument is a set of parameters, either:

• -MDQ mdqfilename -DBNAME dbname

-or-

• -DBTYPE database_type [database specific parameters]

The keyword -MDQ is followed by the name of the database query file (**.mdq**) produced by the Database Interface Designer. This **.mdq** file contains the definition of the database. If the **.mdq** file is in a directory other than the directory of the map, the path must be specified. The **.mdq** filename is followed by the keyword -DBNAME and the database name as specified in the Database Interface Designer.

Using this syntax, the .mdq file is accessed at run time and must be present.

The keyword -DBTYPE is followed by a keyword specifying the database type (for example, ODBC or ORACLE) followed, optionally, by database-specific parameters.

This syntax does not use an **.mdq** file, because the database-specific parameters provide the information required to connect to the database. See the Resource Adapters documentation for detailed information about the database-specific parameters that can be specified.

When used with Meaning 2, DBLOOKUP must conform to these rules:

- All keywords (for example, -DBTYPE) can be upper or lowercase, but not mixed.
- A space is required between the keyword and its value (for example, -DBTYPE ODBC).
- The order of the keywords is not important.

All database-specific parameters are optional.

Examples

Assume that you have a table named "PARTS" that contains the following data:

	PART_NUMBER	
1		1/4" x 3" Bolt
2		1/4" x 4" Bolt

Assume that this database has been defined using the Database Interface Designer in a file named **mytest.mdq** and that the name of the database, as specified in the **.mdq** file, is **PartsDB**.

PART_NAME

• DBLOOKUP ("SELECT PART_NAME from PARTS where PART_NUMBER =1", "mytest.mdq", "PartsDB") Returns: 1/4" x 3" Bolt

Using Meaning 2, you can specify the DBLOOKUP this way:

• DBLOOKUP("SELECT PART_NAME from PARTS where PART_NUMBER =1", "-MDQ mytest.mdq -DBNAME PartsDB")

where both the .mdq file name and database name is specified.

Using Meaning 2, you can also specify the database type and the appropriate database-specific parameters:

• DBLOOKUP("SELECT PART_NAME from PARTS where PART_NUMBER =1", "-DBTYPE ORACLE -CONNECT MyDB -USER janes ")

Related functions

- DBQUERY
- EXTRACT
- FAIL
- LASTERRORCODE
- LASTERRORMSG
- LOOKUP
- SEARCHDOWN
- SEARCHUP
- VALID

For more examples using the DBLOOKUP function, see the Database Interface Designer documentation.

DBQUERY

The DBQUERY function executes an SQL statement against a database. The SQL statement can be any permitted by your database management system or ODBC driver.

When the DBQUERY function is used in a map, the default **OnSuccess** action is adapter specific. The default **OnFailure** action is to rollback any changes made during map processing. The default **Scope** will be integral unless the map is defined to run in bursts (which is the case when one or more inputs have the **FetchAs** property set to **Burst**).

There are two ways to specify the arguments for DBQUERY. You can use DBQUERY [*Meaning 1*] to execute an SQL statement when you want to look up information in a database using a parameterized query that is based on another value in your data. If your SQL statement is a SELECT statement, the DBQUERY function might be used in conjunction with the RUN function to issue dynamic SELECT statements whose results can be used as input to another map.

You can also use the DBQUERY function [*Meaning 2*] to execute an SQL statement when the database, table, or other database parameters might vary; perhaps being supplied by a parameter file.

Syntax:

DBQUERY (single-text-expression , single-text-expression , [single-text-literal])

Meaning:

- 1. DBQUERY (SQL_statement, mdq_filename, database_name)
- 2. DBQUERY (SQL_statement, parameters)

Returns:

A single text item

If your SQL statement is a SELECT statement, the results of the query in the same format as a query specified as a map input card, including row delimiters and terminators, and so on.

If your SQL statement is anything other than a SELECT statement, "none".

Arguments for meaning 1

DBQUERY (SQL_statement , mdq_filename , database_name)

SQL_statement

The first argument is an SQL statement as a text string. This can be any valid SQL statement that is permitted by your database management system and supported by your database-specific driver. In addition to a fixed SQL statement, this argument can be a concatenation of text literals and data objects, enabling the concatenation of data values into your SQL statement.

mdq_filename

The second argument is the name of a database query file (**.mdq**) produced by the Database Interface Designer. It contains the definition of the database that the SQL statement is to be executed against. If the **.mdq** file is in a directory other than the directory of the map, the path must be specified.



Note: The .mdq file is accessed at map build time and is not needed at run time.

database_name

The third argument is the name of a database in the database query file (**.mdq**) as defined in the Database Interface Designer.

If used in this way, both the .mdq filename and database name must be literals.

Arguments for meaning 2

DBQUERY (SQL_statement, parameters)

- The first argument is an SQL statement as a text string. This can be any valid SQL statement that is permitted by your database management system and supported by your database-specific driver. In addition to a fixed SQL statement, this argument can be a concatenation of text literals and data objects, enabling the concatenation of data values into your SQL statement.
- The second argument is a set of parameters, either:
 - -MDQ mdqfilename -DBNAME dbname

-or-

-DBTYPE database_type [database specific parameters]

The keyword -MDQ is followed by the name of the database query file (.**mdq**) produced by the Database Interface Designer. This **.mdq** file contains the definition of the database. If the **.mdq** file is in a directory other than the directory of the map, the path must be specified. The **.mdq** filename is followed by the keyword -DBNAME and the database name as specified in the Database Interface Designer.



Note: Using this syntax, the .mdq file is accessed at run time and must be present.

The keyword -DBTYPE is followed by a keyword specifying the database type (for example, ODBC or ORACLE) followed, optionally, by database-specific parameters.

Note: This syntax does not use an **.mdq** file, because the database-specific parameters provide the information required to connect to the database. See the appropriate database adapter documentation for detailed information about database-specific parameters.

When used with Meaning 2, DBQUERY must conform to these rules:

- All keywords (for example, -DBTYPE) can be upper or lower case, but not mixed.
- A space is required between the keyword and its value (for example, -DBTYPE ODBC).
- The order of the keywords is not important.

All database-specific parameters are optional.

Examples

Assume that you have a table named "PARTS" that contains the following data:

PART_NUMBER

PART_NAME

1

1/4" x 3" Bolt

PART_NUMBER

PART_NAME

2

1/4" x 4" Bolt

Also assume that this database has been defined using the Database Interface Designer in a file named **mytest.mdq** and that the name of the database, as specified in the **.mdq** file, is **PartsDB**.

DBQUERY ("SELECT * from PARTS" , "mytest.mdq" , "PartsDB")

Returns 1|1/4" x 3" Bolt<cr><lf>2|1/4" x 4" Bolt<cr><lf>

where <cr><lf> is a carriage return followed by a line feed.

Using Meaning 2, you can also specify the DBQUERY this way:

DBQUERY ("SELECT * from PARTS" , "-MDQ mytest.mdq -DBNAME PartsDB")

where both the .mdq file name and database name are specified.

Or, specify it this way, using Meaning 2 by specifying the database type and the appropriate database-specific parameters:

DBQUERY ("SELECT * from PARTS" , "-DBTYPE ORACLE -CONNECT MyDB -USER janes")

Assume that you have an input file containing one order record. To map that order to another proprietary format, you also have a parts table with pricing information for every part for every customer, a very large table. Rather than using the entire parts table as the input to your map, you might use the RUN function with a DBQUERY to dynamically select only those rows from the parts table corresponding to the customer in the order file, as follows:

```
RUN ( "MapOrder.MMC" ,
    "IE2" + DBQUERY ( "SELECT * FROM Parts WHERE CustID = "
    + CustomerNo:OrderRecord:OrderFile + " ORDER BY PartNo" ,
    "PartsDB.MDQ", "PartsDatabase" ) )
```

Related functions

- DBLOOKUP
- EXTRACT
- FAIL
- LASTERRORCODE
- LASTERRORMSG
- LOOKUP
- SEARCHUP
- SEARCHDOWN
- VALID

DDEQUERY

The DDEQUERY function allows you to interface to other Windows applications such as Trading Partner PC, Excel, and so forth, provided that certain criteria are met. For example, if you receive an Excel spreadsheet file, you must have

the appropriate version of the Excel application installed (that is compatible with the file received) and the application must be open.

Syntax:

DDEQUERY (single-text-expression , single-text-expression , single-text-expression)

Meaning:

DDEQUERY (application_name, topic, text)

Returns:

A single text item from an application

Examples

• DDEQUERY ("excel", "[MKTPRICE.XLS]Sheet1", "R8C1:R14C3")

In this example, DDEQUERY is used to get data from an Excel spreadsheet. The third argument, **R8C1:R14C3**, specifies the location of the data in the spreadsheet. (In Excel, the 8th row, 1st column to the 14th row, 3rd column is A8:C14.) The content of this spreadsheet range is returned as a single text item.

This example assumes that the application, the map, and the spreadsheet all reside in the same directory. If they are not in the same directory you must add the path. For example:

DDEQUERY ("excel", "c:\spreadsheet[MKTPRICE.XLS]Sheet1", "R8C1:R14C3")

DDEQYUERY ("tppc","PartnerX","BGyourEDIode")

In this example, DDEQUERY is used as a request to Trading Partner PC.

Related functions

- EXIT
- FAIL
- GET
- LASTERRORCODE
- LASTERRORMSG
- PUT
- RUN
- VALID

EXTRACT

Use EXTRACT whenever you need only particular members of a series returned-those that meet a certain condition. An example might be only POs that contain back-ordered items.

The EXTRACT function can only be used in a map rule. It cannot be used in a component rule.

The EXTRACT function returns all members of a series for which a specified condition is true.

Syntax:

EXTRACT (series-object-expression, single-condition-expression)

Meaning:

EXTRACT (objects_to_extract, condition_to_evaluate)

Returns:

A series object.

The result is each member of *series_to_search* for which the condition specified by *condition_to_evaluate* evaluates to "true". EXTRACT returns "none", if no member of *series_to_search* has a corresponding *condition_to_evaluate* that evaluates to "true".

Examples

• EXTRACT (PO:Transaction , Store# = Location:PO:Transaction)

This example returns all POs, individually, whose Location is a particular Store#.

• EXTRACT (Row:DBSelect , ProcessFlag Column:Row:DBSelect = "Y")

This example returns all Rows that have a ProcessFlag Column value of "Y".

Related Functions

- CHOOSE
- LOOKUP
- SEARCHDOWN
- SEARCHUP

GETANDSET

You can use GETANDSET when you have an input file that keeps track of control information that serves as an input to your map and the control information in the file needs to be updated based on processing that occurs in your map.

The GETANDSET function gets a fixed length value from the input data stream, updates that value in the input data stream, and returns either the original or updated value.

Syntax:

GETANDSET (single-fixed-size-item-object-name, single-item-expression, single-integer-expression)

Meaning:

GETANDSET (original_value ,new_value, integer_that_determines_which_value_to_return)

Returns:

A single-fixed-size-item and replaces the original value in the input data stream.

This function does not support decrementing integers past 0 into negative numbers.

GETANDSET updates an input by finding the object represented by *original_value* and replacing it with the value represented by the *new_value*. The function returns either the *original_value* or the *new_value*, depending on the value of the *integer_that_determines_which_value_to_return*. For example,

- If integer_that_determines_which_value_to_return has the value 1, original_value is returned.
- If integer_that_determines_which_value_to_return has the value 2, new_value is returned.
- If integer_that_determines_which_value_to_return has any other value, original_value is returned.
- If one of the input arguments evaluates to "none", GETANDSET returns "none".

The original value specified for *new_value* must be a fixed size item. During map execution, the original value is updated to reflect the evaluation of GETANDSET. When the source is a file, that file will be updated after map completion. However, if the source is a database, message, or application, the content of the source is in memory and the source, itself, is not updated.

Examples

• New Tracking# = GETANDSET (Tracking#:Card, Tracking#:Card + 3, 1)

This rule finds the object **Tracking#:Card** (assume that it has the value 6), adds 3 to it, giving 9, and replaces the 6 with the 9 in the data location of **Tracking#:Card**. Subsequent references to **Tracking#:Card** will find its value to be 9. If **Card** is an input card whose source is a file, the file is rewritten with the new value.

Because the third input argument (*integer_that_determines_which_value_to_return*) is 1, the returned value is the original value of 6.

GETDIRECTORY

The GETDIRECTORY function returns the full path (directory) for the compiled map file or the source or destination associated with a specified card object.

You can use GETDIRECTORY in a map rule or component rule when you need the full path (directory) of either the compiled map or of a data source or destination.

Syntax:

```
GETDIRECTORY ([ single-simple-object-name ] )
```

Meaning:

GETDIRECTORY ([card_or_object_for_which_directory_is_needed])

Returns:

A single text item

Without an argument, GETDIRECTORY returns the full path associated with the compiled map.

With an argument, the following occurs:

- From a map rule, the function returns the full path of the source or destination that is associated with the card. In a map rule, the argument must be the name of the card for which to get the directory.
- From a component rule, the function returns the full path of the source or destination that is associated with the active source or destination.

The GETDIRECTORY command without arguments will return the directory of the compiled map, regardless of whether it is used in a map rule or in a component rule.

Examples

GETDIRECTORY (OrderFile)

If the card OrderFile is associated with the data file, install_dir\order.txt, GETDIRECTORY returns \install_dir\.

GETDIRECTORY()

If the compiled map on the HP-UX is /maps/prod/mymap.mmc, GETDIRECTORY returns /maps/prod/.

Suppose you want to run the map, **MyMap**, from a component rule on **Record** in your input to determine whether input customer names are valid. **MyMap** has two inputs and one output. The first input is the customer name to look up. The second input is a lookup file. The output is a text item whose value is "valid" or "error".

The name of the lookup file is constant; it is always **XREF_TBL.TXT**. However, its location might vary; it will always be in the same directory as the data file used as the source you are trying to validate. For example, if the name of the data file used as the source is **C:\SHR\ABC\INPUT.TXT**, the lookup file name is **C:\SHR \ABC\XREF_TBL.TXT**. If the data file name is **/local/data/somefile**, the lookup file name is **/local/data/XREF_TBL.TXT**, and so forth.

You could use this component rule on Record to determine whether the customer name is valid:

RUN ("MyMap.mmc" , "-IE1S10" + CustomerName:\$ + " -IF2 " + GETDIRECTORY () + "XREF_TBL.TXT" + " -OE1") = "VALID"

Related functions

- GETFILENAME
- GETRESOURCENAME

GETITXUID

The GETITXUID function returns a universally unique identifier (UUID).

Syntax:

resourcelib->GETITXUID ()

GETITXUID ()

Returns:

A unique string of 36 single-digit hexadecimal numbers

This function has no arguments but requires parentheses ().

GETLOCALE

The GETLOCALE function returns the locale setting of the computer.

Syntax:

resourcelib->GETLOCALE ()

Meaning:

GETLOCALE ()

Returns:

A single text item

The GETLOCALE function returns the locale setting of the computer where the map runs. The locale is returned in the format specified by the operating system. Generally, the return format is an ISO Language Code (as defined by ISO-639) in combination with an ISO Country Code (as defined by ISO-3166) when applicable. The language codes are two lowercase letters and the country codes are two uppercase letters. For example, **en_US** is the code for English (United States).

This function has no arguments but requires parentheses.

Exemple

Table 22. Examples

System locale	Returns
French	fr
Korean	ko
Brazilian Portuguese	pt_BR
Taiwanese Chinese	zh-TW

GETFILENAME

The GETFILENAME function returns the file name for a file adapter source or target of a specified card object. Without an argument, it returns the adapter command associated with the active source or destination.

You can use GETFILENAME in a map rule or component rule when you need the data file name.

Syntax:

GETFILENAME ([single-simple-object-name])

Meaning:

GETFILENAME ([card_for_which_resource_info_is_needed])

Returns:

A single text item

With an argument, GETFILENAME returns the file name for a file source or target of a specified card object. Without an argument, the function returns the source or destination name associated with the active source or destination.

Examples

GETFILENAME (OrderFile)

If the card **OrderFile** is associated with the data file, *install_dir***order.txt**, GETFILENAME returns *install_dir***order.txt**.

Suppose you want to run the map **MyMap** from a component rule on **Record** in your input to determine if input customer names are valid. **MyMap** has two inputs and one output. The first input is the customer name to be looked up. The second input is a lookup file. The output is a text item whose value is "valid" or "error".

The name of the lookup file can vary; it must correspond to the name of the data file used as the source you are trying to validate. For example, if the data file name is **c:\DATA.AAA**, the lookup file name is **c:\LOOKUP.AAA**. If the data file name is **c:\DATA.XYZ**, the lookup file name is **c:\LOOKUP.XYZ**, and so on.

You could use this component rule on Record to determine whether the customer name is valid:

RUN ("MyMap.mmc" , "-IE1S10" + CustomerName:\$ + " -IF2 LOOKUP." + RIGHT (GETFILENAME () , 3) + " -OE1") = "VALID"

Related functions

- GETDIRECTORY
- GETRESOURCENAME

GETPARTITIONNAME

You can use GETPARTITIONNAME when you need to know the name of the partition to which the data for the given object belongs.

Syntax:

GETPARTITIONNAME (single-partitioned-object-expression)

GETPARTITIONNAME (partitioned_object)

Returns:

A single simple object name

GETPARTITIONNAME returns a text item that represents the name of the partition to which the data for *partitioned_object* belongs.

Examples

• GETPARTITIONNAME (Transaction:File)

The type defined by **Transaction** is a partitioned object that has three partitions: **Add**, **Delete**, and **Modify**. In this example, if the input data for **Transaction** belongs to the **Delete** partition, the GETPARTITIONNAME function returns "delete".

Related functions

PARTITION

GETRESOURCEALIAS

The GETRESOURCEALIAS function returns the resource alias value specified in a Resource Registry resource name file (.mrn).

Syntax:

resourcelib->GETRESOURCEALIAS (sinlge-text-expression, single-text-expression)

Meaning:

GETRESOURCEALIAS (single-text-expression, single-text-expression)

Returns:

A single text item

The GETRESOURCEALIAS function loads a Resource Registry resource configuration file and retrieves the specified alias value. The values are defined as part of the Global object in the .mrc file.

Exemple

In the below example the resource configuration file is defined as:

```
<?xml version="1.0" encoding="UTF-8"?>
<ResourceCfg>
<Global>
<ResourceFile ActiveVirtualServer="test">Company.mrn</ResourceFile>
```

</Global> </ResourceCfg>

The resource name file is defined as:

```
<?xml version="1.0" encoding="UTF-8"?>
<MRN>
<VirtualServerSet>
</VirtualServer>test</VirtualServer>
</VirtualServerSet>
<Resource>
<Name>company</Name>
<Value Server="test" encrypt="OFF">ABC</Value>
</Resource>
</MRN>
```

..when used as a part of this rule:

```
=resourcelib->GETRESOURCEALIAS("company.mrc","%company%")
```

In this scenario, the return value is "ABC".

When an absolute path is not defined in the location, the default location is the map directory.

GETRESOURCENAME

The GETRESOURCENAME function returns the adapter source or target command of a specified card object. Without an argument, it returns the adapter command associated with the active source or destination.

You can use GETRESOURCENAME in a component or map rule when you need to know the name of a source or destination.

Syntax:

GETRESOURCENAME ([single-simple-object-name])

Meaning:

GETRESOURCENAME ([card_for_which_resource_info_is_needed])

Returns:

A single text item

With an argument, the source or destination name that is associated with the card. Without an argument, returns the source or destination name associated with the active source or destination.

Examples

• GETRESOURCENAME (OrderFile)

If the card **OrderFile** is associated with the data file, *install_dir***order.txt**, the GETRESOURCENAME function returns *install_dir***order.txt**.

Related functions

- GETDIRECTORY
- GETFILENAME

GETTXINSTALLDIRECTORY

The GETTXINSTALLDIRECTORY function returns the HCL® OneTest[™] Data product installation directory.

Syntax:

```
resourcelib->GETTXINSTALLDIRECTORY ()
```

Meaning:

GETTXINSTALLDIRECTORY ()

Returns:

A single text item

GETTXINSTALLDIRECTORY returns the product installation directory.

This function has no arguments but requires parentheses.

This function cannot be used in a z/OS environment.

INDEX

You can use the INDEX function when you need to select or test particular objects based on their occurrence, or to add a sequence number to output objects.

INDEX returns an integer that represents the index of an object relative to its nearest contained object, counting only valid objects.

INDEX cannot be used in a component rule.

Syntax:

INDEX (single-object-name)

Meaning:

INDEX (object_for_which_to_get_index)

Returns:

A single integer

The *object_for_which_to_get_index* variable must be a type name. The result is the index of *object_for_which_to_get_index*.

- If object_for_which_to_get_index is an input, this will be the index within all valid objects.
- If object_for_which_to_get_index is an output, this will be the index within all objects (valid and invalid).
- Returns 0 if the input argument is "none".

The difference between INDEXABS and INDEX is that INDEXABS counts both valid and invalid instances, whereas INDEX counts only valid instances.

Examples

Message (s) = IF (INDEX (Message:Input) > 3, Message:Input, "none")

For example, there are five **Messages** in **Input**. The first three evaluations of this rule return "none". The fourth evaluation returns **Message[4]**. The fifth evaluation returns **Message[5**].

Invoice (s) = MyMap (Invoice Segment:Input, INDEX (\$))

For the first evaluation of MyMap, INDEX(\$) is 1. For the second evaluation of MyMap, INDEX(\$) is 2.

Related functions

- CHOOSE
- COUNT
- COUNTABS
- INDEXABS

INDEXABS

You can use INDEXABS when you need the absolute occurrence of a particular object across all occurrences, rather than across only valid occurrences.

The INDEXABS function returns an integer that represents the index of an object relative to its nearest contained object, counting both valid and invalid instances of the object.

Syntax:

INDEXABS (single-object-name)

Meaning:

INDEXABS (object_for_which_to_get_index)

Returns:

A single integer

INDEXABS returns an integer that represents the absolute index of *object_for_which_to_get_index*. The integer indicates the instance this object that is in the set of *all* instances of the object, including both valid and invalid occurrences. Returns 0 if the input argument is "none".

- If *object_for_which_to_get_index* is an input, this will be the index within all members of the series, including valid objects, invalid objects, and existing "none"s.
- If *object_for_which_to_get_index* is an output, this will be the index within all existing members of the series, including existing "none"s.

The difference between INDEXABS and INDEX is that INDEXABS counts both valid and invalid instances, as well as existing "none"s, whereas INDEX counts only valid instances.

Examples

• INDEXABS (Message Record:Order:PO_File)

For this example, that Order contains the following Messages:

Message Record[1] Valid

Message Record[2 Error

Message Record[3] Valid

In a map rule, INDEXABS (MessageRecord[3]:Order:PO_File) would evaluate to 3.

If the INDEX function was used, INDEX (Message Record[3]:Order:PO) would evaluate to 2.

Related function

• INDEX

LASTERRORCODE

The LASTERRORCODE function returns a text item whose value is the last error code returned by one of a specified set of functions during map execution.

You can use LASTERRORCODE to interrogate or report the error code returned by one of the external interface functions.

Syntax:

```
LASTERRORCODE()
```

Meaning:

```
LASTERRORCODE()
```

Returns:

A single text item

LASTERRORCODE has no arguments but it requires parentheses.

LASTERRORCODE returns a text item whose value is the last error code returned by one of a specified set of functions during map execution.

The following functions can fail:

- DBLOOKUP
- DBQUERY
- DDEQUERY
- EXIT
- GET
- PUT
- RUN

Examples

 Message = VALID (RUN ("Map1Msg.mmc", "-AE -OMMSMQ1B `-QN .\aqueue -CID 2001"), FAIL ("Failure on RUN (" + TEXT (LASTERRORCODE ()) + "):" + LASTERRORMSG ()))

In this example, the LASTERRORCODE and LASTERRORMSG functions are being used in conjunction with the FAIL and VALID functions to fail (abort) the map if the map executed by the RUN function (**Map1Msg.mmc**) fails. In this example, the map fails and returns the error code and error message reported by the RUN function using the LASTERRORCODE and LASTERRORMSG functions.

If **Map1Msg** fails because one or more of its inputs was invalid, **Message** is assigned a value of "none". The map aborts and the following message is reported in the execution audit log:

Failure on RUN (8): One or more inputs was invalid.

Related functions

- DBLOOKUP
- DBQUERY
- DDEQUERY

LASTERRORMSG

The LASTERRORMSG function returns a text item whose value is the message corresponding to the last error code returned by one of a specified set of functions during map execution.

Syntax:

LASTERRORMSG()

Meaning:

LASTERRORMSG()

Returns:

A single text item

Although LASTERRORMSG has no arguments, it does require parentheses.

LASTERRORMSG returns a text item whose value is the message corresponding to the last error code returned by one of a specified set of functions during map execution.

The following is the list of functions that can fail:

• DBLOOKUP	• GET
• DBQUERY	• PUT
• DDEQUERY	• RUN

• EXIT

Examples

```
    Message = VALID ( RUN ( "MaplMsg.mmc" , "-AE -OMMSMQ1B `-QN .\aqueue -CID 2001'" ), FAIL ( "Failure
on RUN (" + TEXT (LASTERRORCODE ( ) ) + "):" + LASTERRORMSG ( ) ) )
```

In this example, the LASTERRORCODE and LASTERRORMSG functions are being used in conjunction with the FAIL and VALID functions to fail (abort) the map if the map executed by the RUN function (**Map1Msg.mmc**) fails. In this example, the map fails and returns the error code and error message reported by the RUN function using the LASTERRORCODE and LASTERRORMSG functions.

If **Map1Msg** fails because one or more of its inputs was invalid, Message is assigned a value of "none". The map aborts and the following message is reported in the execution audit log:

Failure on RUN (8): One or more inputs was invalid.

Related functions

- DBLOOKUP
- DBQUERY
- DDEQUERY

LOOKDOWN

The LOOKDOWN function sequentially searches a series beginning at the end of the series, returning the last member of the series that meets a specified condition.

Syntax:

LOOKDOWN (series-object-expression, single-condition-expression)

Meaning:

LOOKDOWN (series_to_search, condition_to_evaluate)

Returns:

A single object

LOOKDOWN returns the last member of *series_to_search* for which *condition_to_evaluate* evaluates to "true"; it returns "none" if no member of *series_to_search* meets the condition specified by *condition_to_evaluate*.

Examples

• LOOKDOWN (Account#:Customer, Company Name:Customer = "ACME")

This example returns the Account# of Customer whose Company Name is ACME.

 LOOKDOWN (Part#:Row:DBSelect, Model#:Row:DBSelect = ModelCode:Legacy & Serial#:Row:DBSelect > "123")

This example returns the **Part#** of **DBSelect** where the **Model#** in that row matches the **ModelCode** of **Legacy** and the **Serial#** is greater than 123.

Related functions

- CHOOSE
- EXTRACT
- LOOKUP
 - Note: LOOKDOWN differs from LOOKUP in that LOOKDOWN returns the last member of series_to_search that meets the condition_to_evaluate, while LOOKUP returns the first member of series_to_search that meets the condition_to_evaluate.
- SEARCHUP
- SEARCHDOWN

The LOOKDOWN function performs a sequential search on an unsorted series, starting from the end of the series. The SEARCHUP and SEARCHDOWN functions perform a binary search on a series that is sorted in ascending or descending code-page byte-order. The SEARCHUP and SEARCHDOWN functions are efficient for

performing multiple searches on a large series. The LOOKDOWN function can be more efficient for performing fewer searches. Note that LOOKDOWN returns a different instance from the one returned by SEARCHUP and SEARCHDOWN if multiple instances in the series match the condition.

LOOKUP

The LOOKUP function sequentially searches a series, returning the first member of the series that meets a specified condition.

Syntax:

LOOKUP (series-object-expression, single-condition-expression)

Meaning:

LOOKUP (series_to_search , condition_to_evaluate)

Returns:

A single object

LOOKUP returns the first member of series_to_search for which condition_to_evaluate evaluates to "true"; it returns "none" if no member of series_to_search meets the condition specified by condition_to_evaluate.

Examples

• LOOKUP (Account#:Customer, Company Name:Customer = "ACME")

This example returns the Account# of Customer whose Company Name is ACME.

• LOOKUP (Part#:Row:DBSelect , Model#:Row:DBSelect = ModelCode:Legacy & Serial#:Row:DBSelect > "123")

This example returns the **Part#** of **DBSelect** where the **Model#** in that row matches the **ModelCode** of **Legacy** and the **Serial#** is greater than 123.

Related functions

- CHOOSE
- EXTRACT



Note: LOOKUP differs from EXTRACT in that LOOKUP returns the first member of *series_to_search* that meets the *condition_to_evaluate*, while EXTRACT returns all members (one at a time) of *series_to_search* that meet the *condition_to_evaluate*.

LOOKDOWN

- Note: LOOKUP differs from LOOKDOWN in that LOOKUP returns the first member of series_to_search that meets the condition_to_evaluate, while LOOKDOWN returns the last member of series_to_search that meets the condition_to_evaluate.
- SEARCHUP
- SEARCHDOWN

The LOOKUP function performs a sequential search on an unsorted series, starting from the beginning of the series. The SEARCHUP and SEARCHDOWN functions perform a binary search on a series that is sorted in ascending or descending code-page byte-order. The SEARCHUP and SEARCHDOWN functions are efficient for performing multiple searches on a large series. The LOOKUP function can be more efficient for performing fewer searches.

MEMBER

Use MEMBER when you need to know whether an object occurs within a series.

The MEMBER function searches a series, looking for a single specified object in the series. If any object in the series matches the specified object, MEMBER returns "true". If there is no match, MEMBER returns "false".

Syntax:

MEMBER (single-object-expression, series-object-expression)

MEMBER (single-object-expression, { literal, literal ... })

Meaning:

MEMBER (object_to_look_for , series_of_objects_to_look_at)

Returns:

"True" or "false"

MEMBER returns "true" if object_to_look_for matches one of the values in series_of_objects_to_look_at.

It returns "false" if object_to_look_for does not match at least one of the values in series_of_objects_to_look_at.

The two arguments, *object_to_look_for* and *series_of_objects_to_look_at*, must be objects of the same item interpretation or the same group type. For example, if *object_to_look_for* is a date/time item, *series_of_objects_to_look_at* must be a series of date/time items.

Examples

MEMBER (EntityIDCode:Name, {"BT", "ST"})

This example tests whether EntityIDCode has one of a particular set of literal values.

• MEMBER (Store#, EntityIDCode:Name)

This example tests whether Store# has the same value as any EntityIDCode:Name.

Related functions

- EXTRACT
- LOOKUP

SEARCHDOWN

Use the SEARCHDOWN function to look up data within a series of data that is sorted in descending code-page byteorder. SEARCHDOWN performs a binary search on the sorted series and returns a related object that corresponds to the item found.

The byte-order of characters varies by code page. For example, because the ASCII **A** character (0x41) has a higher numeric value than the ASCII **0** character (0x30), the SEARCHDOWN function requires the **0** character to be sorted after the ASCII **A** character in the series. The EBCDIC **A** character (0xC1) has a lower numeric value than the EBCDIC **0** character, so the SEARCHDOWN function requires the EBCDIC **A** character to be sorted be after the EBCDIC **0** character in the series.

The HCL® OneTest[™] Data Data Language property values change the collation order of some characters. For example, the German National Language property value is arranged in byte order, with the exception of certain characters: æ is ordered after a, e is ordered before ä, and so forth. There are particular collation rules for other National Language property values. However, there is no collation order for "Western" and "Japanese" property values, and the deprecated Data Language property values are always in byte order.

Syntax:

SEARCHDOWN (series-object-expression, series-item-object-expression, single-item-expression)

Meaning:

SEARCHDOWN (corresponding_object_to_return , descending_items_to_search , item_to_match)

Returns:

A single object

SEARCHDOWN performs a binary search on the item series of *descending_items_to_search*. The *descending_items_to_search* must be sorted in descending code page byte-order. The value to search for is specified as the *item_to_match*. The object returned (*corresponding_object_to_return*) must be related to *descending_items_to_search* by a common object name.

If no match is found, SEARCHDOWN returns "none".

Examples

SEARCHDOWN (Age Column:Row:DBSelect, SSN Column:Row:DBSelect, SSN_Value:Message)

If there are ten rows in **DBSelect**, the search starts by comparing the first **SSN Column** of the fifth row with the **SSN_Value** in **Message**. If the result matches, SEARCHDOWN returns the first **Age Column** of that **Row**. If the value of **SSN Column** is less than the **SSN_Value** in **Message**, the search continues with the third **Row**. If the value of **SSN Column** is greater than the **SSN_Value** in **Message**, the search continues with the seventh Row in **DBSelect**. The search continues in this fashion until either a match is found or until one **Row** is selected. If there is more than one **SSN Column** for the selected **Row**, a similar search is initiated for all **SSN Column**'s for the selected **Row** in **DBSelect**.

SEARCHDOWN returns the first Age Column for the selected Row of DBSelect.

Related functions

- EXTRACT
- LOOKUP
- SEARCHUP

SEARCHUP

Use the SEARCHUP function to look up data within a series of data that is sorted in ascending code-page byte-order. The SEARCHUP function performs a binary search on the sorted series and returns a related object that corresponds to the item found.

The byte-order of characters varies by code page. For example, because the ASCII **A** character (0x41) has a higher numeric value than the ASCII **0** character (0x30), the SEARCHUP function requires the **0** character to be sorted before the ASCII **A** character in the series. The EBCDIC **A** character (0xC1) has a lower numeric value than the EBCDIC **0** character, so the SEARCHUP function requires the EBCDIC **A** character to be sorted before the EBCDIC **0** character in the series.

The HCL® OneTest[™] Data Data Language property values change the collation order of some characters. For example, the German National Language property value is arranged in byte order, with the exception of certain characters: æ is ordered after a, e is ordered before ä, and so forth. There are particular collation rules for other National Language property values. However, there is no collation order for "Western" and "Japanese" property values, and the deprecated Data Language property values are always in byte order.

Syntax:

SEARCHUP (series-object-expression, series-item-object-expression, single-item-expression)

Meaning:

SEARCHUP (corresponding_object_to_return, ascending_items_to_search, item_to_match)

Returns:

A single object

SEARCHUP performs a binary search on the item series of ascending_items_to_search. The ascending_items_to_search must be sorted in ascending code page byte-order. The value to search for is specified as the item_to_match and must be of the same type as the ascending_item_to_search.

The object returned (*corresponding_object_to_return*) must be related to *ascending_items_to_search* by a common object name. If no match is found, SEARCHUP returns "none".

Examples

• SEARCHUP (Age Column:Row:DBSelect, SSN Column:Row:DBSelect, SSN_Value:Message)

If there are ten rows in **DBSelect**, the search starts by comparing the first **SSN Column** of the fifth **Row** with the **SSN_Value** in **Message**. If the result matches, SEARCHUP returns the first **Age Column** of that **Row**. If the value of **SSN Column** is greater than the **SSN_Value** in **Message**, the search continues with the third **Row**. If the value of **SSN Column** is less than the **SSN_Value** in **Message**, the search continues with the seventh **Row** in **DBSelect**. The search continues in this fashion until either a match is found or until one **Row** is selected. If there is more than one **SSN Column** for the selected **Row**, a similar search is initiated for all **SSN Column**'s for the selected **Row** in **DBSelect**.

SEARCHUP returns the first Age Column for the selected Row of DBSelect.

Related functions

- EXTRACT
- LOOKUP
- SEARCHDOWN

SORTDOWN

Use the SORTDOWN function to sort objects in a series in descending sequence. The function returns a series containing the values from the input series in descending order.

- When the character set of the data is ASCII, the objects are sorted in ASCII descending order.
- · For all other character sets, the objects are sorted in binary descending order.

Syntax:

SORTDOWN (series-item-expression)

Meaning:

SORTDOWN (item_series_to_sort)

Returns:

A series object

Returns the values in *item_series_to_sort* in descending order.

Examples

• SORTDOWN (Abbr:File)

In this example, if Abbr has these ASCII values:

ABC, GHI, DEF

SORTDOWN returns these values as a series as:

GHI, DEF, ABC

• The following table displays the results of using the SORTDOWN and SORTUP functions for a typical series of ASCII text items.

Original Input Series	Result using SORTDOWN	Result using SORTUP
Clams Casino	shrimps	1 Shrimp
Grouper	raw oysters	22 Shrimp
groupers	oysters	A
Shrimp	lobster tails	A 1 A shrimp
shrimps	lobster	A1A Shrimp
lobster	groupers	AA
lobster tails	clams	ΑΑΑΑΑ
oysters	aaaaa	Clams Casino
raw oysters	аа	Grouper
clams	a	Rock Lobster
SHRIMP	Snapper	SHRIMP
1 Shrimp	Snapper	Shark Fin Soup
22 Shrimp	Shrimp	Shrimp
A 1 A shrimp	Shark Fin Soup	Snapper
A1A Shrimp	SHRIMP	Snapper
ΑΑΑΑΑ	Rock Lobster	а
88888	Grouper	аа

Original Input Series	Result using SORTDOWN	Result using SORTUP
аа	Clams Casino	ааааа
AA	ΑΑΑΑ	clams
A	AA	groupers
а	A1A Shrimp	lobster
Rock Lobster	A 1 A shrimp	lobster tails
Snapper	A	oysters
Snapper	22 Shrimp	raw oysters
Shark Fin Soup	1 Shrimp	shrimps

Related functions

- SEARCHDOWN
- SEARCHUP
- SORTUP
- UNIQUE

SORTDOWNBY

Use SORTDOWNBY to sort the objects of a series based on a component that the objects contain. The SORTDOWNBY function returns the input series, sorted in descending order by the value of the specified component.

- When the character set of the data is ASCII, the objects are sorted in ASCII descending order.
- For all other character sets, the objects are sorted in binary descending order.

The SORTDOWNBY function does not sort the output of the EXTRACT, REJECT, or UNIQUE functions.

Syntax:

SORTDOWNBY (series-item-expression, single-item-expression)

Meaning:

SORTDOWNBY (group_series_to_sort, group_component_to_sort_by)

Returns:

A series object

SORTDOWNBY returns a series of instances of a group, sorted in descending order by the value of an item that the group contains.

Example

In this example, the group Soldier contains the items:

- Name
- Rank
- Serial number

The following command returns the instances of Soldier, sorted in descending order by Rank:

```
SORTDOWNBY (Soldier:Army, Rank:Soldier:Army)
```

Related functions

- SEARCHDOWN
- SEARCHUP
- SORTDOWN
- SORTUP
- SORTUPBY

SORTUP

Use SORTUP to sort the objects of a series in ascending sequence. The SORTUP function returns a series containing the values from an input series in ascending order.

- When the character set of the data is ASCII, the objects are sorted in ASCII ascending order.
- · For all other character sets, the objects are sorted in binary ascending order.

Syntax:

```
SORTUP (series-item-expression)
```

Meaning:

SORTUP (item_series_to_sort)

Returns:

A series object

SORTUP returns the values in *item_series_to_sort* in ascending order.

Examples

• SORTUP (Abbr:File)

In this example, if **Abbr** had the ASCII values ABC, GHI, DEF, the SORTUP function would return these values as a series: ABC, DEF, GHI.

- SEARCHDOWN
- SEARCHUP

- SORTDOWN
- UNIQUE

SORTUPBY

Use SORTUPBY to sort the objects of a series based on a component that the objects contain. The SORTUPBY function returns the input series, sorted in ascending order by the value of the specified component.

- When the character set of the data is ASCII, the objects are sorted in ASCII ascending order.
- For all other character sets, the objects are sorted in binary ascending order.

The SORTUPBY function does not sort the output of the EXTRACT, REJECT, or UNIQUE functions.

Syntax:

SORTUPBY (series-item-expression, single-item-expression)

Meaning:

SORTUPBY (group_series_to_sort, group_component_to_sort_by)

Returns:

A series object

SORTUPBY returns a series of instances of a group, sorted in ascending order by the value of an item that the group contains.

Example

In this example, the group Soldier contains the items:

- Name
- Rank
- Serial number

The following command returns the instances of Soldier, sorted in ascending order by Rank:

SORTUPBY (Soldier:Army, Rank:Soldier:Army)

- SEARCHDOWN
- SEARCHUP
- SORTUP
- SORTDOWN
- SORTDOWNBY

UNIQUE

The UNIQUE function returns a series containing all "unique" members of a series.

UNIQUE can only be used in a map rule, not in a component rule.

Syntax:

UNIQUE (series-object-expression)

Meaning:

UNIQUE (series_to_evaluate)

Returns:

A series object

UNIQUE evaluates to a series containing all unique members of *series_to_evaluate* and evaluates to "none" if *series_to_evaluate* evaluates to "none".

Examples

• UNIQUE (PartNumber:Inventory:File)

Returns the unique PartNumbers in Inventory:File

• COUNT (UNIQUE (Customer:Order:File))

Returns the number of unique Customers in Order:File

Related functions

- SORTDOWN
- SORTUP

GETENV

The GETENV function returns the value of the environment variable. If no variable exists, an empty string is returned.

Syntax:

GETENV(single-text-expression)

Meaning:

GETENV (the environment variable name)

Returns:

A single-text-item

Related reference

GETOSNAME on page 1052

GETOSNAME

The GETOSNAME function returns the name of the operating system.

The returned values can be:

- · Windows for any version of Microsoft Windows operating system
- zLinux for Linux operating system on z/OS hardware
- · Linux for Linux operating system on Intel hardware
- AIX for AIX operating system on PowerPC hardware
- OS/390 for native z/OS operating system

Syntax:

GETOSNAME()

Meaning:

GETOSNAME ()

Returns:

A single-text-item

Related reference

GETENV on page 1051

GETFILENAME on page 1032

Math and statistics functions

Precede all MATHLIB functions with

mathlib->

ABS

The ABS function returns the absolute value of a number.

Syntax:

ABS (single-number-expression)

Meaning:

ABS (number)

Returns:

A single number; the absolute value of a number

Examples

• ABS (-3)

Returns 3

• ABS (3)

Returns 3

AvailableCredit has a value of -69.42

ABS (AvailableCredit) returns 69.42

FlexDollars has a value of 50

ABS ((100 - FlexDollars)/2) returns 25

ACOSINE

Use the ACOSINE function to calculate the arccosine of a value.

Syntax:

mathlib->ACOSINE (single-number-expression)

Meaning:

mathlib->ACOSINE (number_to_convert)

Returns:

A single number item

The result is the arccosine of the converted value.

ASIN

Use the ASIN function to calculate the arcsine of a value.

Syntax:

mathlib->ASIN (single-number-expression)

Meaning:

mathlib->ASIN (number_to_convert)

Returns:

A single number item

The result is the arcsine of the converted value.

ATAN

The ATAN function calculates the arctangent of a value.

Syntax:

mathlib->ATAN (single-number-expression)

Meaning:

mathlib->ATAN (number_to_convert)

Returns:

A single number item

ATAN2

The ATAN2 function calculates the arctangent of y,x.

Syntax:

mathlib->ATAN2 (single-number-expression, single-number-expression)

Meaning:

mathlib->ATAN2 (number_to_convert)

Returns:

A single number item

COSINE

The COSINE function calculates the cosine of a value.

Syntax:

mathlib->COSINE (single-number-expression)

Meaning:

mathlib->COSINE (number_to_convert)

Returns:

A single number item

COSINEH

The COSINEH function calculates the hyperbolic cosine of a value.

Syntax:

mathlib->COSINEH (single-number-expression)

Meaning:

mathlib->COSINEH (number_to_convert)

Returns:

A single number item

COUNT

You can use the COUNT function to return an integer representing the number of valid input or output objects in a series.

Syntax:

COUNT (series-object-expression)

Meaning:

COUNT (valid_objects_to_count)

Returns:

A single integer

The result is the number of valid_objects_to_count. If the input argument evaluates to "none", COUNT returns 0.

COUNT does not count existing "none"s unless its group was defined as an explicit format with a **Track** setting of Places.

Examples

• COUNT (Claim Record:Patient File)

This example returns the number of valid Claim Record objects in Patient File.

COUNT (Class IN Transcript)

This example returns the number of valid Class objects in Transcript.

COUNT (UNIQUE (Class IN Transcript))

This example returns the number of valid Unique Class objects in Transcript.

Related functions

• COUNTABS

COUNTABS

You can use COUNTABS to count the input or output objects in a series, regardless of the validity of the object.

Unlike COUNT, COUNTABS includes both valid and invalid objects in a series.

Syntax:

COUNTABS (series-object-expression)

Meaning:

COUNTABS (objects_to_count)

Returns:

A single-integer

The result is the number of *objects_to_count*. If the input argument evaluates to "none", COUNTABS returns 0.

COUNTABS does not count existing "none's" unless its group was defined as an explicit format with a **Track** setting of **Places**.

Examples

• COUNTABS (Claim Record: Patient File)

This example returns the number of Claim Record objects in Patient File.

• COUNTABS (Class IN Transcript)

This example returns the number of **Class** objects in **Transcript**.

Related functions

COUNT

EXP

The EXP function calculates the exponential of a value.

Syntax:

mathlib->EXP (single-number-expression)

Meaning:

```
mathlib->EXP (number_to_convert)
```

Returns:

A single number item

FACTORIAL

The FACTORIAL function calculates the factorial of a value.

Syntax:

mathlib->FACTORIAL (single-number-expression)

Meaning:

mathlib->FACTORIAL (number_to_convert)

Returns:

A single number item

FROMBASETEN

You can use FROMBASETEN when you need to convert numbers to a base other than 10.

The FROMBASETEN function converts an integer to a text item that can be interpreted as a number, using positional notation of the base specified.

Syntax:

FROMBASETEN (single-integer-expression, single-integer-expression)

Meaning:

FROMBASETEN (positive_integer_to_convert, base_to_convert_to)

Returns:

A single text item

FROMBASETEN returns a text item that results from converting *positive_integer_to_convert* to a text item that can be interpreted as a number using positional notation of the base specified by *base_to_convert_to*.

If base_to_convert_to is less than 2 or greater than 36, FROMBASETEN evaluates to "none". Resulting text item characters A-Z are interpreted as digits having decimal values from 10-35, respectively. The characters returned are uppercase.

Example

• FROMBASETEN (18, 2)

Returns the value 10010

• FROMBASETEN (123, 8)

Returns the value 173

Related function

TOBASETEN

INT

You can use the INT function when you need only the integer portion of a number.

Syntax:

INT (single-number-expression)

Meaning:

INT (number_to_convert)

Returns:

A single integer

INT returns the integer portion of a number. The result is the integer part of *number_to_convert*. Any fractional part after the decimal point is dropped.

Examples

• INT (1.45)

Returns 1

• INT (3.6)

Returns 3

• INT (Purchase:Amt - Discount:Amt)

Subtracts Discount:Amt from Purchase:Amt and returns the result as a whole number.

Related functions

- MOD
- ROUND
- TRUNCATE

LOG

The LOG function calculates the logarithms of a value.

Syntax:

mathlib->LOG (single-number-expression)

Meaning:

mathlib->LOG (number_to_convert)

Returns:

A single number item

LOG10

The LOG10 function calculates the logarithms for base 10 of a value.

Syntax:

mathlib->LOG10 (single-number-expression)

Meaning:

mathlib->LOG10 (number_to_convert)

Returns:

A single number item

MAX

The MAX function returns the maximum value from a series of number, date, time, or text values.

Syntax:

MAX (series-item-expression)

Meaning:

MAX (series_of_which_to_find_max)

Returns:

A single number

The result is the maximum value in the input argument series: number, text, or date/time.

Examples

• MAX (UnitPrice:Input)

If the values for UnitPrice are {20, 10, 100}, MAX returns 100.

• MAX(EXTRACT(DueDate:Book:Library, CheckedOut:Book:Library = "Y"))

Returns the maximum (latest) DueDate for a book that is checked out from the library.

Related functions

• MIN

MIN

Use MIN when you need the minimum value from a series of number, date, time, or text values.

The MIN function returns the minimum value from a series.

Syntax:

MIN (series-item-expression)

Meaning:

MIN (series_of_which_to_find_min)

Returns:

A single number

The result is the minimum value of the input series: number, text, or date/time.

Examples

• MIN (UnitPrice:Input)

If the values for **UnitPrice** are {20,10,100}, MIN returns 10.

• MIN (StartTime:.:Schedule)

Returns the minimum (earliest) StartTime in Schedule.

Related functions

• MAX

MOD

Use MOD when you need the modulus of an integer and a number.

The MOD function returns the modulus that remains after a number is divided by an integer.

Syntax:

MOD (single-number-expression, single-integer-expression)

Meaning:

MOD (dividend, divisor)

Returns:

A single integer

The result is the remainder (modulus) after dividend is divided by divisor. The result has the same sign as divisor.

The *dividend* is first divided by the integer *divisor*, resulting in a quotient. The modulus is calculated by multiplying the integer portion of the quotient by *divisor* and then subtracting that product from *dividend*.

If divisor is 0, MOD returns "none".

Examples

• MOD (3, 2) or MOD (-3, 2)

Returns 1

• MOD (3, -2) or MOD (-3, -2)

Returns -1

• MOD (-3, 2) or MOD (-3, -2)

Returns 1

• MOD (-3, -2) or MOD (-3, -2)

Returns -1

POWER

The POWER function calculates x raised to the power of y.

Syntax:

mathlib->POWER (single-number-expression, single-number-expression)

Meaning:

mathlib->POWER (base_number, exponent_number)

Returns:

A single number item

RAND

The RAND function returns a pseudorandom number.

Syntax:

RAND ()

Meaning:

RAND ()

Returns:

A single number item

RAND takes no parameters. If the SEED function is called prior to RAND, RAND will return the same value based on the value to SEED.

Related functions

- RANDDATA
- SEED

ROUND

The ROUND function rounds a number to a specified number of decimal places. If the number of decimal places is not specified, the number is rounded to a whole number. The result is in character number format.

Syntax:

ROUND (single-number-expression [, single-integer-expression])

Meaning:

ROUND (number_to_round [, number_of_decimal_places])

Returns:

A single number

ROUND converts *number_to_round* to character format, if necessary, and then produces the value of *number_to_round* rounded to the number of decimal places specified by *number_of_decimal_places*. If *number_of_decimal_places* is not specified, *number_to_round* is rounded to the nearest whole number.

Examples

• ROUND (1.46, 1)

Returns 1.5

• ROUND (1.46)

Returns 1

Related functions

TRUNCATE

SEED

The SEED function primes the RAND and RANDDATA functions so they produce repeated results.

Syntax:

SEED(single-number-expression)

Meaning:

SEED(number_for_seed)

Returns:

NONE

Related functions

- RAND
- RANDDATA

SIN

The SIN function calculates the sine of a value.

Syntax:

mathlib->SIN (single-number-expression)

Meaning:

mathlib->SIN (number_to_convert)

Returns:

The value of a number

SINH

The SINH function calculates the hyperbolic sine of a value.

Syntax:

mathlib->SINH (single-number-expression)

Meaning:

mathlib->SINH (number_to_convert)

Returns:

A single number item

SQRT

The SQRT function returns the square root of a number.

Syntax:

SQRT (single-number-expression)

Meaning:

SQRT (number)

Returns:

A single number

SQRT returns the square root of number.

Examples

• SQRT (4)

Returns 2

SUM

The SUM function calculates the sum of a series of numbers.

Syntax:

SUM (series-number-expression)

Meaning:

SUM (series_to_sum)

Returns:

A single number

SUM returns the sum of all members in *series_to_sum*.

Examples

• SUM (Quantity:LineItem)

This example calculates the sum of all the **Quantity** objects of LineItem.

TAN

The TAN function calculates the tangent of a value.

Syntax:

mathlib->TAN (single-number-expression)

Meaning:

mathlib->TAN (number_to_convert)

Returns:

A single number item

TANH

The TANH function calculates the hyperbolic tangent of a value.

Syntax:

mathlib->TANH (single-number-expression)

Meaning:

mathlib->TANH (number_to_convert)

Returns:

A single number item

TOBASETEN

The TOBASETEN function converts a text item that can be interpreted as a number, using positional notation of the base specified, to a base 10 number.

Syntax:

TOBASETEN (single-text-expression, single-integer-expression)

Meaning:

TOBASETEN (text_to_convert, base_to_convert_from)

Returns:

A single integer

TOBASETEN returns a number that results from converting *text_to_convert* that can be interpreted as a number, using positional notation of the base specified by *base_to_convert_from*, to its base 10 representation. Text item characters A-Z are interpreted as digits having decimal values from 10-35, respectively.

If base_to_convert_from is less than 2 or greater than 36, TOBASETEN evaluates to "none". If text_to_convert contains a character that is not alphanumeric or is not in the range specified by base_to_convert_from, TOBASETEN returns "none".

Examples

• TOBASETEN ("A", 16)

Returns the value 10

• TOBASETEN ("10", 36)

Returns the value 36

• TOBASETEN ("A0", 15)

Returns the value 150

• TOBASETEN ("A0", 5)

Returns the value "none"

Related functions

FROMBASETEN

TRUNCATE

The TRUNCATE function removes decimal places from a number, leaving a specified number of decimal places.

You can use TRUNCATE with a second argument to truncate a number to a specified number of decimal places or without a second argument to reduce a number to an integer by removing all decimal places.

Syntax:

TRUNCATE (single-number-expression[, single-integer-expression])

Meaning:

TRUNCATE (number_to_truncate[, number_of_decimal_places])

Returns:

A single number

TRUNCATE first converts *number_to_truncate* to character format, if necessary. It then truncates that number by removing decimal places to the right of *number_of_decimal_places*. If *number_of_decimal_places* is not used, the number is truncated to an integer.

Examples

• TRUNCATE (3.9292, 2)

Returns 3.92

• TRUNCATE (3.9292)

Returns 3

Related functions

- INT
- ROUND

Text functions

BCDTOTEXT

The BCDTOTEXT function converts the digits in a BCD (Binary Coded Decimal) item to a text item containing the digits of the BCD-encoded item as a string of characters.

Syntax:

BCDTOTEXT (single-text-expression)

Meaning:

BCDTOTEXT (BCD_item_to_convert)

Returns:

A single text item

BCD_item_to_convert is converted from BCD format to a text string containing the digits of the BCD-encoded value as a string of characters.

Numbers in BCD format have two decimal digits in each byte. Each half-byte, therefore, can contain a binary value from 0000 (which represents the digit 0) through 1001, which represents the digit 9). Based on this definition, the following behavior applies:

- If any half-byte of the BCD number contains the binary value 1101 or 1111, that half-byte is ignored.
- If the BCD item contains the binary value 1010, 1011, 1100, or 1110, the output of the function is "none".

Examples

BCDTOTEXT (Qty:Item)

If Qty is x`1234', the result is 1234.

BCDTOTEXT (DiscountAmt)

If DiscountAmt is x`0123', the result is 0123.

BCDTOTEXT (TotalDollars)

If Total is x`F123', the result is 123.

- BCDTOHEX
- BCDTOINT
- TEXTTOBCD

COUNTSTRING

You can use the COUNTSTRING function when you need to know the number of times a specific text string appears within another text string. The function begins to look for the character string from the first position of the first string, and proceeds forward one byte at a time.

Syntax:

COUNTSTRING (single-text-expression, single-text-expression)

Meaning:

```
COUNTSTRING (text_to_search , text_to_find_and_count)
```

Returns:

A single-integer

COUNTSTRING returns an integer that represents the number of times that a specified character string appears in another character string.

The result is a number representing the number of times text_to_find_and_count appears within text_to_search. If either text_to_search or text_to_find_and_count evaluates to "none", COUNTSTRING returns 0.

Examples

• COUNTSTRING ("banana" , "a")

Returns a value of 3

• COUNTSTRING ("aaaa" , "aa")

Returns a value of 3.

Related functions

- FIND
- LEFT
- MID
- RIGHT

CPACKAGE

CPACKAGE specifies the character set of the output of the function. From that point onward, the data is treated as if it were in that character set. If the data is not in the specified character set, you get the wrong answer.

The character set is required to be specified in this function. If you choose not to specify a character set, you should use the original version of the PACKAGE function.

Syntax:

CPACKAGE (single-object-expression, "character-set-of-object-content")

Meaning:

CPACKAGE (object_to_convert, object_character_set)

Returns:

A single text item

The second argument, *object_character_set*, represents the character set of the resulting object. Character set codes are listed in Character set codes on page 1127.

Examples

In this example, the group **Record** has an initiator of "#", a terminator of "@" and a delimiter of "," with the following data:

"#1339X10A,491.38,Green,42x54@"

• CPACKAGE (Record:Card, "ASCII")

Returns: #1339X10A,491.38,Green,42x54@

CSERIESTOTEXT

CSERIESTOTEXT specifies the character set of the output of the function. From that point onward, the data is treated as if it were in that character set. If the data is not in the specified character set, you get the wrong answer.

The character set is required to be specified in this function. If you choose not to specify a character set, you should use the original version of the SERIESTOTEXT function.

Syntax:

CSERIESTOTEXT (series-object-expression, "character-set-of-object-content")

Meaning:

CSERIESTOTEXT (series_to_convert, object_character_set)

Returns:

A single text item

The *series_to_convert* argument concatenates the series of the input argument, including nested delimiters but excluding initiators and terminators.

The second argument, object_character_set, represents the character set of the resulting object.

Examples

In this example, you have the following data that represents bowler information for a bowling league:

Andrews, Jessica:980206:JBC:145:138:177:159

Little, Randy:980116:BBK:175:168

Wayne, Richard:980102:JBC:185:204:179:164:212

Each record consists of the bowler's name, the date of their last game played, a team code and one or more bowling scores. **Record** is defined as a group that is infix delimited by a colon.

Using the following rule produces results of the concatenation of all scores for all of the bowlers, even though the scores are not all contiguous within the data.

• = CSERIESTOTEXT (Score Field:Bowler:Input, "ASCII")

```
Returns: 145138177159175168185204179164212
```

You can change the rule to concatenate the list of scores to the bowler's name using the following rule:

```
• = BowlerName Field:Bowler:Input + " ->" + CSERIESTOTEXT (Score Field:Bowler:Input, "ASCII")
```

Returns:

Andrews, Jessica -> 145138177159

Little, Randy -> 175168

Wayne, Richard -> 185204179164212

In this example, you have an input number that is of variable size, followed by a name. There is no syntax that separates the number from the name. You can define the number as a group with **Byte(s)** as a component and provide a component rule for **Byte(s)**, such as:

ISNUMBER (\$)

CSIZE

The CSIZE function returns an integer representing the size of a specified object in characters, exclusive of any pad characters.

Syntax:

CSIZE (single object expression)

Meaning:

CSIZE (object whose size is needed)

Returns:

A single integer

Exemple Example

Exemple

This example shows how the CSIZE function differs from the SIZE function.

Exemple

The SIZE function returns the number of bytes used to represent those symbolic characters in a particular code page.

Exemple

The CSIZE function returns the number of symbolic characters.

Exemple Symbolic text: Mañana

Exemple

UTF-8 hexadecimal representation: 0x4D 0x61 0xC3 0xA3 0x61 0x6E 0x61

Exemple

SIZE(Mañana)

Exemple Returns 7 bytes

Exemple CSIZE(Mañana)

Exemple Returns 6 characters

CTEXT

CTEXT specifies the character set of the output of the function. From that point onward, the data is treated as if it were in that character set. If the data is not in the specified character set, you get the wrong answer.

The character set is required to be specified in this function. If you choose not to specify a character set, you should use the original version of the TEXT function.

Syntax:

CTEXT (single-object-expression, "character-set-of-object-content")

Meaning:

CTEXT (object_to_convert , object_character_set)

Returns:

A single text item

The first argument, *object_to_convert*, represents the object that is converted to a text item, excluding the initiator and terminator of the input object.

The second argument, object_character_set, represents the character set of the resulting object.

Example

In this example, the group **Record** has an initiator of the pound sign (#), a terminator of the at sign (@), and a delimiter of a comma (,), and uses the following data:

#1339X10A,491.38,Green,42x54@

• CTEXT (Record:card, "ASCII")

Returns: 1339X10A,491.38,Green,42x54

The initiator and terminator are not included because only the content of the object is converted to text.

DATETOTEXT

The DATETOTEXT function converts a date object or expression to a text item.

Syntax:

DATETOTEXT (single-date-expression)

Meaning:

DATETOTEXT (date_to_convert)

Returns:

A single text item

If *date_to_convert* is a date object name, this returns the date as a text item formatted according to the presentation of the date object.

If *date_to_convert* is a date expression produced by a function, this returns the date as a text item formatted according to the presentation of the output argument of that function.

Examples

• DATETOTEXT (ShipDate)

In this example, **ShipDate** is converted from a date to text. If **ShipDate** has a CCYYMMDD presentation, the resulting text item will have that presentation, as well.

• DATETOTEXT (CURRENTDATETIME ("{MM/DD/CCYY}"))

In this example, CURRENTDATETIME evaluates and returns a date in MM/DD/CCYY format. Then DATETOTEXT evaluates and returns a text string that is that date in MM/DD/CCYY format.

For example, use DATETOTEXT, to do text concatenation. The FROMDATETIME function provides greater flexibility in specifying the format of the resulting text item.

Related Functions

- FROMDATETIME
- NUMBERTOTEXT
- TEXT
- TEXTTODATE
- TEXTTONUMBER
- TEXTTOTIME
- TIMETOTEXT
- TODATETIME

FILLLEFT

The FILLLEFT function returns a text item of the length specified. In the output, the text item is preceded with the specified pad value.

You can use FILLLEFT when you have a value that needs to be of a fixed size with a variable number of leading characters with a specified value.

Syntax:

FILLLEFT (single-text-expression, single-text-expression, single-integer-expression)

Meaning:

FILLLEFT (text_to_fill , pad_character , pad_to_length)

Returns:

A single text item

The FILLLEFT function returns the text string that results from padding out *text_to_fill* by preceding it with the *pad_character* up to *pad_to_length* bytes.

If the pad-length argument is less than the number of bytes in the text to fill, no padding will appear.

Examples

• FILLLEFT (AcctID:Transaction, "0", 5)

If AcctID has the value 14, FILLLEFT returns 00014

• FILLLEFT (NUMBERTOTEXT (InvoiceAmt) , "*" , 10)

If InvoiceAmt has the value 24.75, FILLLEFT returns *****24.75

- FILLRIGHT
- LEAVEALPHA

- LEAVEALPHANUM
- LEAVENUM
- LEAVEPRINT
- SQUEEZE
- SUBSTITUTE
- TRIMLEFT
- TRIMRIGHT

FILLRIGHT

The FILLRIGHT function returns a text item of the length specified. In the output, the text item is appended with the specified pad value.

You can use FILLRIGHT when you have a value that needs to be of a fixed size with a variable number of trailing characters of a specified value.

Syntax:

FILLRIGHT (single-text-expression, single-text-expression, single-integer-expression)

Meaning:

FILLRIGHT (text_to_fill , pad_character , pad_to_length)

Returns:

A single text item

FILLRIGHT returns the text string that results from padding out *text_to_fill* by appending the *pad_character* up to *pad_to_length* bytes.

If the pad-length argument is less than the number of bytes in the text to fill, no padding will appear.

Examples

• FILLRIGHT (LastName:Contact, " ", 25)

If LastName has the value Peterson, FILLRIGHT returns Peterson followed by 17 spaces.

- FILLLEFT
- LEAVEALPHA
- LEAVEALPHANUM
- LEAVENUM
- LEAVEPRINT
- SQUEEZE
- SUBSTITUTE

- TRIMLEFT
- TRIMRIGHT

FIND

The FIND function looks for one text string within another text string and returns to its starting position, if found.

Syntax:

FIND (single-text-expression , single-text-expression
[, single-number-expression])

Meaning:

FIND (text_to_find, where_to_look[, position_to_start_the_search])

Returns:

A single integer

FIND returns the starting position of the text item specified by *text_to_find* within the text item specified by *where_to_look*. A third argument (*position_to_start_the_search*) can be used to specify the location in *where_to_look* for the FIND to begin. Bytes in the text are numbered from left to right, with the leftmost byte being position 1.

If text_to_find is "none", FIND evaluates to "none".

If a third argument is not used or *position_to_start_the_search* evaluates to a negative number, it is assumed to be 1. If *position_to_start_the_search* evaluates to a number greater than the size of *where_to_look*, FIND evaluates to "none".

If text_to_find is not found in the where_to_look string, FIND evaluates to 0.

Examples

• FIND ("id", "Florida")

Returns the value 5

• FIND ("id", "Florida", 8)

Returns 0 because the 8 (position_to_start_the_search) is greater than the size of where_to_look

• FIND ("\", "mypath",2)

Returns 0 because the string "\" was not found in argument 2

- LEFT
- MID
- RIGHT

HEXTEXTTOSTREAM

HEXTEXTTOSTREAM is the reverse of STREAMTOHEXTEXT. You can use the HEXTEXTTOSTREAM function to assign a binary text value to a character text item represented by hexadecimal pairs.

HEXTEXTTOSTREAM returns a binary text stream whose value is the evaluation of input character text represented by hexadecimal pairs.

Syntax:

HEXTEXTTOSTREAM (single-text-expression)

Meaning:

HEXTEXTTOSTREAM (series_of_hex_pairs)

Returns:

A single byte stream item

This function returns a binary text stream item whose value is the evaluation of input character text in *series_of_hex_pairs*, ignoring <WSP> characters between the hexadecimal pairs. White space characters include space, horizontal tab, carriage return, and line feed characters.

Input formats

The following table shows an example of input in its character text representation as viewed through the character editor, and in its ASCII code representation (binary text stream) as viewed through the hex editor. Each pair of binary text in the hex view represents one character in the character view of the character text.

Input ("41 42 43 44")	Editor View	Value
Character text (hex pairs)	Character	"41 42 43 44"
ASCII code representation (binary text stream)	Hex	0x3431203432203433203434

Examples

• HEXTEXTTOSTREAM ("41 42 43 44")

Returns the evaluated value of the input (ASCII) character text string "41 42 43 44" as the output (ASCII) character text string "ABCD" as viewed in the character editor. (The hex view of the input is 0x3431203432203433203434. The hex view of the output is 0x41424344.)

• HEXTEXTTOSTREAM ("OD 0A 00")

Returns the evaluated value of the input (ASCII) character text string "0D 0A 00" as the output (ASCII) character text string "<CR><LF><NULL>" as viewed in the character editor. (The hex view of the input is 0x3044203041203030. The hex view of the output is 0x0D0A00.)

See Design Studio Introduction documentation for a list of special symbols.

Related functions

- SYMBOL
- STREAMTOHEXTEXT

LEAVEALPHA

The LEAVEALPHA function removes all non-alphabetic characters from a specified text item.

You can use LEAVEALPHA to remove non-alphabetic characters such as symbols or numbers from a text item.

Syntax:

LEAVEALPHA (single-text-expression)

Meaning:

LEAVEALPHA (text_to_change)

Returns:

A single text item

LEAVEALPHA returns a string containing only the alphabetic characters (for example, A-Z and a-z) in text_to_change.

Examples

• LEAVEALPHA ("A-b-C-1\$3")

Returns: AbC

Related functions

- ISALPHA
- ISLOWER
- ISNUMBER
- ISUPPER
- LEAVEALPHANUM
- LEAVENUM
- LEAVEPRINT

LEAVEALPHANUM

The LEAVEALPHANUM function removes all non-alphanumeric characters (such as symbols) from a specified text item.

Syntax:

LEAVEALPHANUM (single-text-expression)

Meaning:

LEAVEALPHANUM (text_to_change)

Returns:

A single text item

LEAVEALPHANUM returns a string containing only the alphanumeric characters (for example, A-Z, a-z and 0-9) in text_to_change.

Examples

• LEAVEALPHANUM ("A-b-C-1\$3")

Returns: AbC13

Related functions

- ISALPHA LEAVEAL-
 - PHA
- ISLOWER
 LEAVENUM
- ISNUMBER LEAVEPRINT
- ISUPPER

LEAVENUM

The LEAVENUM function removes all non-numeric characters from a text item. For example, you can use LEAVENUM when you want to remove all alphabetic characters and symbols from a text string.

Syntax:

LEAVENUM (single-text-expression)

Meaning:

LEAVENUM (text_to_change)

Returns:

A single text item

LEAVENUM returns a string containing only the numeric characters (for example, 0-9) in text_to_change.

Examples

• LEAVENUM ("A-b-C-1\$3")

Returns: 13

Related functions

- ISALPHA LEAVEALPHA
- ISLOWER
 LEAVEAL PHANUM
- ISNUMBER
 LEAVEPRINT
- ISUPPER

LEAVEPRINT

The LEAVEPRINT function removes all non-printable characters from a text item.

Syntax:

LEAVEPRINT (single-text-expression)

Meaning:

LEAVEPRINT (text_to_change)

Returns:

A single text item

LEAVEPRINT returns a string containing only printable characters in text_to_change.

Examples

```
• LEAVEPRINT ("A-b<SP>C-1$3<CR><LF>")
```

Returns: A-b C-1\$3

HCL OneTest[™] Server

Related functions

- ISALPHA LEAVEALPHA
- ISLOWER LEAVEAL-PHANUM
- ISNUMBER
 LEAVENUM
- ISUPPER

LEFT

The LEFT function returns a specified number of characters from a text expression beginning with the leftmost byte of a text item.

You can use LEFT when you need a specific part of a text item. For example, a customer number might have several uses and sometimes only the first 10 characters are needed. Therefore, LEFT can be used to return only the leftmost 10 characters.

Syntax:

LEFT (single-text-expression, single-integer-expression)

Meaning:

LEFT (text_to_extract_from , number_of_characters_to_extract)

Returns:

A single text item

LEFT returns the leftmost *number_of_characters_to_extract* characters from *text_to_extract_from* starting at the first (the leftmost) character in *text_to_extract_from*.

If number_of_characters_to_extract evaluates to an integer whose value is less than 1, LEFT evaluates to "none". If number_of_characters_to_extract evaluates to an integer whose value is greater than the size of text_to_extract_from, LEFT evaluates to the entire value of text_to_extract_from.

Examples

• LEFT ("Abcd", 2)

Returns Ab

• LEFT ("Abcd", 6)

Returns Abcd

• LEFT (LastName + ", " + FirstName, 25)

Returns the leftmost 25 characters of the text string resulting from the concatenation of **LastName** and **FirstName** (separated by a comma and a space).

Related functions

- RIGHT
- MID
- FIND

LOWERCASE

The LOWERCASE function converts an alphabetic text item to all lowercase characters.

Syntax:

LOWERCASE (single-text-expression)

Meaning:

LOWERCASE (text_to_convert)

Returns:

A single text item

LOWERCASE produces a text item in which each byte from the input has been converted to lowercase. Any numeric or symbol characters in the text item remain unchanged.

Examples

LOWERCASE ("A1b2C!")

Returns: a1b2c!

Related functions

- ISLOWER
- ISUPPER
- UPPERCASE

MAX

The MAX function returns the maximum value from a series of number, date, time, or text values.

Syntax:

MAX (series-item-expression)

Meaning:

MAX (series_of_which_to_find_max)

Returns:

A single number

The result is the maximum value in the input argument series: number, text, or date/time.

Examples

• MAX (UnitPrice:Input)

If the values for UnitPrice are {20, 10, 100}, MAX returns 100.

MAX(EXTRACT(DueDate:Book:Library, CheckedOut:Book:Library = "Y"))

Returns the maximum (latest) DueDate for a book that is checked out from the library.

Related functions

• MIN

MID

You can use the MID function when you need specific characters from a text item. MID returns one or more characters from a text item.

Syntax:

MID (single-text-expression, single-number-expression, single-number-expression)

Meaning:

MID (source_text, position_to_start_the_search, number_of_characters)

Returns:

A single text item

MID extracts one or more characters from *source_text* where *position_to_start_the_search* is the position of the first character to extract and *number_of_characters* specifies the number of characters to extract. The first character (leftmost) of *source_text* has a starting position of 1.

If position_to_start_the_search is greater than the length of source_text, MID returns "none". If position_to_start_the_search or number_of_characters is less than one, MID returns "none". If the rightmost number of characters of source_text, starting at position_to_start_the_search, is less than number_of_characters, MID returns the rightmost characters starting at the position specified in position_to_start_the_search.

Examples

• MID ("abc123", 5, 3)

Returns 23

• MID ("abc123", 7, 1)

Returns "none" because argument2 is larger than the number of characters in argument1

• MID ("abc123", -1, 3)

Returns "none" because argument2 is a negative number

• MID ("abc123", 2 , -2)

Returns "none" because argument3 is a negative number

Related functions

- FIND
- LEFT
- RIGHT

MIN

Use MIN when you need the minimum value from a series of number, date, time, or text values.

The MIN function returns the minimum value from a series.

Syntax:

MIN (series-item-expression)

Meaning:

MIN (series_of_which_to_find_min)

Returns:

A single number

The result is the minimum value of the input series: number, text, or date/time.

Examples

• MIN (UnitPrice:Input)

If the values for UnitPrice are {20,10,100}, MIN returns 10.

• MIN (StartTime:.:Schedule)

Returns the minimum (earliest) StartTime in Schedule.

Related functions

• MAX

NORMXML

Use this function to remove XML formatting from an input XML fragment. The function accepts text items only.

Syntax:

NORMXML (single-text-expression)

Meaning:

NORMXML (XML fragment)

Returns:

A single text item

This function removes any XML whitespaces from between a (parent) start tag and the start tag of the first child element; and from between the end tag of the child element and the (parent) end tag. *XML whitespace* pertains to carriage returns, line feeds, tabs, and spaces.

For example, all carriage returns, line feeds, tabs, and spaces in between parent tags $\langle A \rangle$ and $\langle /A \rangle$ are removed, excluding any that are inside of child element tags $\langle a \rangle$ and $\langle /a \rangle$.

In the following example, there is a carriage return after $\langle A \rangle$, $\langle a \rangle$, and $\langle b \rangle$. There are also three spaces before $\langle a \rangle$ and three spaces before $\langle b \rangle$.

```
<A>
<a>This is sample text</a>
<b>More sample text</b>
</A>
```

The NORMXML function removes the three carriage returns and the six spaces. As a result, there is one line instead of four lines:

```
<A><a>This is sample text</a><b>More sample text</b></A>
```

Limitation

When a type has mixed content, the function removes any XML whitespaces from the character data sections. Here is the previous example, but with mixed content added:

```
<A>My first example
   <a>This is sample text</a>
   <b>More sample text</b>
</A>
```

This is the result of using the NORMXML function:

<A>Myfirstexample<a>This is sample textMore sample text

The XML whitespaces in My first example are removed because they are not enclosed within child element tags.

Using SIZE with NORMXML

The NORMXML function converts the input data to Unicode, and then removes the XML formatting from the input XML fragment. The conversion to Unicode is transparent because the normal processing automatically converts the data from Unicode to the character set that was assigned to the output object.

If the SIZE function is used with the NORMXML function to determine the size of the specified object after NORMXML removes the XML formatting from the input XML fragment, the SIZE operation calculates the size of the data as it exists at that time, in the Unicode character set. The returned size does not match the size that would have been calculated if the data remained in its original character set, unless the original character set was Unicode.

Using CSIZE with NORMXML

If the CSIZE function is used with the NORMXML function, the CSIZE operation returns the size in characters, regardless of the character set.

NUMBERTOTEXT

The NUMBERTOTEXT function converts a character number to a text item that looks like the original object.

You can use NUMBERTOTEXT when you need an object that is defined as a number converted to an object defined as text. This is useful when you need to concatenate text, however, the FROMNUMBER function provides greater flexibility in specifying the format of the resulting text item.

Syntax:

NUMBERTOTEXT (single-number-expression)

Meaning:

NUMBERTOTEXT (number_to_convert)

Returns:

A single text item

The resulting text looks like the input argument. The result is truncated, if necessary.

Examples

• NUMBERTOTEXT (ROUND (1000 - 24.75, 3))

This example converts the result of the calculation (rounded to 3 decimal places) to text, resulting in 975.250.

NUMBERTOTEXT (PurchaseNumber)

This example converts PurchaseNumber from a number to text.

Related functions

- FROMNUMBER
- TEXTTONUMBER
- TODATETIME
- TONUMBER

PACKAGE

The PACKAGE function converts a group or item object to a text item, including its initiator, terminator, and any delimiters it contains.

Syntax:

PACKAGE (single-object-expression)

Meaning:

PACKAGE (object_to_convert)

Returns:

A single text item

The PACKAGE function converts *object_to_convert*, which must be a type reference to a text item, including the type reference's initiator, terminator, and all delimiters. PACKAGE differs from TEXT in that it includes the initiator and terminator of the specified type reference.

Examples

• PACKAGE (Record:Card)

Returns: #1339X10A,491.38,Green,42x54@

For this example, the group **Record** has an initiator of "#", a terminator of "@" and a delimiter of ",". The data looks like this: "#1339X10A,491.38,Green,42x54@".

Related functions

- DATETOTEXT
- NUMBERTOTEXT
- SERIESTOTEXT
- TIMETOTEXT
- TEXT

PACKAGE differs from TEXT because it includes the initiator and terminator of the input object.

PROPERCASE

Use PROPERCASE to convert the first alphabetic character in each word to uppercase and all remaining characters to lowercase.

Syntax:

PROPERCASE (single-text-item-expression)

Meaning:

PROPERCASE (text_item_to_convert)

Returns:

A single text item

The PROPERCASE function views the text string as containing a series of "words" where the delimiter between words is the space character. For each "word" in *text_item_to_convert*, PROPERCASE converts the first alphabetic character (for example, A-Z and a-z) found to uppercase and all other characters are converted to lowercase.

Example

PROPERCASE ("sallY jo BRADLEY")

Returns: Sally Jo Bradley

Related functions

- ISALPHA
- ISLOWER
- ISUPPER
- LOWERCASE
- UPPERCASE

RANDDATA

The RANDDATA function returns random text based on the properties of the output type. The RAND function returns a pseudo-random integer between 0 and RAND_MAX (guaranteed to be at least 32,767). The RANDDATA function generates a valid random value of the item type that is being built when it is invoked.

Syntax:

RANDDATA ()

Meaning:

RANDDATA ()

Returns:

A single object (text, a date/time object, or a number)

RANDDATA takes no parameters. If the SEED function is called prior to RANDDATA, RANDDATA will return the same value for the same item properties it is returning to, based on the value to SEED.

Related functions

- RAND
- SEED

REVERSEBYTE

Use the REVERSEBYTE function when you need the bytes in the opposite sequence. REVERSEBYTE reverses the byte order of an item.

Syntax:

REVERSEBYTE (single-item-expression)

Meaning:

REVERSEBYTE (item_to_reverse)

Returns:

A single item

This function reverses the byte order of *item_to_reverse*.

Examples

• REVERSEBYTE ("HI MOM!")

Returns "!MOM IH"

• RIGHT (FullName, FIND (" ", REVERSEBYTE (FullName)) - 1)

If **FullName** is "Alyce N. Wunderland", the above example uses REVERSEBYTE to reverse the characters in **FullName** (resulting in "dnalrednuW .N ecylA"). Then, the FIND function is evaluated to locate the first space in the resultant string (between the "W" and the ".") that would result in a value of 11. Finally, the RIGHT function is evaluated to take the rightmost 10 (11-1) characters of **FullName**; providing the final result of "Wunderland".



Note: The examples are used for illustration only. Do not use this function with string literals.

RIGHT

You can use RIGHT when you need a specific part of a text item. For example, a customer number might have several uses and sometimes only the last three characters are needed. RIGHT can be used to return only the rightmost three characters.

The RIGHT function returns a specified number of characters from a text expression beginning with the rightmost byte of a text item.

Syntax:

RIGHT (single-text-expression, single-integer-expression)

Meaning:

RIGHT (text_to_extract_from , number_of_characters_to_extract)

Returns:

A single text item

RIGHT returns the rightmost *number_of_characters_to_extract* characters from *text_to_extract_from* starting at the last (the rightmost) character in *text_to_extract_from*.

If number_of_characters_to_extract evaluates to an integer whose value is less than 1, RIGHT evaluates to "none". If number_of_characters_to_extract evaluates to an integer whose value is greater than the size of text_to_extract_from, RIGHT evaluates to the entire value of text_to_extract_from.

Examples

• RIGHT ("Abcd", 2)

Returns cd

• RIGHT ("Abcd", 6)

Returns Abcd

• RIGHT ("000000" + NUMBERTOTEXT (TransactionNum), 6)

If **TransactionNum** contains 123, this example returns 000123. If **TransactionNum** contains 123456789, this example returns 456789.

Related functions

- FIND
- LEFT
- MID

SEED

The SEED function primes the RAND and RANDDATA functions so they produce repeated results.

Syntax:

SEED(single-number-expression)

Meaning:

SEED(number_for_seed)

Returns:

NONE

Related functions

- RAND
- RANDDATA

SERIESTOTEXT

You can use the SERIESTOTEXT function to project your input data as a series and to interpret it as a text item for output.

SERIESTOTEXT converts a contiguous or non-contiguous series to a text item.

Syntax:

SERIESTOTEXT (series-object-expression)

Meaning:

SERIESTOTEXT (series_to_convert)

Returns:

A single text item

SERIESTOTEXT returns a text item containing the concatenation of the series of the input argument, including nested delimiters but excluding initiators and terminators.

Examples

In this example, you have the following data that represents bowler information for a bowling league:

Andrews, Jessica:980206:JBC:145:138:177:159

Little, Randy:980116:BBK:175:168

Wayne, Richard:980102:JBC:185:204:179:164:212

Each record consists of the bowler's name, the date of their last game played, a team code and one or more bowling scores. **Record** is defined as a group that is infix-delimited by a colon.

Using the rule:

= SERIESTOTEXT (Score Field:Bowler:Input)

the following results are produced, which is the concatenation of all of the scores for all of the bowlers, even though the scores are not all contiguous within the data:

145138177159175168185204179164212

However, if the rule was changed, for instance, to concatenate the list of scores to the bowler's name:

= BowlerName Field:Bowler:Input + " ->" + SERIESTOTEXT (Score Field:Bowler:Input)

the following output would be produced:

Andrews, Jessica -> 145138177159

Little, Randy -> 175168

Wayne, Richard -> 185204179164212

In this example, you have an input number that is of variable size, followed by a name. There is no syntax that separates the number from the name. You can define the number as a group with **Byte(s)** as a component and provide a component rule for **Byte(s)**, such as:

ISNUMBER (\$)

Related functions

- PACKAGE
- TEXT

SQUEEZE

The SQUEEZE function removes consecutive duplicate occurrences of a specified character or characters from a text item.

Syntax:

SQUEEZE (single-text-item , single-text-item)

Meaning:

SQUEEZE (text_to_squeeze, duplicate_characters_to_remove)

Returns:

A single text item

SQUEEZE returns a text item with all the consecutive duplicates of *duplicate_characters_to_remove* removed from *text_to_squeeze*.

Examples

• SQUEEZE ("AB CDE F", " ")

Returns: AB CDE F

• SQUEEZE ("Connolly", "n")

Returns: Conolly

Related functions

- LEAVEALPHA
- LEAVEALPHANUM
- LEAVENUM
- LEAVEPRINT
- SUBSTITUTE

SUBSTITUTE

You can use the SUBSTITUTE function to replace or remove a character. You can also use this function for multiple pairs.

Syntax:

SUBSTITUTE (single-text-expression {, single-text-expression , single-text-expression })

Meaning:

SUBSTITUTE (item_to_convert, one-or-more-text-substitution-pairs)

Where each one-or-more-text substitution-pair is text_to_change , substitute_text

Returns:

A single text item

SUBSTITUTE returns the text string that results from replacing all instances of the first text_to_change with substitute_text in item_to_convert, then replaces all instances of the second text_to_change with the substitute_text in the result of the first substitution, and so forth.

Examples

• SUBSTITUTE ("123*456*7" , "*" , "/")

Finds 123*456*7 and returns 123/456/7

• SUBSTITUTE ("120-45-6789" , "-" , "")

Finds 120-45-6789 and returns 120456789

• =SUBSTITUTE ("ABBA" , "B", "A", "A", "B")

This example illustrates multiple searches for the SUBSTITUTE function.

The first search-and-replace finds all "B"s and returns "A"s: AAAA

The next search-and-replace finds all "A"s and returns "B"s: BBBB

The end result is a return of: BBBB

Related functions

- LEAVEALPHA
- LEAVEALPHANUM
- LEAVENUM
- LEAVEPRINT
- SQUEEZE

TEXT

You can use the TEXT function to convert an object to a text item or when echoing entire data objects to another map.

TEXT converts the content of a group or item object to a text item.

Syntax:

TEXT (single-object-expression)

Meaning:

TEXT (object_to_convert)

Returns:

A single text item

The TEXT function converts object_to_convert to a text-item, excluding the initiator and terminator of the input object.

Examples

• TEXT (Record:card)

Data: #1339X10A,491.38,Green,42x54@

Returns: 1339X10A,491.38,Green,42x54

In this example, the group **Record** has an initiator of the pound sign (#), a terminator of the at-sign (@), and a delimiter of a comma (,).

The initiator and terminator are not included because only the content of the object is converted to text.

Related functions

- DATETOTEXT
- FROMDATETIME
- FROMNUMBER
- NUMBERTOTEXT
- PACKAGE

Note: TEXT differs from PACKAGE in that it does not include the initiator and terminator of the input object.

- SERIESTOTEXT
- TIMETOTEXT

TEXTTOBCD

The TEXTTOBCD function converts a text item from decimal digits to BCD (Binary Coded Decimal) format.

Syntax:

TEXTTOBCD (single-integer-text-expression)

Meaning:

TEXTTOBCD (text_to_be_converted)

Returns:

A single BCD-formatted text item

TEXTTOBCD converts *text_to_be_converted* (which consists of decimal digits) to BCD format. In this format, each byte contains two decimal digits represented as binary numbers. If there is an odd number of decimal digits in the input, the high-order half-byte of the leftmost output byte will contain the decimal value 15 (hex "F").

If anything other than a decimal digit is encountered in the input, TEXTTOBCD returns "none".

Examples

• TEXTTOBCD ("1234")

Returns the hexadecimal value x'1234'

• TEXTTOBCD ("123A")

Returns "none"

• TEXTTOBCD ("123")

Returns the hexadecimal value x'F123'

In this example, the values shown as input ("123") are meant to represent character items in the native character set to the machine on which the map is running. On a personal computer, "123" would contain the ASCII characters for the digits that have the hexadecimal values "31", "32", and "33". The output, described as "the hexadecimal value `F123''', consists of the two binary bytes "F1" and "23".

On an IBM mainframe the input string would contain EBCDIC characters for the digits that have the hexadecimal values "F1", "F2", "F3", \hat{A}^{o} , but the output would be the same as the personal computer output.

Related functions

- BCDTOHEX
- BCDTOINT
- BCDTOTEXT

TEXTTONUMBER

Use TEXTTONUMBER to convert text to a number.

The TONUMBER function provides greater flexibility for specifying the format of the text item that is to be converted to a number.

Syntax:

TEXTTONUMBER (single-text-expression)

Meaning:

TEXTTONUMBER (text_to_convert_to_number)

Returns:

A single character number

The *text_to_convert_to_number* must be in integer or ANSI-formatted (floating point) presentation. The resulting number looks like the input argument, however, nonsignificant zeroes to the right of the decimal separator will be truncated. If the input argument is in error (for example, it is not a recognizable as a valid number), the result is "none".

When specified as in ANSI-formatted presentation, the text string must meet the following requirements:

- The decimal point can be a period, a comma, or "none".
- The leading sign can be a plus sign, a minus sign, or "none".
- No thousands separator is allowed.

Examples

• TEXTTONUMBER (OrderQty)

Returns OrderQty as a character number item

Related functions

- DATETOTEXT
- FROMNUMBER
- NUMBERTOTEXT
- TEXTTODATE

- TEXTTOTIME
- TIMETOTEXT

TEXTTOTIME

Use TEXTTOTIME when you want to convert an object defined as text that is in HHMM or HHMMSS presentation, to an item defined as time. For greater flexibility, use the TODATETIME function for specifying the format of the text item that is to be converted to a date/time.

Syntax:

TEXTTOTIME (single-text-expression)

Meaning:

TEXTTOTIME (text_to_convert_to_time)

Returns:

A single time

The text_to_convert_to_time must be in HHMM or HHMMSS presentation. HH is a two-digit hour in a 24-hour format. If the result is being assigned to a time object, the resulting time looks like the output object. Otherwise, the resulting time looks like the input argument. If the input argument is in error (for example, it is not a valid time), the result is "none".

Examples

• TEXTTOTIME (CallTime)

Returns CallTime as a time item

Related functions

- DATETOTEXT TEXTTONUM-BER
- FROMDATETIME TIMETOTEXT
- NUMBERTO- TODATETIME TEXT
- TEXTTODATE

TIMETOTEXT

You can use the TIMETOTEXT function to perform text concatenation. For greater flexibility, use the FROMDATETIME function for specifying the format of the resulting text item.

TIMETOTEX converts a time object or expression to a text item.

Syntax:

TIMETOTEXT (single-time-expression)

Meaning:

TIMETOTEXT (time_to_convert_to_text)

Returns:

A single text item

If *time_to_convert_to_text* is a time object name, this returns the time as a text item formatted according to the presentation of the input date object.

If *time_to_convert_to_text* is a time expression produced by a function, this returns the time as a text item formatted according to the presentation of the output argument of that function.

Examples

• TIMETOTEXT (LeadTime)

In this example, **LeadTime** is converted from a time to text. If **LeadTime** has an HH:MM presentation, the resulting text item will be of that presentation.

• TIMETOTEXT (CURRENTDATETIME ("{HH:MM:SS}"))

Here, CURRENTDATETIME evaluates and returns a time in HH:MM:SS format. Then, TIMETOTEXT evaluates and returns a text string that is that time in HH:MM:SS format.

Related functions

- DATETOTEXT
- FROMDATETIME
- NUMBERTOTEXT
- TEXTTODATE
- TEXTTONUMBER
- TEXTTOTIME
- TODATETIME

TODATETIME

The TODATETIME function converts a text string of a specified format to a date-time item.

Syntax:

TODATETIME (single-character-text-expression [, single-text-expression])

Meaning:

TODATETIME (text_to_convert [, date_time_format_string])

Returns:

A single character date item

TODATETIME returns the date-time that corresponds to the value specified by *text_to_convert*, which is in the format specified by *date_time_format_string*. If *date_time_format_string* is not specified, it will be assumed that *text_to_convert is* in [CCYYMMDDHH24MMSS] format.

The date_time_format_string must conform to the date-time format strings as described in "Format strings".

Examples

• TODATETIME ("05/14/1999@10:14pm" , "{MM/DD/CCYY}@{HH12:MMAM/PM}")

In this example, a text string containing a date and time is converted to a date-time item.

• RptDate = TODATETIME (RIGHT (GETRESOURCENAME() , 8) , "CCYYMMDD")

Assume that you receive a file that contains historical data. The name of the file identifies the date of the historical data. For example, a filename of **19960424** indicates that the data was produced on April 24, 1996. To map this date to **RptDate**, the TODATETIME function could be used with the RIGHT and GETRESOURCENAME functions.

Related functions

- CURRENTDATE
- CURRENTDATETIME
- CURRENTTIME
- TEXTTODATE
- TEXTTOTIME

TONUMBER

The TONUMBER function converts a text string of a specified format to a number.

Syntax:

TONUMBER (single-character-text-expression [, single-text-expression])

Meaning:

TONUMBER (text_to_convert [, number_format_string])

Returns:

A single character number item

TONUMBER returns the number that corresponds to the value specified by *text_to_convert*, which is in the format specified by *number_format_string*. If *number_format_string* is not specified, it will be assumed that *text_to_convert* is in ANSI decimal format (for example, "{L-####['.'##]}").

The number_format_string must conform to the number format strings as described in the "Format strings" topic.

Examples

TONUMBER(text_to_convert, "{L+'\$'#', ###}")

L+'\$' indicates the leading dollar sign is positive. That leading sign and the comma separators are removed when the text is converted to a number.

Input String: \$123,000,000

Output: 123000000

TONUMBER(text_to_convert, "{####T-}")

Four number signs are required for each whole number, regardless of the actual number of digits in the number.

Input string:	Output:	Note:
12345-	-12345	The output becomes a negative number.
67890	67890	No change occurs.
345-	-345	The output becomes a negative number.

TONUMBER(text_to_convert, "{####T+'K'-}")

If an invalid character, such as an X, is encountered, nothing is returned.

If a K is encountered, it is treated as a positive indicator.

Input string:	Output:	Note:
11212-	-11212	The output becomes a negative number.
67890X		The X is an invalid character. No number is returned.
54354	54354	No change occurs.
34567K	34567	The K is recognized as a positive sign. The character is re- moved and the number is returned as a positive.
345-	-345	The output becomes a negative number.

• TONUMBER(text_to_convert, "{L-'('#', ###T-')'}")

The parentheses indicating a negative number are removed and replaced with a negative sign.

Comma separators are removed when the text is converted to a number.

Input string:	Output:	Note:
(12,345)	-12345	The output becomes a negative number. The comma sepa- rator is removed.
67,890	67890	The comma separator is removed.
(345)	-345	The output becomes a negative number.

• TONUMBER(text_to_convert, "{#[',']###['.'##5]T+'K'-}")

The optional comma separators are removed, but the decimal points and decimal values are retained.

Input string:	Output:	Note:	
54,345.098	54354.098	The comma separator is removed.	
67890.0X		The X is an invalid character. No number is returned.	
11213-	-11213	The output becomes a negative number.	
34567K	34567	The K is recognized as a positive sign. The character is removed and the number is returned as a positive.	
345.1-	-345.1	The output becomes a negative number.	

Related functions

- DATETONUMBER
- FROMNUMBER
- NUMBERTODATE
- NUMBERTOTEXT

TRIMLEFT

You can use the TRIMLEFT function to remove spaces or a text string at the beginning of some text.

TRIMLEFT removes leading characters from a text item.

Syntax:

TRIMLEFT (single-text-expression [, single-text-expression])

Meaning:

```
TRIMLEFT ( item_to_trim [ , text_to_trim ] )
```

Returns:

A single text item

TRIMLEFT removes leading characters that match *text_to_trim* from *item_to_trim* and returns the result as a single text item. If *text_to_trim* is not specified, leading spaces are removed from *item_to_trim*.

Examples

• TRIMLEFT (" abc")

Returns: abc

• TRIMLEFT ("000345" , "0")

Returns: 345

• TRIMLEFT (LastName Column:Row , "<WSP>")

Returns the content of **LastName Column** after removing all leading whitespace characters (space, horizontal tab, carriage return, or line feed characters).

Related functions

• FILLLEFTP	LEAVEPRINT
• FILLRIGHT	• SQUEEZE
• LEAVEALPHA	SUBSTITUTE
• LEAVEAL- PHANUM	• TRIMRIGHT

LEAVENUM

TRIMRIGHT

You can use the TRIMRIGHT function to remove spaces or a text string at the end of text.

TRIMRIGHT removes trailing characters from a text item.

Syntax:

TRIMRIGHT (single-text-expression [, single-text-expression])

Meaning:

TRIMRIGHT (item_to_trim [, text_to_trim])

Returns:

A single text item

TRIMRIGHT removes trailing characters that match *text_to_trim* from *item_to_trim* and returns the result as a single text item. If *text_to_trim* is not specified, trailing spaces are removed from *item_to_trim*.

Example

• TRIMRIGHT ("abc ")

Returns: abc

• TRIMRIGHT ("Cat in the Hat!?!?!?" , "!?")

Returns: Cat in the Hat

• TRIMRIGHT (LastName Column:Row)

Returns the content of LastName Column after removing all trailing spaces.

Related functions

- FILLLEFTP LEAVEPRINT
- FILLRIGHT SQUEEZE
- LEAVEALPHA SUBSTITUTE
- LEAVEAL- TRIMLEFT PHANUM
- LEAVENUM

UPPERCASE

The UPPERCASE function converts text to all uppercase characters.

Syntax:

UPPERCASE (single-text-expression)

Meaning:

UPPERCASE (text_to_convert)

Returns:

A single text item

UPPERCASE produces a text item in which each byte in *text_to_convert* has been converted to uppercase. Any numeric or symbolic characters in *text_to_convert* remain unchanged.

Examples

• UPPERCASE ("abC123!")

Returns ABC123!

Related functions

- ISLOWER
- ISUPPER
- LOWERCASE

WORD

You can use the WORD function to parse a text item that is delimited by some character, such as a space or a comma.

WORD returns the characters between two user-defined separators within a text item. The separators are counted from left to right when the third argument is positive, and from right to left when the third argument is negative, enabling the function to search from either end of the item.

Syntax:

WORD (single-text-expression , single-text-expression , single-integer-expression)

Meaning:

WORD (text_to_search , word_separator , number_of_word_to_get)

Returns:

A single text item

WORD returns the characters (word) between the *n*th-1 and *n*th *word_separator*, where *n* corresponds to *number_of_word_to_get*.

Define the separator (*word_separator*) and specify the number of the occurrence of that separator. The WORD function returns the characters between the *nth-1* and *n*th separators in the delimited text item.

The separator is case sensitive.

Examples

The following examples assume that a file exists named Letter with two text objects named Line1 and Line2:

```
Linel:Congratulations, Mr Brown! You're a winner!;
```

Line2:You may have already won 1 million dollars!;

• WORD (Line1:Letter, "", 3)

Returns: Brown!

The exclamation point is returned because it is read as a character within the word before the separator (a space).

```
• WORD ( Line1:Letter , " " , 6 )
```

Returns: winner!

If the *n*th separator is missing and the *nth-1* separator exists, the function returns the characters between the last separator and the end of the delimited text item. The separator is a space; "winner!" (including the exclamation point) is the sixth word.

• WORD (Line2:Letter , "!" , 3)

Returns "none"

Both *nth* and *nth-1* separators are missing. In this example, there is only one separator, located at the end of the text object. As a result, there is no third word because the function sees everything before "!" as the first word.

• WORD (Line1:Letter, "", 1)

Returns: Congratulations,

If n-1 = 0, the function returns the characters between the beginning of the delimited text item and the first separator.

```
• WORD ( Line1:Letter , " " , -1 )
```

Returns: winner!

If n+1 = 0, then the function returns the characters between the end of the text item and the last separator.

Related functions

- FIND
- MID

XML functions

There are several XML functions that you can call from component rules and map rules to process input XML data. They fall under two different categories. The XML functions in one category are called through the XMLLIB library. They are the XPATH (used with XMLLIB), VALIDATEEX, VALIDATE, XPATHEX, XSLT (used with XMLLIB), and XSLTEX functions. The XML functions in the other category are called directly, without using the XMLLIB library. They are the XPATH, XVALIDATE, and XSLT functions.

VALIDATE

The VALIDATE function validates the XML input by using the XMLLIB library.

This function validates XML input, which is provided as a text stream or URL, against the provided XML Schema, returning o if the validation succeeded or -1 otherwise.

Syntax:

VALIDATE (single-text-expression, single-text-expression)

Meaning:

VALIDATE (xml_url_or_xml_fragment, target_namespace XML_schemaname)

Returns:

A single number

Exemple

Examples

• NUMBERTOTEXT(xmllib->VALIDATE("ipo.in.xml", "urn:hl7-org:v3 http://www.example.com/IPO ipo.xsd"))

Returns o when validation of the ipo.in.xml file succeeds and returns -1 otherwise.

• VALID(NUMBERTOTEXT(xmllib->VALIDATE(PACKAGE(source), "ipo.xsd")), LASTERRORMSG())

Returns o when validation of the input XML fragment succeeds or returns a validation error message otherwise.

VALIDATEEX

The VALIDATEEX function validates the XML input, and logs the function processing in the directory where the map runs by using the XMLLIB library.

This function validates XML input, which is provided as a text stream or URL, against the provided XML Schema. The VALIDATEEX function returns **o** if the validation succeeded or **i** if validation failed, and generates the specified trace log file in the directory.

Syntax:

VALIDATEEX (single-text-expression, single-text-expression, tracelog)

Meaning:

VALIDATEEX (xml_url_or_xml_fragment, target_namespace XML_schemaname, trace_file_name.extension)

Returns:

A single number

Exemple

Example

 NUMBERTOTEXT(xmllib->VALIDATEEX("ipo.in.xml", "urn:hl7-org:v3 http://www.example.com/IPO ipo.xsd", "numtotext.log"))

Returns o when validation of the ipo.in.xml file succeeds or returns -1 when validation fails, and generates a trace log of function processing.

XVALIDATE

The XVALIDATE function validates the XML input.

This function validates XML input, provided as a text stream or URL, against the provided XML Schema.

Syntax:

XVALIDATE (single-text-expression, single-text-expression)

Meaning:

XVALIDATE (xml_url_or_xml_fragment, target_namespace XML_schemaname)

Returns:

This function evaluates to a Boolean "true" or "false".

Exemple

Examples

• IF(XVALIDATE("ipo.in.xml", "http://www.example.com/IP ipo.xsd"), "VALIDATION SUCCESS", LASTERRORMSG())

Returns the message VALIDATION SUCCESS when the validation of the ipo.in.xml file succeeds and returns a message that explains the validation error otherwise.

XPATH functions

XPATH

The XPATH function queries the XML input.

This function queries the XML input, which is provided as a text stream or URL, by using the specified XPATH expression and context, returning the result of the evaluation.

Syntax:

XPATH (single-text-expression, single-text-expression, single-text-expression)

Meaning:

XPATH (xml_url_or_xml_fragment, xpath_expression, context_expression)

Returns:

A single text item

Exemple

Examples

• XPATH("current://ipo.in.xml", "/ipo:purchaseOrders/order/items/item[1]/shipDate", "ipo http:// www.example.com/IPO")

Returns the content of the shipDate element from the ipo.in.xml file.

• XPATH(PACKAGE(source), "/ipo:purchaseOrders/order/items/item[1]/shipDate", "ipo http://www.example.com/ IPO")

Returns the content of the shipDate element from the input XML fragment.

XPATH used with XMLLIB

The XPATH function that is used with XMLLIB queries the XML input.

This function queries the XML input, which is provided as a text stream or URL, by using the specified XPATH expression and context, returning the result of the evaluation.

Syntax:

XPATH (single-text-expression, single-text-expression, single-text-expression)

Meaning:

XPATH (xml_url_or_xml_fragment, xpath_expression, context_expression)

Returns:

A single text item

Exemple

Examples

- xmllib->XPATH("ipo.in.xml", "./order//item[1]/shipDate", "/ipo:purchaseOrders ")
- Returns the content of the shipDate element from the ipo.in.xml file.
- xmllib->XPATH(PACKAGE(source), "/ipo:purchaseOrders/order/items/item[1]/shipDate", "/")

Returns the content of the shipDate element from the input XML fragment.

XPATHEX

The XPATHEX function queries the XML input by using the XMLLIB library, and logs function processing in the directory where the map runs.

This function queries the XML input, provided as a text stream or URL, by using the specified XPath expression and context. The XPATHEX function returns the result of the evaluation and generates the specified trace log file in the directory where the map runs.

Syntax:

XPATHEX (single-text-expression, single-text-expression, single-text-expression, tracelog)

Meaning:

XPATHEX (xml_url_or_xml_fragment, xpath_expression, context_expression, trace_file_name.extension)

Returns:

A single text item

Exemple

Example

• xmllib->XPATHEX("ipo.in.xml", "./order//item[1]/shipDate", "/ipo:purchaseOrders ", "xpathlog.txt")

Returns the content of the shipDate element from the ipo.in.xml file and generates a trace log of function processing.

XSLT functions

XSLT

The XSLT function applies an XSLT transformation.

This function applies an XSLT transformation, expressed as a text stream or URL, to the provided XML input, returning the result of the transformation.

Syntax:

XSLT (single-text-expression, single-text-expression)

Meaning:

XSLT (xml_url_or_xml_fragment, xslt_url_or_xslt_fragment)

Returns:

A single text item

Exemple

Examples

• XSLT("current://ipo.in.xml", "current://ipo.xsl")

Applies the XSLT transformation that is defined in the ipo.xsl file to the ipo.in.xml file.

```
• XSLT( PACKAGE( source ), "current://ipo.xsl" )
```

Applies the XSLT transformation that is defined in the ipo.xsl file to the input XML fragment.

XSLT used with XMLLIB

The XSLT function that is used with XMLLIB applies an XSLT transformation.

This function applies an XSLT transformation, expressed as a text stream or URL, to the provided XML input, returning the result of the transformation.

Syntax:

XSLT (single-text-expression, single-text-expression)

Meaning:

XSLT (xml_url_or_xml_fragment, xslt_url_or_xslt_fragment)

Returns:

A single text item

Exemple

Examples

```
• xmllib->XMLLIB XSLT( "ipo.in.xml", "ipo.xsl" )
```

Applies the XSLT transformation that is defined in the ipo.xsl file to the ipo.in.xml file.

```
• xmllib->XMLLIB XSLT( PACKAGE( source ), "ipo.xsl" )
```

Applies the XSLT transformation that is defined in the ipo.xsl file to the input XML fragment.

XSLTEX

The XSLTEX function applies an XSLT transformation to the XML input, and logs the function processing in the directory where the map runs by using the XMLLIB library.

This function applies an XSLT transformation, expressed as a text stream or URL, to the provided XML input. The XSLTEX function returns the result of the transformation and generates the specified trace log file in the directory.

Syntax:

XSLTEX (single-text-expression, single-text-expression, tracelog)

Meaning:

XSLTEX (xml_url_or_xml_fragment, xslt_url_or_xslt_fragment, trace_file_name.extension)

Returns:

A single text item

Exemple

Example

• xmllib->XSLTEX("ipo.in.xml", "ipo.xsl", "transform.log")

Applies the XSLT transformation that is defined in the ipo.xsl file to the ipo.in.xml file, and generates a trace log of function processing

Custom functions

From the Type Designer or Map Designer, you can create custom functions to call external libraries. While the EXIT function is often used to call external libraries, the EXIT function is limited to support only text objects and is operating system dependent. When you create a custom function to use in a map rule, the function is operating system independent and supports text, number, and date-time objects.

Similar to the regular functions that are shipped with the product, a maximum of four parameters are supported per argument.

Creating a custom function

To create your own functions, a C or C++ development tool is required, or the Java Native Interface (JNI) if you are working in a Java environment.

 From a component rule in the Type Designer or from a map rule in the Map Designer, right-click and select the Insert Function option.
 (Additionally in the Map Designer, if you are not in a map rule, you can create a new function by selecting

Rules > New Function.)

2. From the Insert Function window, select Design.

Result

The Custom Function Modules window is displayed.

3. In the **Path** field, enter the path of where to create the external library.

This should always be in the *install_dir/*function_libs directory.

4. In the Name field, enter a name for the library.

5. Click Add to add a function to the library.

Result

The Function Specifics window is displayed.

- 6. In the Name field, enter a name for the function.
- 7. For Return Type, select the function return type from the drop-down list.

You can select up to four function parameters from the respective drop-down list. Choices include Boolean, date, number, text, time, and byte stream.

8. In the space provided, enter a description for your function.

This information will be displayed in the Insert Function window of both Designers.

- 9. Click OK to validate the selected parameters and close the Function Specifics window.
- 10. Click Generate.

Result

The Designer generates a collection of operating system specific makefiles and definition files that provide the framework for the function you are creating.

11. Go to the *install_dir*/function_libs directory to view the results.

Result

As a result of the generation process, framework files are created for each operating system that HCL® OneTest[™] Data supports. You can find the operating system-specific makefiles and definition files in the *install_dir/*function_libs/*your_new_lib* directory.

12. Now you must modify the framework that was generated by the Designer.

The following functions with the parameter information that you selected were exported to the .c file:

- GetFunctionCount
- GetFunctionName
- · GetInputParameter
- GetReturnType
- GetParameterCount
- GetFunctionDesc

To complete the new function, open the .c file and add your programming code for the applicable function or functions provided.

Use the .c file to build your dynamic link library (DLL) and then place the DLL in the *install_dir/*function_libs/*your_new_lib* directory. (All custom designed libraries and functions must be placed in the *install_dir/*function_libs directory.)

The new library name is listed under **Category** in the **Insert Function** window, and the new function that you created is placed in the list of functions and will remain available for future use from both the Type Designer and Map Designer applications.

Exemple

The following example displays how to implement a custom function called SIN.

```
void ConvertToBytes(double returnValue, LPEXITPARAM lpep)
{
```

```
double value = 0.0;
  int decimal = 2, sign = 0, j = 0, k = 0;
  char byString[100];
  char* lpbyData = _fcvt(returnValue, 7, &decimal, &sign );
  memset(byString, 0, sizeof(byString));
  if (sign)
       byString[j++] = '-';
  if (decimal <= 0)
  {
  byString[j++] = '0';
  byString[j++] = '.';
   while (decimal != 0)
   {
    byString[j++] = '0'; decimal++;
   }
  }
  else if (decimal > 0)
  {
   while (decimal != 0)
   {
    byString[j++] = lpbyData[k++]; decimal--;
   }
    byString[j++] = '.';
  }
  while (lpbyData[k]) byString[j++] = lpbyData[k++];
  byString[j] = '\0';
  if (NULL == (lpep->lpDataFromApp = GlobalAllocPtr
    (GHND, j + 1)))
  {
  lpep -> nReturn = -1;
  lstrcpy(lpep->szErrMsg, "Memory allocation failed in Alternate");
  return;
  }
  memcpy(lpep->lpDataFromApp, byString, j);
 lpep->dwFromLen = j;
  lpep->lpDataFromApp[j++] = '\0';
}
void CALLBACK EXPORT SIN(LPEXITPARAM lpep)
{
 double value = 0.0;
 double returnValue = 0.0;
 LPEXITPARAMEXTENDED lpExtended = NULL;
  if (lpep->dwSize != sizeof(EXITPARAM))
  {
  return;
  }
  lpExtended = (LPEXITPARAMEXTENDED)lpep->lpv;
value = atof(lpExtended->lpFirstInputParameter);
```

```
returnValue = sin(value);
ConvertToBytes(returnValue, lpep);
  lpep->wCleanupAction = GetReturnType("SIN");
lstrcpy(lpep->szErrMsg, "SIN function was successful");
return;
}
```

What to do next

At run time, all custom designed libraries and functions that your maps use must be in the *install_dir/*function_libs directory. When you deploy a map that uses a custom function to a remote host, the library is not transferred. Therefore you must manually copy the custom function library to the install_dir/ function_libs directory on the remote host.

Date and time format strings

You can use the listed format strings for numbers, dates and times in functions such as the CURRENTDATETIME, FROMNUMBER, TONUMBER, FROMDATETIME, and TODATETIME.

Create custom date and time formats by using the symbols based on the given format strings.

Time units

Symbol

Description

HH24

Hour (based on a 24-hour clock) in two digits (00 to 24)

H24

Hour (based on a 24-hour clock) in one or two digits as needed (0 to 24)

HH12

```
Hour (based on a 12-hour clock) in two digits (1-12)
```

H12

Hour (based on a 12-hour clock) in one or two digits as needed (1 to 12)

MM

Minute in two digits (00 to 59)

Μ

Minute in one or two digits as needed (0 to 59)

SS

Seconds in two digits (00 to 59)

S

Second in one or two digits as needed (0 to 59)

AM/PM

Meridian (AM/PM)

ZZZ

Three character abbreviation for time zone (EST, and so on)

+/-ZZZZ

Hours and minutes before or after Greenwich Mean Time (GMT), also known as Coordinated Universal Time (UTC)

+/-ZZ:ZZ

4-digit time where the format is a 2-digit hour and 2-digit minute, separated by a colon.

+/-ZZ[:ZZ]

4-digit time where the format is a 2-digit hour and an optional 2-digit minute, separated by colon.

+/-ZZ[ZZ]

4-digit time where the format is a 2-digit hour and an optional 2-digit minute.

TZD

4-digit time where the format is a 2-digit hour and 2-digit minute, separated by a colon. Z on output, if value is +/-00:00.

Date units

Symbol

Description

CCYY

Full year including century (2001)

YΥ

Last two digits of the year (00-99)

MM

Month of the year in two numeric digits (01-12)

М

Month of the year in one or two numeric digits as needed (1 to 12)

MON

First three letters of the month (Jan to Dec)

MONTH

Full name of the month (January to December)

DDD

Day of the year in three numeric digits (001 to 366)

DD

Day of the month in two numeric digits (01 to 31)

D

Day of the month in one or two numeric digits as needed (1 to 31)

DY

First three letters of the weekday (Sun to Sat)

DAY

Full name of the weekday (Sunday to Saturday)

ww

Week of year (1-52)

Qn

Quarter of the year (Q1-Q4)

EEYY

Emperor's year, long form

EY

Emperor's year, short form

Binary date and time format strings

Sub-String Name

Sub-String Value

Binary DateTime

["{" + Date + "}"] + ["{" + Time + "}"]

Date

CCYYMMDD

YYMMDD

CCYYDDD

YYDDD

Time

HH24MMSS

HH24MM

Japanese date and time format strings

Sub-String Name

Sub-String Value

Japanese DateTime

"{" + DateTime + "}"

"{" + DateTime + "}" + Separator(1) + "{" + DateTime + "}"

"{" + DateTime + "}" + "[" + Separator(1) + "{" + DateTime + "}" + "]"

DateTime

Date

Time

Separator

Separator is optional. If specified, it can be up to 120 bytes, composed of non-alphabetic characters. Symbol table values, such as <CR>, can be used to indicate non-printable characters.

The Separator is required if the second DateTime option is used and the format string of the first DateTime ends in a variable sized specification - EY, M, or D for Date or H24, H12, M, or S for Time.

Japanese date format strings

Sub-String Name

Sub-String Value

Japanese Date

Year + MonthSet(1)

Year

CCYY

YΥ

EEYY

EΥ

MonthSet

```
Separator(1) + "MM" + DayOfMonth(1)
```

"[" + Separator(1) + "MM" + DayOfMonth(1) +]

Separator(1) + M + DayOfMonth(1)

[+Separator(1) + M + DayOfMonth(1) +]

DayOfMonth

Separator(1) + "DD" + WeekDay(1)

```
"[" + Separator(1) + "DD" + WeekDay(1) + "]"
```

Separator(1) + "D" + WeekDay(1)

"[" + Separator(1) + "D" + WeekDay(1) + "]"

WeekDay

```
Separator(1) + "DY"
```

"[" + Separator(1) + "DY" + "]"

Separator(1) + "DAY"

"[" + Separator(1) + "DAY" + "]"

Separator

Separator is optional. If specified, it can be up to 120 bytes composed of non-alphabetic characters. Symbol table values, such as <CR>, can be used to indicate non-printable characters.

MonthSet Separator required if Year is EY

DayOfMonth Separator required if MonthSet is M

WeekDay Separator required if DayOfMonth is D

Japanese time format strings

Sub-String Name

Sub-String Value

Japanese Time

Meridian(1) + HMS

Meridian

"AM/PM"

HMS

"HH24" + MinuteSet(1)

```
"H24" + MinuteSet(1)
```

```
"HH12" + MinuteSet(1)
```

```
"H12" + MinuteSet(1)
```

MinuteSet

Separator(1) + "MM" + SecondSet(1)

```
"[" + Separator(1) + "MM" + SecondSet(1) + "]"
```

```
Separator(1) + "M" + SecondSet(1)
```

```
"[" + Separator(1) + "M" + SecondSet(1) + "]"
```

SecondSet

```
Separator(1) + "SS"
```

"[" + Separator(1) + "SS" + "]"

Separator(1) + "S"

"[" + Separator(1) + "S" + "]"

Separator

Separator is optional. If specified, it can be up to 120 bytes, composed of non-alphabetic characters. Symbol table values, such as <CR> can be used to indicate non-printable characters.

MinuteSet Separator required if HMS is H24 or H12

SecondSet Separator required if MinuteSet is M

Western date and time format strings

Substring Name

Substring Value

Western DateTime

```
"{" +DateTime + "}"
```

"{" +DateTime + "}" + Separator(1) + "{" + DateTime + "}"

"{" +DateTime + "}" + "[" + Separator(1) + "{" + DateTime + "}" + "]"

DateTime

Date

Time

Separator

Separator is optional. If specified, it can be up to 120 bytes, composed of non-alphabetic characters. Symbol table values, such as <CR>, can be used to indicate non-printable characters.

The Separator is required if the second DateTime option is used and the format string of the first DateTime ends in a variable sized specification - M, MONTH, D, or DAY for Date or H24, H12, M, or S for Time.

Western date format strings

Sub-String Name

Sub-String Value

Date

DateUnit + DatePart2(1)

DatePart2

```
Separator(1) + DateUnit + DatePart3(1)
```

"[" + Separator(1) + DateUnit + DatePart3(1) + "]"

DatePart3

Separator(1) + DateUnit + DatePart4(1)

"[" + Separator(1) + DateUnit + DatePart4(1) + "]"

DatePart4

Separator(1) + DateUnit

"[" + Separator(1) + DateUnit + "]"

Separator

Separator is optional. If specified, it can be up to 120 bytes, composed of non-alphabetic characters. Symbol table values, such as <CR>, can be used to indicate non-printable characters.

When DateUnit has a variable length (M, MONTH, D, DAY), a Separator must follow that DateUnit if data follows.

Western time format strings

Sub-String Name

Sub-String Value

Western Time

```
Hours + MinutesSet(1) + Meridian(1) + Zone(1)
```

Hours

HH24

H24

HH12

H12

MinutesSet

Separator(1) + "MM" + SecondSet(1)

"[" + Separator(1) + "MM" + SecondSet(1) + "]"

Separator(1) + "M" + SecondSet(1)

"[" + Separator(1) + "M" + SecondSet(1) + "]"

SecondSet

Separator(1) + "SS" + FractionSet(1)

"[" + Separator(1) + "SS" + FractionSet(1) + "]"

Separator(1) + "S" + FractionSet(1)

"[" + Separator(1) + "S" + FractionSet(1) + "]"

FractionSet

Separator(1) + MinPlaces + "-" + MaxPlaces

"[" + Separator(1) + MinPlaces + "-" + MaxPlaces + "]"

MinPlaces

An integer from 0 to 9

MaxPlaces

An integer from 0 to 9 (must be less than MinPlaces)

Meridian

"AM/PM"

"[AM/PM]"

Zone

"+/-ZZZZ"

"ZZZ"

"+/-ZZ:ZZ"

"+/-ZZ[:ZZ]"

"+/-ZZ[ZZ]"

"TZD"

"[+/-ZZZZ]"

"[ZZZ]"

"[+/-ZZ:ZZ]"

"[+/-ZZ[:ZZ]]"

"[+/-ZZ[ZZ]]"

"[TZD]"

Separator

Separator is optional. If specified, it can be up to 120 bytes, composed of non-alphabetic characters. Symbol table values, such as <CR>, can be used to indicate non-printable characters.

MinuteSet Separator required if Hours is H24 or H12

SecondSet Separator required if MinuteSet is M

FractionSet Separator required if SecondSet is S

Number format strings

You can create custom number formats by using the given format strings.

Decimal

```
"{" + Leading-Sign(1) + Whole# + Fraction + Trailing-Sign(1) + "}"
```

Integer

```
"{" + Leading-Sign(1) + Whole# + Trailing-Sign(1) + "}"
```

Leading sign format strings

Sub-String Name	Sub-String Value	Positive	Negative
Leading-Sign	"L" + Positive + Negative + Zero(1)	Req	Req
	-or-		
	"L" + "[" + Positive + "]" + Negative + Zero(1)	Opt	Req
	-or-		

Sub-String Name	Sub-String Value	Positive	Negative
	"L" + Positive + "[" + Negative + "]" + Zero(1)	Req	Opt
	-or-		
	"L" + Positive + Zero(1)	Req	-
	-or-		
	"L" + Negative + Zero(1)	-	Req

Trailing sign format strings

Sub-String Name	Sub-String Value	Positive	Negative
Trailing-Sign	"T" + Positive + Negative + Zero(1)	Req	Req
	"T" + "[" + Positive + "]" + Negative + Zero(1)	Opt	Req
	"T" + Positive + "[" + Negative + "]" + Zero(1)	Req	Opt
	"T" + Positive + Zero(1)	Req	-
	"T" + Negative + Zero(1)	-	Req

Substring format strings

Substring Name	Substring Value	Meaning
Positive	"+" + Value(1)	
Negative	"-" + Value(1)	
Value	A text-string enclosed in single quotation marks '. Value has a release character of / if the text contains any single quotation mark ' or forward slash / characters.	
Zero	"Z" + Value "[" + "Z" + Value + "]"	Specifies the required leading sign value if the num- ber is zero. If Zero is not used, there is no sign asso- ciated with a zero.
		Specifies the optional leading sign value if the num-

ber is zero. If Zero is not used, there is no sign asso-

ciated with a zero.

Whole number and fraction format strings

Whole# substring name

Substring value

Meaning

```
MinDigits(1) + "#" + Value(1) + "###" + MaxDigits(1)
```

```
MinDigits(1) + "#" + "[" + Value(1) + "]" + "###" + MaxDigits(1)
```

Specifies the thousands separator and the range of whole number digits. If min-digits is not used, the default is zero. If max-digits is not used, the default is "S". If a ThousandsItem is specified, a Value must be present as the default for the syntax item.

Fraction substring name

Substring value

Meaning

```
"V" + ImpliedPlaces
```

Specifies the decimal to be in an explicit place, and ImpliedPlaces determines where the intended decimal separator is to be placed.

```
Value + MinDigits(1) + "##" + MaxDigits(1)
```

Specifies the value of the decimal separator to be required and the range of fraction digits. If min-digits is not used, default is zero. If max-digits is not used, default is "S"

```
"[" + Value + MinDigits(1) + "##" + MaxDigits(1) + "]"
```

Specifies the value of the decimal separator to be optional if there is no fractional portion of the number. It also specifies the range of fraction digits. If min-digits is not used, default is zero. If max-digits is not used, default is "S"

RUN function return codes

The RUN function return codes and messages might result when using the RUN function. Return codes and messages are returned when the particular activity completes. Return codes and messages might also be recorded as specified in the audit logs, trace files, execution summary files, and so forth.

The following table lists the return codes and messages that can result when using the RUN function.

Return Code

Message

50

Memory allocation failure

Occurs when memory fails.

51

Card override failure

Occurs when memory fails.

52

I/O initialization failure

Occurs when memory fails.

53

Open audit failure

The audit log file is not accessible.

54

No command line

There is nothing to process.

55

Recursive command files

More than one command file is included in the command line.

56

Invalid command line option -x

The option is invalid for the command.

57

Invalid `W' command line option

The Work file option is invalid.

58

Invalid `B' command line option

The Batch (close) file option is invalid.

59

Invalid `R' command line option

The Refresh Rate option is invalid.

60

Invalid `A' command line option

The Audit option is invalid.

61

Invalid `P' command line option

The Paging option is invalid

62

Invalid `Y' command line option

The General I/O Retry option is invalid.

63

Invalid `T' command line option

The Trace option is invalid.

64

Invalid `G' command line option

The Ignore option is invalid

65

Invalid `I' command line option for input x

The Source option is invalid for the identified input.

66

Invalid size in echo command line for input x

The size specified using the Size option is greater than memory allowed.

67

Invalid adapter type in command line for input x

The adapter is not of a known adapter type. Includes -IMxxx where xxx is an unknown adapter alias.

68

Invalid `O' command line option for output x

The target option is invalid for output x. The number of characters between the single quotation marks that represent the options for an adapter exceed 258 characters in the adapter override.

69

Invalid adapter type in command line for output \boldsymbol{x}

The adapter is not of a known adapter type. Includes -OMxxx where xxx is an unknown adapter alias.

70

Command line memory failure

Occurs when memory is exceeded during echo or override card commands.

71

Invalid `D' command line option

The Date option is invalid.

72

Invalid `F' command line option

The Failure option is invalid.

73

Resource manager failure

(Launcher only) The resource manager is not used, possibly a memory failure.

74

Invalid `Z' command line option

The Ignore option is invalid.

75

Adapter failed to get data on input

Enable the adapter trace to record the adapter activity to discover the cause of the error.

76

Adapter failed to put data on output

Enable the adapter trace to record the adapter activity to discover the cause of the error.

77

Invalid map name

This message can occur in two different cases. First, this message occurs when the map name specified on the command line is more than 32 bytes long in UTF-8 encoding. Also, this message can occur when there is an error in the command line such that text for another execution command is erroneously being interpreted as the map name. For example, in the command line below, the number representing the size of the echoed data is missing.

mymap.mmc -IE1S HereIsMyDataButIForgotToSpecifyTheSize -AED

Because the size is missing, it is interpreted to be 0, such that there is no echoed data. The next string encountered on the command line

(HereIsMyData...)

Because it does not start with a hyphen (-), it is assumed to be the name of the next map to execute. Because the text is longer than 32 bytes in UTF-8 encoding, the *Invalid Map Name* message is returned.

Character set codes for CPACKAGE, CSERIESTOTEXT, and CTEXT

The second argument of the CPACKAGE, CSERIESTOTEXT, and CTEXT functions specifies the character set of the output of the function. The value of the second argument (the character set of the object content), must be a valid character set code.

All actions done that use the text string that results from one of these functions (CPACKAGE, CSERIESTOTEXT, or CTEXT) treat the text string as being of the specified character set–it is not automatically treated as Native.

Character set code	Data language
Native	Native
ASCII	ASCII (deprecated)
EBCDIC	EBCDIC (deprecated)
UNICODE_BE	UNICODE Big Endian (deprecated)
EUC	EUC (deprecated)
SJIS	SJIS (deprecated)
IBMKANJI	IBM Kanji (deprecated)
CIIKANJI	CII Kanji (deprecated)
JIS	JIS (deprecated)
UNICODE_LE	UNICODE Little Endian (deprecated)
UTF-8	UTF-8 (deprecated)
Latin1	Latin1 (deprecated)
UTF-8\ibm-1208	UTF-8
UTF-16	UTF-16
UTF-16BE	UTF-16 Big Endian
UTF-16LE	UTF-16 Little Endian
UTF-32	UTF-32
UTF-32BE	UTF-32 Big Endian
UTF-32LE	UTF-32 Little Endian
UTF16_PlatformEndian	UTF-16 Platform Endian
UTF16_OppositeEndian	UTF-16 Opposite Endian
UTF32_PlatformEndian	UTF-32 Platform Endian
UTF32_OppositeEndian	UTF-32 Opposite Endian
UTF-16BE,version=1	UTF-16BE,version=1

Character set code	Data language
UTF-16LE,version=1	UTF-16LE,version=1
UTF-16,version=1	UTF-16,version=1
UTF-16,version=2	UTF-16,version=2
UTF-7	UTF-7
IMAP-mailbox-name	IMAP-mailbox-name
SCSU	SCSU
BOCU-1	BOCU-1
CESU-8	CESU-8
ISO-8859-1	Latin1
US-ASCII	US-ASCII
gb18030	gb18030
ibm-912_P100-1995	Latin2
ibm-913_P100-2000	Latin3
ibm-914_P100-1995	CESU-8
ibm-915_P100-1995	Cyrillic
ibm-1089_P100-1995	Arabic
ibm-9005_X110-2007	Greek8
ibm-813_P100-1995	ibm-813
ibm-5012_P100-1999	Hebrew
ibm-916_P100-1995	ibm-916
ibm-920_P100-1995	Latin5
iso-8859_10-1998	Latin6
lso-8859_11-2001	Thai8
ibm-921_P100-1995	ibm-921
iso-8859_14-1998	Latin8
ibm-923_P100-1998	Latin-9
ibm-942_P12A-1999	shift_jis78
ibm-943_P15A-2003	MS_Kanji
ibm-943_P130-1999	Shift_JIS
ibm-33722_P12A-1999	EUC-JP

Character set code	Data language
ibm-33722_P120-1999	ibm-33722_P120-1999
ibm-954_P101-2000	ibm-954_P101-2000
ibm-1373_P100-2002	ibm-1373_P100-2002
windows-950-2000	Big5
ibm-950_P110-1999	ibm-950_P110-1999
ibm-1375_P100-2003	Big5-HKSCS (IBM)
ibm-5471_P100-2006	ibm-5471_P100-2006
ibm-1386_P100-2001	ibm-1386_P100-2001
windows-936-2000	GBK
ibm-1383_P110-1999	EUC-CN
ibm-5478_P100-1995	GB_2312-80
ibm-964_P110-1999	EUC-TW
ibm-949_P110-1999	ibm-949_P110-1999
ibm-949_P11A-1999	ibm-949_P11A-1999
ibm-970_P110-1995	ibm-eucKR
ibm-971_P100-1995	ibm-971_P100-1995
ibm-1363_P11B-1998	ibm-1363 (korean)
ibm-1363_P110-1997	ibm-1363_P110-1997
windows-949-2000	Windows 949 (korean)
windows-874-2000	Windows 874
ibm-874_P100-1995	ibm-874
ibm-1162_P100-1999	ibm-1162
ibm-437_P100-1995	ibm-437
ibm-720_P100-1997	ibm-720
ibm-737_P100-1997	ibm-737
ibm-775_P100-1996	ibm-775
ibm-850_P100-1995	ibm-850
ibm-851_P100-1995	ibm-851
ibm-852_P100-1995	ibm-852
ibm-855_P100-1995	ibm-855

Character set code

ibm-856_P100-1995	ibm-856
ibm-857_P100-1995	ibm-857
ibm-858_P100-1997	ibm-858
ibm-860_P100-1995	ibm-860
ibm-861_P100-1995	ibm-861
ibm-862_P100-1995	ibm-862
ibm-863_P100-1995	ibm-863
ibm-864_X110-1999	ibm-864
ibm-865_P100-1995	ibm-865
ibm-866_P100-1995	ibm-866
ibm-867_P100-1998	ibm-867
ibm-868_P100-1995	ibm-868
ibm-869_P100-1995	ibm-869
ibm-878_P100-1996	KOI8-R
ibm-901_P100-1999	ibm-901
ibm-902_P100-1999	ibm-902
ibm-922_P100-1999	ibm-922
ibm-1168_P100-2002	KOI8-U
ibm-4909_P100-1999	ibm-4909
ibm-5346_P100-1998	ibm-5346
ibm-5347_P100-1998	ibm-5347
ibm-5348_P100-1997	ibm-5348
ibm-5349_P100-1998	ibm-5349
ibm-5350_P100-1998	ibm-5350
ibm-9447_P100-2002	ibm-9447
ibm-9448_X100-2005	ibm-9448
ibm-9449_P100-2002	ibm-9449
ibm-5354_P100-1998	ibm-5354
ibm-1250_P100-1995	ibm-1250
ibm-1251_P100-1995	ibm-1251

Data language

Character set code	Data language
ibm-1252_P100-2000	ibm-1252
ibm-1253_P100-1995	ibm-1253
ibm-1254_P100-1995	ibm-1254
ibm-1255_P100-1995	ibm-1255
ibm-5351_P100-1998	ibm-5351
ibm-1256_P110-1997	ibm-1256
ibm-5352_P100-1998	ibm-5352
ibm-1257_P100-1995	ibm-1257
ibm-5353_P100-1998	ibm-5353
ibm-1258_P100-1997	ibm-1258
macos-0_2-10.2	macintosh
macos-6-10.2	x-mac-greek
macos-7_3-10.2	x-mac-cyrillic
macos-29-10.2	x-mac-ce
macos-35-10.2	x-mac-turkish
ibm-1051_P100-1995	hp-roman8
ibm-1276_P100-1995	ibm-1276 (Adobe Standard Encoding)
ibm-1006_P100-1995	ibm-1006
ibm-1098_P100-1995	ibm-1098
ibm-1124_P100-1996	ibm-1124
ibm-1125_P100-1997	ibm-1125
ibm-1129_P100-1997	ibm-1129
ibm-1131_P100-1997	ibm-1131
ibm-1133_P100-1997	ibm-1133
ISO_2022,locale=ja,version=0	ISO_2022,locale=ja,version=0
ISO_2022,locale=ja,version=1	ISO_2022,locale=ja,version=1 (JIS)
ISO_2022,locale=ja,version=2	ISO_2022,locale=ja,version=2
ISO_2022,locale=ja,version=3	ISO_2022,locale=ja,version=3 (JIS7)
ISO_2022,locale=ja,version=4	ISO_2022,locale=ja,version=4 (JIS8)
ISO_2022,locale=ko,version=0	ISO_2022,locale=ko,version=0

Character set code	Data language
ISO_2022,locale=ko,version=1	ISO_2022,locale=ko,version=1
ISO_2022,locale=zh,version=0	ISO_2022,locale=zh,version=0
ISO_2022,locale=zh,version=1	ISO_2022,locale=zh,version=1
ISO_2022,locale=zh,version=2	ISO_2022,locale=zh,version=2
HZ	HZ-GB-2312
x11-compound-text	x11-compound-text
ISCII,version=0	x-iscii-de
ISCII,version=1	x-iscii-be
ISCII,version=2	x-iscii-pa
ISCII,version=3	x-iscii-gu
ISCII,version=4	x-iscii-or
ISCII,version=5	x-iscii-ta
ISCII,version=6	x-iscii-te
ISCII,version=7	x-iscii-ka
ISCII,version=8	x-iscii-ma
LMBCS-1	LMBCS-1
ibm-37_P100-1995	ibm-037 (ebcdic-cp-us/ca/wt/nl)
ibm-273_P100-1995	ebcdic-de
ibm-277_P100-1995	EBCDIC-CP-DK/NO
ibm-278_P100-1995	ebcdic-cp-fi/se/sv
ibm-280_P100-1995	ebcdic-cp-it
ibm-284_P100-1995	ebcdic-cp-es
ibm-285_P100-1995	ebcdic-cp-gb
ibm-290_P100-1995	EBCDIC-JP-kana
ibm-297_P100-1995	ebcdic-cp-fr
ibm-420_X120-1999	ebcdic-cp-ar1
ibm-424_P100-1995	ebcdic-cp-he
ibm-500_P100-1995	ebcdic-cp-be/ch
ibm-803_P100-1999	ibm-803
ibm-838_P100-1995	IBM-Thai

Character set code	Data language
ibm-870_P100-1995	ebcdic-cp-roece/yu
ibm-871_P100-1995	ebcdic-is
ibm-875_P100-1995	ibm-875
ibm-918_P100-1995	ebcdic-cp-ar2
ibm-930_P120-1999	ibm-930
ibm-933_P110-1995	ibm-933
ibm-935_P110-1999	ibm-935
ibm-937_P110-1999	ibm-937
ibm-939_P120-1999	ibm-939
ibm-1025_P100-1995	ibm-1025
ibm-1026_P100-1995	ibm-1026
ibm-1047_P100-1995	ibm-1047
ibm-1097_P100-1995	ibm-1097
ibm-1112_P100-1995	ibm-1112
ibm-1122_P100-1999	ibm-1122
ibm-1123_P100-1995	ibm-1123
ibm-1130_P100-1997	ibm-1130
ibm-1132_P100-1998	ibm-1132
ibm-1137_P100-1999	ibm-1137
ibm-4517_P100-2005	ibm-4517
ibm-1140_P100-1997	ibm-1140 (ebcdic-us-37+euro)
ibm-1141_P100-1997	ibm-1141 (ebcdic-de-273+euro)
ibm-1142_P100-1997	ibm-1142 (ebcdic-dk/no-277+euro)
ibm-1143_P100-1997	ibm-1143 (ebcdic-fi/se-278+euro)
ibm-1144_P100-1997	ibm-1144 (ebcdic-it-280+euro)
ibm-1145_P100-1997	ibm-1145 (ebcdic-es-284+euro)
ibm-1146_P100-1997	ibm-1146 (ebcdic-gb-285+euro)
ibm-1147_P100-1997	ibm-1147 (ebcdic-fr-297+euro)
ibm-1148_P100-1997	ibm-1148 (ebcdic-international+euro)
ibm-1149_P100-1997	ibm-1149 (ebcdic-is-871+euro)

Character set code

ibm-1153_P100-1999	ibm-1153
ibm-1154_P100-1999	ibm-1154
ibm-1155_P100-1999	ibm-1155
ibm-1156_P100-1999	ibm-1156
ibm-1157_P100-1999	ibm-1157
ibm-1158_P100-1999	ibm-1158
ibm-1160_P100-1999	ibm-1160
ibm-1164_P100-1999	ibm-1164
ibm-1364_P110-1997	ibm-1364
ibm-1371_P100-1999	ibm-1371
ibm-1388_P103-2001	ibm-1388
ibm-1390_P110-2003	ibm-1390
ibm-1399_P110-2003	ibm-1399
ibm-5123_P100-1999	ibm-5123
ibm-8482_P100-1999	ibm-8482
ibm-16684_P110-2003	ibm-16684
ibm-4899_P100-1998	ibm-4899
ibm-4971_P100-1999	ibm-4971
ibm-9067_X100-2005	ibm-9067
ibm-12712_P100-1998	ebcdic-he
ibm-16804_X110-1999	ebcdic-ar
ibm-37_P100-1995,swaplfnl	ibm-37-s390
ibm-1047_P100-1995,swaplfnl	ibm-1047-s390
ibm-1140_P100-1997,swaplfnl	ibm-1140-s390
ibm-1141_P100-1997,swaplfnl	ibm-1141-s390
ibm-1142_P100-1997,swaplfnl	ibm-1142-s390
ibm-1143_P100-1997,swaplfnl	ibm-1143-s390
ibm-1144_P100-1997,swaplfnl	ibm-1144-s390
ibm-1145_P100-1997,swaplfnl	ibm-1145-s390
ibm-1146_P100-1997,swaplfnl	ibm-1146-s390

Data language

Character set code Data language ibm-1147_P100-1997,swaplfnl ibm-1147-s390 ibm-1148_P100-1997,swaplfnl ibm-1148-s390 ibm-1149_P100-1997,swaplfnl ibm-1149-s390 ibm-1153_P100-1999,swaplfnl ibm-1153-s390 ibm-12712_P100-1998,swaplfnl ibm-12712-s390 ibm-16804_X110-1999,swaplfnl ibm-16804-s390 ebcdic-xml-us ebcdic-xml-us

Chapter 9. Troubleshooting

This guide describes how to analyze and resolve some of the common problems that you might encounter while you work with HCL OneTest[™] Server.

Known issues are documented in the Release document and the link is in the Release Notes under the Known issues section. See Known issues on page 11.

You can contact HCL Support if you are unable to troubleshoot the problem. Gather all the required background information and provide the details to HCL Support for investigation. For more information, see HCL Customer Support.

Troubleshooting issues

You can find information about the issues or problems that you might encounter while working with HCL OneTest[™] Server. Details about issues, their causes and the resolutions that you can apply to fix the issues are described.

The troubleshooting issues are presented to you in the following tables based on where or when you might encounter these issues on HCL OneTest[™] Server.

- Table 23: Troubleshooting issues: installation on page 1136
- Table 24: Troubleshooting issues: server administration on page 1139
- Table 25: Troubleshooting issues: resource monitoring on page 1139
- Table 26: Troubleshooting issues: configuring test runs on page 1139
- Table 27: Troubleshooting issues: test or stub runs on page 1141
- Table 29: Troubleshooting issues: test results and reports on page 1145

Problem	Cause	Solution
On Ubuntu, when you are installing the server software and you en- counter errors in the scripts that are running.	At times, scripts might not appear to be running due to any of the follow- ing reasons: • Slow connection speeds. • Insufficient CPU, memory, or disk resources. • A firewall that was configured incorrectly is already enabled.	You can complete any of the follow- ing tasks: • To identify the issue, you can perform a diagnostic check by running the following com- mand: journalctl -u k3s This command displays the log that you can use to check for the problem.

Table 23. Troubleshooting issues: installation

Problem	Cause	Solution
		 Run the following command to see which pods are run- ning and which pods are not running: kubectl get pods -A Run the following command to get details about a specific pod:
On Ubuntu, DNS is not working as expected.		The DNS configuration that is used by the cluster can be displayed by us- ing the following command: kubectl get cm -n kube-system coredns -ojsonpath="{.data.Corefil e}" The forward setting displays the nameservers that are used. For ex- ample, you might see the following in the corefile: .:53 { : forward . 8.8.8.8 9.9.9.9 : }

Table 23. Troubleshooting issues: installation (continued)

Problem	Cause	Solution
		A script (ubuntu-set-dns.sh) is supplied for managing these values. For example, to set the DNS values for the values shown in the previous example:
		<pre>sudo ./ubuntu-set-dns.sh server 8.8.8.8server 9.9.9.9</pre>
		Note: If you do not use sudo in the command, the script runs but the configuration might be lost if the cluster is restarted.
		To learn more about the behavior of the script, run the following com- mand:
		sudo ./ubuntu-set-dns.sh help
When running helm install the creat- ed pods keep crashing, and the logs	In some instances, the RabbitMQ password is not automatically setup	Manually apply the necessary pass- word:
contain: ACCESS_REFUSED when try- ing to connect to RabbitMQ	correctly.	<pre>kubectl exec -n <namespace> <release-name>-rabbitmq-0 rabbitmqctl change_password user \ "\$(kubectl get secret -n <namespace> <release-name>-rabbitmq -o jsonpath='{.data.rabbitmq-p assword}' base64 decode)"</release-name></namespace></release-name></namespace></pre>

Table 23. Troubleshooting issues: installation (continued)

Table 24. Troubleshooting issues: server administration

Problem	Cause	Solution
When a user is assigned an addition- al role, the change in the permissions is not observed in the browser.		You must log out of the session and log in again for the changed role to take effect.
You see the following message dis- played on HCL OneTest™ Server: You can't request to join a project that has no owners	You requested to join an project that no longer has an owner. Orphaned projects occur when the project own- ers are deleted. This can occur, for example, when the person leaves the organization.	Ask an administrator to take owner- ship of the project, and then add you as a member.

Table 25. Troubleshooting issues: resource monitoring

Problem	Cause	Solution
You are not able to add a Prometheus server as a Resource Monitoring source.	The cause might be that you have not installed the Prometheus server at the time of server installation.	Verify that the Prometheus server was installed in Helm at the time of server installation. See Installing the server software on Ubuntu by us- ing k3s on page 42. If not, consult your cluster administrator to get the Prometheus server installed and con- figured.

Table 26. Troubleshooting issues: configuring test runs

Problem	Cause	Solution
When you configure a run of a sched- ule that matches the following condi-	-	To resolve the problem, select from either of the following methods:
tions:		

Problem	Cause	Solution
 The schedule has two user groups configured to run on static agents when the schedule was created in HCL OneTest[™] Performance 10.1. One of the user groups is disabled and the asset is committed to the remote repository. Both the static agents are displayed as available for the test run in the Location tab of the Execute test asset dialog when only one agent that is configured for the user group must be available. 	 The schedule was created in HCL OneTest[™] Performance 10.1. The user group that is disabled is not removed or deleted from the test resources. The agent configured on the disabled user group is already added as an agent to the server project and is available for selection. 	 By using HCL OneTest™ Performance 10.1.1. Perform the following steps: Open the schedule in HCL OneTest™ Performance 10.1.1. Save the schedule and the project. Commit your test asset to the remote repository. Proceed to configure a run for the schedule on HCL OneTest™ Server 10.1.1. By using HCL OneTest™ Performance 10.1. By using HCL OneTest™ Performance 10.1. Click Remove. Save the schedule and the project. Commit your test asset to the remote repository. Server 10.1.1.
You have added a remote repository to your project that contains the test assets or resources of the following types:	This problem occurs if the server ex- tension is not enabled. Although the extension was enabled at the time of installation of HCL OneTest [™] Server,	You must verify if the server exten- sion is enabled and running by run- ning the following command:kubectl get pod -n <test-system>, where <test-system> is the namespace that</test-system></test-system>

Table 26. Troubleshooting issues: configuring test runs (continued)

Problem	Cause	Solution
• Postman • JMeter • JUnit	it was disabled subsequently by the server administrator.	you created to install the server soft- ware. The server extensions that are running are displayed.
The test assets or resources are not displayed on the Execution page for you to select the asset for a run.		If the server extension that you want is not running implying that the serv- er extension is not enabled. You must enable the server extension. Contact the server administrator to enable the server extension.

Problem	Cause	Solution
 You encounter any of the following issues: When many tests are run simultaneously on the default cluster location and you observe the following issues: Out of memory errors. Observe that the test runs are slow with a high CPU usage. The Kubernetes pods are getting evicted. When you run an AFT suite that contains multiple Web UI tests and you observe the following issues: Error stating that the browser might not be installed or the browser 	 The issue is seen when any of the following events occur: Many tests are run in parallel. The memory that is used by the tests during the test run exceeds the allocated default memory of 1 GB. The default memory of the container is not adequate for the test run. Pods are evicted due to low node memory. 	To resolve the problem, you can increase the resource allocation for test runs by using the arguments listed in Table Table 28: Increasing resource allocation on page 1143. You can enter arguments in the Additional configuration options field in the Advanced settings panel of the Execute test asset dialog when configuring a test run. Important: The memory settings that you configure for a test run is persisted for the test when ever you run it. You must use this setting judiciously. Configuring all tests for an increased memory limit might affect subsequent test runs or cause other

Table 27. Troubleshooting issues: test or stub ru	ns
---	----

Problem	Cause	Solution
er version is unsup-		er memory issues when tests
ported.		run simultaneously.
 Error stating multiple 		
random time-outs or		In addition, in the JVM Arguments
an internal error.		field under the Advanced settings
 When you run VU schedules 		you can set the maximum heap size
that contain multiple Web UI		for the test run time. For example,
test or large number of virtu-		adding the JVM argument -Xmx3g
al users or a combination of		sets the maximum heap size to 3Gi.
Web UI, performance, and API		
tests, and you observe the fol-		
lowing issue:		
 The test run hangs 		
and the inadequacy		
of memory can be in-		
ferred as the cause in		
the logs.		
You are not able to run the Istio stubs from the Execution page.	The cause might be that the fully qualified domain name is not spec- ified in the Host field for the stub when it was created.	Verify and ensure to add the fully qualified domain name of the serv- er in the Host field when the physica transport for the stub is configured in HCL OneTest [™] API.
You are not able to run Web UI tests	Browser launch is prevented when	To resolve this issue, you must per-
on a remote agent that runs on Linux	the remote agent runs as <i>root</i> or <i>su</i> -	form the following steps after you
because the browser fails to launch.	do.	have installed the remote agent:
		 Stop the agent. Start the agent as the logged in user by performing the fol- lowing steps: Open a terminal on Linux. Enter the following commands: /opt/HCL/ HCLOneTest/Major- domo/

Table 27. Troubleshooting issues: test or stub runs (continued)

Table 27. Troubleshooting issues: test or stub runs (continued)

Problem	Cause	Solution
		sudo ./MDStop.sh
		./MDStart.sh

Note: You can refer to the Kubernetes documentation for information about the different units that can be used for resources in the **Additional configuration option** fields.

Table 28. Increasing resource allocation

Requirement	Configuration option name	Default value, if no value is set	An example value	Result of using the example value
Specifying the memo- ry limit of the <i>init con-</i> <i>tainer</i> .	init.resource.memo- ry.limit	1024Mi	2048Mi	Increases the memo- ry limit of the <i>init con-</i> <i>tainer</i> from the de- fault value to 2048Mi.
Configuring a larger memory request for the <i>init container</i> to avoid pod eviction.	init.resource.memo- ry.request	64Mi	1024Mi	Increases the ini- tial memory request for the <i>init container</i> from the default val- ue to 1024Mi.
Specifying the cpu re- quest for the <i>init con-</i> <i>tainer</i> .	init.resource.cpu- .request	50m	60m	Increases the cpu re- quest for the <i>init con-</i> <i>tainer</i> from the de- fault value 60m.
Specifying the memo- ry limit of the contain- er used for the test run.	resource.memory.lim- it	The larger of 3Gi or maximum heap size + 1Gi	4Gi	Changes the memory limit of the main con- tainer from the de- fault value to 4Gi.

Table 28. Increasing resource allocation

(continued)

Requirement	Configuration option	Default value, if no	An example value	Result of using the
	name	value is set		example value
Note: If the				
memory lim-				
it you set is				
more than the				
default limit,				
you must run				
the following				
command to				
increase the				
allotted lim-				
it to 8 GB or				
any other val-				
ue above the				
default val-				
ue of 3 GB, at				
the time of in-				
stalling the				
server or any-				
time later:				
set execution .template. resources. limits.mem ory=8Gi				
You must be				
a server ad-				
ministrator to				
run this com-				
mand.				
Specifying the mem-	resource.memory.re-	1024Mi	2048Mi	Increases the mem-
ory request for the	quest			ory request for the
container used by the	Arcor			main container from
test run.				

Table 28. Increasing resource allocation

(continued)

Requirement	Configuration option name	Default value, if no value is set	An example value	Result of using the example value
				the default value to 2048Mi.
Specifying the cpu request for the main container used by the test run.	resource.cpu.request	50m	70m	Increases the cpu re- quest for the main container from the default value to 70m.

Table 29.	Troubleshooting	issues: test	results and	d reports
-----------	-----------------	--------------	-------------	-----------

Troubleshooting issues: Data fabrication

You can find information about the issues or problems that you might encounter while working with the data fabrication feature in HCL OneTest[™] Server. Details about issues, their causes and the resolutions that you can apply to fix the issues are described.

Schema designing error or warning messages

The HCL® OneTest[™] Data analyzer validates the logical and structural consistency of the data definition of a schema. In case of any inconsistency in the schema structure, the analyzer issues error or warning messages based on the type of the analysis.

- Logical analysis addresses the integrity of the relationships that you define in the schema.
- Structural analysis addresses the integrity of the underlying database.

Warnings indicate a successful analysis and are relatively insignificant. Warning messages provide information about inconsistencies that occurred, when you changed the schema, and are automatically resolved.

Error messages are important. Error messages provide information about errors in the type definitions that you must correct. An error might result in unpredictable results in the mapping of the data definitions.

Return codes and error messages

You can find information about both error messages and warnings based on structural analysis or logical analysis.

Schema analysis logic error messages

The following table lists the logic error messages that result from a logical analysis of a schema:

Return Code

Message

L100

COMPONENT neither inherited nor local: `type name' of TYPE: `type name'

Hint: Look at the super-type's component list. The component is a valid type, but the supertype has a component list that restricts you from using this type as a component. You may have added subtype components before adding supertype components. Either remove all supertype components or add the components in error to the component list of the supertype.

L101

This GROUP must have at least one component - TYPE: 'type name'

Hint: If you want to map this group, add components. If you do not want to map it, make it a category.

L102

Circular reference found in COMPONENT # (`type name') - TYPE: `type name'

Hint: Look at the type of the component in error. It is probably missing an initiator or terminator.

L103

Circular reference found in Floating Component type - TYPE: 'type name'

Hint: Look at the floating component type in error. It is probably missing an initiator or terminator.

L104

DELIMITER for TYPE - `type name' must have a value

Hint: All delimited groups need a delimiter. Edit delimited group properties to insert the missing delimiter.

L105

DELIMITER type neither inherited nor local - TYPE: 'type name'

Hint: The delimiter name has been entered incorrectly. It should be the name of a local type, or the name of an inherited delimiter, or the name of a type in the sub-tree of the inherited delimiter.

L106

Default DELIMITER not specified - TYPE: `type name'

Hint: This Type was specified with a FIND option for its delimiter. Please add a default value to define what to use for building outputs.

L107

Default DELIMITER not in restriction list - TYPE: 'type name'

Hint: This delimiter was specified as a syntax item. Add the default value to the restriction list for that syntax item.

L108

DELIMITER type is not a SYNTAX ITEM - TYPE: 'type name'

Hint: Delimiters specified as an item must be specified to be interpreted as SYNTAX to set the value of the delimiter if it appears as a component in a data stream.

L109

DELIMITER type has no restriction list - TYPE: 'type name'

Hint: All syntax items need a restriction list.

L110

RELEASE CHARACTER neither inherited nor local - TYPE: 'type name'

Hint: The release character name has been entered incorrectly. It should be either the name of a local type, the name of an inherited release character, or the name of a type in the sub-tree of the inherited release character.

Default RELEASE CHARACTER not specified - TYPE: 'type name'

Hint: This Type was specified with a syntax item for its release character. Please add a default value to define a value for the release character that has not been encountered in the data.

L112

Default RELEASE CHARACTER not in restriction list - TYPE: `type name'

Hint: This Type was specified with a syntax item for its release character. Please add the default value to the restriction list of that syntax item.

L113

RELEASE CHARACTER type is not a SYNTAX ITEM - TYPE: 'type name'

Hint: Release characters specified as an item must be specified to be interpreted as SYNTAX to set the value of the release character if it appears as a component in a data stream.

L114

RELEASE CHARACTER type has no restriction list - TYPE: 'type name'

Hint: All syntax items need a restriction list.

L115

Floating Component TYPE neither inherited nor local - TYPE: `type name'

Hint: The floating component name has been entered incorrectly. It should be either the name of a local type, the name of an inherited floating component, or the name of a type in the sub-tree of the inherited floating component.

L116

INITIATOR type neither inherited nor local - TYPE: `type name'

Hint: The initiator name has been entered incorrectly. It should be either the name of a local type, the name of an inherited initiator, or the name of a type in the sub-tree of the inherited initiator.

L117

Default INITIATOR not specified - TYPE: `type name'

Hint: This Type was specified with a syntax item for its initiator. Add a default value to define a value for that initiator has not been encountered in the data.

L118

Default INITIATOR not in restriction list - TYPE: 'type name'

Hint: This Type was specified with a syntax item for its initiator. Add the default value to the restriction list of that syntax item.

INITIATOR type is not a SYNTAX ITEM - TYPE: `type name'

Hint: Initiators specified as an item must be specified to be interpreted as SYNTAX to set the value of the initiator if it appears as a component in a data stream.

L120

INITIATOR type has no restriction list - TYPE: 'type name'

Hint: All syntax items need a restriction list.

L121

TERMINATOR type neither inherited nor local - TYPE: `type name'

Hint: The terminator name has been entered incorrectly. It should be either the name of a local type, the name of an inherited terminator, or the name of a type in the sub-tree of the inherited terminator.

L122

Default TERMINATOR not specified - TYPE: 'type name'

Hint: This Type was specified with a syntax item for its terminator. Add a default value to define a value for that terminator has not been encountered in the data.

L123

Default TERMINATOR not in restriction list - TYPE: 'type name'

Hint: This Type was specified with a syntax item for its terminator. Please add the default value to the restriction list of that syntax item.

L124

TERMINATOR type is not a SYNTAX ITEM - TYPE: `type name'

Hint: Terminators specified as an item must be specified to be interpreted as SYNTAX to set the value of the terminator if it appears as a component in a data stream.

L125

TERMINATOR type has no restriction list - TYPE: 'type name'

Hint: All syntax items need a restriction list.

L126

COMPONENT range minimum (#) greater than range maximum (#) - COMPONENT `type name' - TYPE: `type name'

Hint: The minimum range must be less than or equal to the maximum range.

COMPONENT range minimum (#) less than inherited range minimum(#) - COMPONENT `type name' - TYPE: `type name'

Hint: The component in error has been inherited. Look at the range of the component with the same name in the super-type's component list.

L128

COMPONENT range maximum (#) greater than inherited range maximum(#) - COMPONENT `type name' - TYPE: `type name'

Hint: The component in error has been inherited. Look at the range of the component with the same name in the super-type's component list.

L129

COMPONENT RULE references a COMPONENT later in the component list - `type name' - TYPE: `type name'

Hint: Move the component rule to the component later in the list.

L130

COMPONENT RULE references undefined type - COMPONENT # of TYPE: 'type name'

Hint: Verify the spelling of the data object name. The rule should reference a data object name of the component or a data object name of a component earlier in the component list.

L131

COMPONENT RULE references components of a partitioned group - COMPONENT # of TYPE type name

L132

Invalid partitioning: TYPE has no SUBTYPES - TYPE: 'type name'

Hint: Remove the partitioned option from the class window or add sub-types to the Type in error.

L133

Type of COMPONENT exists, but its relative name is not valid: `type name' in TYPE: `type name'

Hint: To get the correct relative name, drag the type you want to use as a component and drop it in the component list of the Type. (Remember to delete the invalid component!)

L134

Reference to `ANY' not allowed: COMPONENT number # of TYPE: `type name'

Hint: In this case, the Type in error is a group and it is not the root of a partitioned tree. ANY cannot be used if that component needs to be validated. So, if that group is partitioned, you cannot use ANY for a component up to and including the identifier (if there is one). If that group is not partitioned, you cannot use ANY at all.

COMPONENT number # cannot reference a CATEGORY in TYPE: `*type name*' (because group is not partitioned)

Hint: In this case, the Type in error is a group and it's not the root of a partitioned tree. A category cannot be used if the component must be validated. So, if that group is partitioned, you cannot use a category for a component up to and including the identifier (if there is one). If that group is not partitioned, you cannot use a category as a component at all.

L136

COMPONENT `type name' occurs more than once in list - TYPE: `type name'

Hint: Each component in the same component list must have a unique type name. Try to make subtypes of the type name in error and replace each non-unique component with one of the new sub-types.

L137

COMPONENT `type name' and its super-type cannot be in same COMPONENT LIST (in TYPE: `type name')

Hint: Try making another sub-type of the super-type and replace the super-type reference with the new sub-type.

L138

COMPONENT 'type name' is same type as delimiter - TYPE: 'type name'

Hint: A component and a delimiter cannot have the same name. You may need to add sub-types to the type name used in error to resolve this one.

L139

COMPONENT `type name' is sub-type of delimiter - TYPE: `type name'

Hint: This occurs when a syntax item is used to specify a delimiter. You can add another sub-type to the syntax item and replace the delimiter name with the new sub-type name.

L140

COMPONENT `type name' is super-type of delimiter - TYPE: `type name'

Hint: This occurs when a syntax item is used to specify a delimiter. You can add another sub-type to the syntax item and replace the component name with the new sub-type name.

L141

COMPONENT `type name' is same type as initiator - TYPE: `type name'

Hint: A component and an initiator cannot have the same name. You can add sub-types to the type name used in error and replace both the component name and the initiator name.

COMPONENT `type name' is sub-type of initiator - TYPE: `type name'

Hint: This occurs when a syntax item is used to specify an initiator. You can add another sub-type to the syntax item and replace the initiator name with the new sub-type name.

L143

COMPONENT `type name' is super-type of initiator - TYPE: `type name'

Hint: This occurs when a syntax item is used to specify an initiator. You can add another sub-type to the syntax item and replace the component name with the new sub-type name.

L144

COMPONENT 'type name' is same type as terminator - TYPE: 'type name'

Hint: A component and a terminator cannot have the same name. Try adding sub-types to the type name used in error and replace both the component name and terminator name with one of the new sub-types.

L145

COMPONENT `type name' is sub-type of terminator - TYPE: `type name'

Hint: This occurs when a syntax item is used to specify a terminator. You can add another sub-type to the syntax item and replace the terminator name with the new sub-type name.

L146

COMPONENT `type name' is super-type of terminator - TYPE: `type name'

Hint: This occurs when a syntax item is used to specify a terminator. You can add another sub-type to the syntax item and replace the component name with the new sub-type name.

L147

COMPONENT `type name' is same type as Floating Component - TYPE: `type name'

Hint: Make both the floating component name and the component name sub-types of the floating component.

L148

COMPONENT `type name' is sub-type of Floating Component - TYPE: `type name'

Hint: Make both the floating component name and the component name sub-types of the floating component.

L149

COMPONENT `type name' is super-type of Floating Component - TYPE: `type name'

Hint: Make both the floating component name and the component name sub-types of the floating component.

L150

COMPONENT `type name' is same type as release character - TYPE: `type name'

Hint: This occurs when a syntax item is used to specify a release character. You can add sub-types to the syntax item and replace both the component name and the release character name with the new sub-type names.

L151

COMPONENT `type name' is sub-type of release character - TYPE: `type name'

Hint: This occurs when a syntax item is used to specify a release character. You can add another subtype to the syntax item and replace the release character name with the new sub-type name.

L152

COMPONENT `type name' is super-type of release character - TYPE: `type name'

Hint: This occurs when a syntax item is used to specify a release character. You can add sub-types to the syntax item and replace the component name with the new sub-type name.

L153

DELIMITER 'type name' is same type as initiator - TYPE: 'type name'

Hint: A delimiter and an initiator cannot have the same name. You may need to add sub-types to the type name used in error and replace both the delimiter and initiator names to refer to the new sub-types.

L154

DELIMITER `type name' is sub-type of initiator - TYPE: `type name'

Hint: This occurs when a syntax item is used to specify both an initiator and a delimiter. You can add another sub-type to the syntax item and replace the initiator name with the new sub-type name.

L155

DELIMITER `type name' is super-type of initiator - TYPE: `type name'

Hint: This occurs when a syntax item is used to specify both an initiator and a delimiter. You can add another sub-type to the syntax item and replace the delimiter name with the new sub-type name.

L156

DELIMITER `type name' is same type as terminator - TYPE: `type name'

Hint: A delimiter and a terminator cannot have the same name. You may need to add sub-types to the type name used in error and replace both the delimiter and terminator names to refer to the new sub-types.

DELIMITER `type name' is sub-type of terminator - TYPE: `type name'

Hint: This occurs when a syntax item is used to specify both a delimiter and a terminator. You can add another sub-type to the syntax item and replace the terminator name with the new sub-type name.

L158

DELIMITER `type name' is super-type of terminator - TYPE: `type name'

Hint: This occurs when a syntax item is used to specify both a delimiter and a terminator. You can add another sub-type to the syntax item and replace the delimiter name with the new sub-type name.

L159

DELIMITER `type name' is same type as release character - TYPE: `type name'

Hint: A delimiter and a release character cannot have the same name. You may need to add sub-types to the type name used in error and replace both the delimiter and release character names to refer to the new sub-types.

L160

DELIMITER `type name' is sub-type of release character - TYPE: `type name'

Hint: This occurs when a syntax item is used to specify both a delimiter and a release character. You can add another sub-type to the syntax item and replace the release character name with the new sub-type name.

L161

DELIMITER `type name' is super-type of release character - TYPE: `type name'

Hint: This occurs when a syntax item is used to specify both a delimiter and a release character. You can add another sub-type to the syntax item and replace the delimiter name with the new sub-type name.

L162

DELIMITER `type name' is same type as Floating Component - TYPE: `type name'

Hint: A delimiter and a floating component cannot have the same name. Try adding sub-types to the type name used in error and replace both the delimiter and floating component names to refer to the new sub-types.

L163

DELIMITER `type name' is sub-type of Floating Component - TYPE: `type name'

Hint: This occurs when a syntax item is used to specify both a delimiter and a floating component. You can add another sub-type to the syntax item and replace the floating component name with the new sub-type name.

DELIMITER `type name' is super-type of Floating Component - TYPE: `type name'

Hint: This occurs when a syntax item is used to specify both a delimiter and a floating component. You can add another sub-type to the syntax item and replace the delimiter name with the new sub-type name.

L165

INITIATOR `type name' is same type as terminator - TYPE: `type name'

Hint: An initiator and a terminator cannot have the same name. You may need to add sub-types to the type name used in error and replace both the initiator and terminator names to refer to the new sub-types.

L166

INITIATOR `type name' is sub-type of terminator - TYPE: `type name'

Hint: This occurs when a syntax item is used to specify both an initiator and a terminator. You can add another sub-type to the syntax item and replace the terminator name with the new sub-type name.

L167

INITIATOR `type name' is super-type of terminator - TYPE: `type name'

Hint: This occurs when a syntax item is used to specify both an initiator and a terminator. You can add another sub-type to the syntax item and replace the initiator name with the new sub-type name.

L168

INITIATOR `type name' is same type as release character - TYPE: `type name'

Hint: This occurs when a syntax item is used to specify both an initiator and a release character. You can add sub-types to the syntax item and replace both the initiator name and the release character name with a new sub-type name.

L169

INITIATOR `type name' is sub-type of release character - TYPE: `type name'

Hint: This occurs when a syntax item is used to specify both an initiator and a release character. You can add another sub-type to the syntax item and replace the release character name with the new sub-type name.

L170

INITIATOR `type name' is super-type of release character - TYPE: `type name'

Hint: This occurs when a syntax item is used to specify both an initiator and a release character. You can add another sub-type to the syntax item and replace the initiator name with the new sub-type name.

INITIATOR 'type name' is same type as Floating Component - TYPE: 'type name'

Hint: An initiator and a floating component cannot have the same name. Try adding sub-types to the type name used in error and replace both the initiator and floating component names with the new sub-types.

L172

INITIATOR 'type name' is sub-type of Floating Component - TYPE: 'type name'

Hint: This occurs when a syntax item is used to specify both an initiator and a floating component. You can add another sub-type to the syntax item and replace the floating component name with the new sub-type name.

L173

INITIATOR 'type name' is super-type of Floating Component - TYPE: 'type name'

Hint: This occurs when a syntax item is used to specify both an initiator and a floating component. You can add another sub-type to the syntax item and replace the initiator name with the new sub-type name.

L174

TERMINATOR `type name' is same type as release character - TYPE: `type name'

Hint: A terminator and a release character cannot have the same name. You may need to add sub-types to the type name used in error and replace both the terminator and release character names with the new sub-types.

L175

TERMINATOR `type name' is sub-type of release character - TYPE: `type name'

Hint: This occurs when a syntax item is used to specify both a terminator and a release character. You can add another sub-type to the syntax item and replace the release character name with the new sub-type name.

L176

TERMINATOR `type name' is super-type of release character - TYPE: `type name'

Hint: This occurs when a syntax item is used to specify both a terminator and a release character. You can add another sub-type to the syntax item and replace the terminator name with the new sub-type name.

L177

TERMINATOR `type name' is same type as Floating Component - TYPE: `type name'

Hint: A terminator and a floating component cannot have the same name. You may need to add subtypes to the type name used in error and replace both the terminator and floating component names with the new sub-types.

TERMINATOR `type name' is sub-type of Floating Component - TYPE: `type name'

Hint: This occurs when a syntax item is used to specify both a terminator and a floating component. You can add another sub-type to the syntax item and replace the floating component name with the new sub-type name.

L179

TERMINATOR `type name' is super-type of Floating Component - TYPE: `type name'

Hint: This occurs when a syntax item is used to specify both a terminator and a floating component. You can add another sub-type to the syntax item and replace the terminator name with the new sub-type name.

L180

RELEASE CHARACTER `type name' is same type as Floating Component - TYPE: `type name'

Hint: A release character and a floating component cannot have the same name. You may need to add sub-types to the type name used in error and replace both the release character and floating component names to refer to the new sub-types.

L181

RELEASE CHARACTER `type name' is sub-type of Floating Component - TYPE: `type name'

Hint: This occurs when a syntax item is used to specify both a release character and a floating component. You can add another sub-type to the syntax item and replace the floating component name with the new sub-type name.

L182

RELEASE CHARACTER `type name' is super-type of Floating Component - TYPE: `type name'

Hint: This occurs when a syntax item is used to specify both a release character and a floating component. You can add another sub-type to the syntax item and replace the release character name with the new sub-type name.

L183

COMPONENT NAME ambiguous: 'type name' in TYPE: 'type name'

Hint: This type has a component whose relative name can be associated with more than one type in the schema. Rename the conflicting types.

L184

RESTRICTION longer than max TYPE size - RESTRICTION # of TYPE: `type name'

Hint: The Type in error is an item. Either change the maximum size of the item or remove the restriction.

RESTRICTION used in an earlier partition - RESTRICTION # of TYPE: `type name'

Hint: Item Partitions must have mutually exclusive restrictions. Remove the restriction from one of the partition restriction lists.

L186

Type of COMPONENT does not exist - `type name' in TYPE: `type name'

Hint: You probably entered an incorrect type name. Try the drag and drop approach to get the correct one.

L187

TYPE must be partitioned (since in a partitioned tree and has sub-types) - TYPE: 'type name'

Hint: All types in a partitioned sub-type must have mutually exclusive data objects. Set the partitioned property for the type in error.

L188

TYPE is FIXED, COMPONENT # must have a maximum range value - TYPE type name

L189

TYPE is FIXED, but COMPONENT # is not fixed - TYPE: `type name'

Hint: If the component is not intended to be fixed in size, change the group format for the Type to implicit. If the group format is intended to be fixed, check the component: if that component is an item, make sure it has a Padded To length; if that component is a group, change its type to be of fixed syntax.

L190

BINARY text ITEM used as COMPONENT neither FIXED nor SIZED - COMPONENT # of TYPE: `type name'

Hint: The size of a binary text item must either have a Padded To length or it must be sized by the previous component.

L191

COMPONENT with SIZED attribute is not an UNSIGNED INTEGER ITEM TYPE - COMPONENT # of TYPE: `type name'

Hint: A component used to size the component that follows it must be defined as an unsigned integer item type.

L192

The last COMPONENT in the COMPONENT LIST may not have a SIZED attribute: TYPE: 'type name'

Hint: Specify a component to follow the one with the sized attribute.

Range of COMPONENT # must have a maximum value to indicate how many placeholders are needed for its series in TYPE: `type name'.

Hint: Change the range maximum to a specific value (not "s") if you may re-define the data this way.

L194

Cannot distinguish delimiter from terminator in TYPE: 'type name'.

Hint: Make the range of the last component in the type fixed or make the delimiter of the type different from its terminator.

L195

Cannot distinguish delimiter contained in COMPONENT # from terminator of TYPE: `type name'.

Hint: Make that component bound or make that contained delimiter different from the type terminator.

L196

Cannot distinguish delimiter of COMPONENT # from delimiter of TYPE: *type name* because COMPONENT # has no placeholder.

Hint: Make that component bound or make that component's delimiter different from the type delimiter.

L197

Cannot distinguish delimiter of COMPONENT # from delimiter of TYPE: *type name* because COMPONENT # has no range maximum.

Hint: Make that component bound, or make that component's delimiter different from the type delimiter, or specify a range maximum that has a specific value (not "s") for the last component of COMPONENT #.

L198

Cannot distinguish delimiter contained in COMPONENT # from delimiter of TYPE: 'type name'.

Hint: Make that contained component bound or make that contained component's delimiter different from the type delimiter.

L200

Cannot distinguish delimiter contained in COMPONENT # from delimiter of TYPE: `type name'.

Hint: Either make that contained component bound, make that contained component's delimiter different from the type delimiter, or specify a range maximum that has a specific value (not "s") for the last component of the contained component.

Logic error and warning messages

The tables in this section list the logic warning messages that result from a logic analysis of a schema.

The following table lists the warnings than can result when a map is compiled.

Warnings should be resolved because they may produce unpredictable results at mapping time.

Return Code

Message

L199

COMPONENT # is not distinguishable from COMPONENT # that may follow in TYPE: `type name'.

Hint: Make the first COMPONENT bound, or look at the tables in "Distinguishable objects" on page 863 to see how you can define the two component types as distinguishable.

L201

Different data objects of COMPONENT # are not distinguishable in TYPE: `type name'.

Hint: See "Distinguishable objects" on page 863 for more information about distinguishable objects.

L202

RESTRICTION list deleted: TYPE is not an ITEM - TYPE: `type name'

Hint: Type class was changed from an item to a group or category, so the restriction list was deleted. If this was not your intent, change it back to the way it was.

L203

COMPONENT list deleted: TYPE is an ITEM - TYPE: 'type name'

Hint: Type class was changed from a group to a item or category, so the program deleted its component list. If this was not your intent, change it back to the way it was.

L204

DELIMITER deleted: TYPE is not a DELIMITED GROUP - TYPE: 'type name'

Hint: Group format was changed from delimited to something else, so the program deleted its delimiter. If this was not your intent, change it back to the way it was.

L205

COMPONENT RULE deleted: TYPE is a CATEGORY - TYPE: `type name' (warning)

Hint: Type class was changed from a group to a category, so its component rule was deleted. If this was not your intent, change it back to the way it was.

L206

DELIMITER cannot be found (because first component is not required) - TYPE: `type name' (warning)

Hint: If the delimiter is missing, a previously set initiator value or the default value is used.

L251

COMPONENT NAME could apply to more than one type: 'type name' in TYPE: 'type name' (warning).

Schema analysis structure error messages

The following table lists the structure error messages that result from a structural analysis of a schema:

Return Code

Message

S100

Invalid TYPE Name: SubTYPE # of TYPE: `type name'

S101

Invalid TYPE chain: SubTYPE # of TYPE: `type name'

S118

Invalid TYPE NAME WhereUsed chain - TYPE NAME: `type name' (error).

S133

Referenced COMPONENT not `InUse' - COMPONENT # of TYPE: `type name' (error).

S134

COMPONENT previously referenced - COMPONENT # (COMP #) of TYPE: 'type name' (error).

S149

Bad Parent COMPONENT Index - COMPONENT `type name' - TYPE: `type name' (error)

Schema analysis structure warning messages

The following table lists the structure warning messages that result from a structural analysis of a schema:

Return Code

Message

S102

Unused DELIMITER deleted: `type name' (at index #)

S103

Invalid DELIMITER pointer deleted - TYPE: 'type name'

S104

Invalid default DELIMITER pointer deleted - TYPE: 'type name'

S105

Invalid RELEASE Char pointer deleted - TYPE: 'type name'

S106

Invalid default RELEASE Char pointer deleted - TYPE: `type name'

S107

Invalid INITIATOR pointer deleted - TYPE: `type name'

S108

Invalid default INITIATOR pointer deleted - TYPE: 'type name'

S109

Invalid TERMINATOR pointer deleted - TYPE: `type name'

S110

Invalid default TERMINATOR pointer deleted - TYPE: 'type name'

S111

Resetting DELIMITER Use Count (was # now #) - DELIMITER: `type name'

S112

Unused DESCRIPTION deleted: `type name' (at index #)

S113

Invalid DESCRIPTION pointer deleted - TYPE: `type name'

S114

Resetting DESCRIPTION Use Count (was # now #) - DESCRIPTION: `type name'

S115

Invalid Floating Component TYPE pointer deleted - TYPE: `type name'

S116

Invalid TYPE UsedInComp chain repaired - TYPE: 'type name'

S117

Unused TYPE NAME deleted - TYPE NAME: `type name' (at index #)

S119

Resetting TYPE NAME use count (was # now #) - TYPE NAME: `type name'

S120

Repaired empty TYPE NAME WhereUsed chain - TYPE NAME: `type name'

S121

Unused RESTRICTION NAME deleted: `type name' (at index #)

S122

Invalid RESTRICTION NAME deleted no DESCRIPTION was available - TYPE: 'type name'.

S123

Invalid RESTRICTION NAME deleted DESCRIPTION was `type name' - TYPE: `type name'

S124

Resetting RESTRICTION NAME Use Count (was # now #) - RESTRICTIONS: 'type name'

S125

Unused RESTRICTION DESCRIPTION deleted: `type name' (at index #)

S126

Invalid RESTRICTION DESCRIPTION deleted - TYPE: 'type name'

S127

Resetting RESTRICTION DESCRIPTION Use Count (was # now #) - RESTRICTIONS: 'type name'

S128

Unused RULE deleted: `type name' (at index #)

S129

Invalid RULE pointer deleted - COMPONENT # of TYPE: 'type name'

S130

Resetting RULE Use Count (was # now #) - RULE: `type name'

S131

Invalid COMPONENT TYPE Description pointer - COMPONENT #

S132

COMPONENT marked `InUse' found in Free Chain- COMPONENT #

S135

COMPONENT in Free Chain referenced by a TYPE - COMPONENT #

S136

COMPONENT recovered and added to Free Chain - COMPONENT #

S137

TYPE in Free Chain referenced by another TYPE - TYPE #

S138

TYPE recovered and added to Free Chain - TYPE X'%04X'

S139

TYPE marked `InUse' but not referenced - TYPE #

S140

Referenced TYPE not marked `InUse' - TYPE #

S141

TYPE Free Chain not in order: sorting

S142

COMPONENT Free Chain not in order: sorting

S143

Overlap found in LIST Free Chain

S144

Free Chain extends into unallocated region

S145

Overlap found in COMPONENT LIST SPACE: list cleared COMPONENTS will be deleted

S146

Invalid COMPONENT LIST pointer: all COMPONENTS DELETED - TYPE: 'type name'

S147

Resetting COUNT in COMPONENT LIST: some COMPONENTS may be lost

S148

RULE truncated (due to internal error): 'type name' (at index #)

S150

CATEGORY `type name' was missing GROUP and/or ITEM attributes

S151

GROUP `type name' was missing GROUP attributes

S152

ITEM `type name' was missing ITEM attributes

Compile-time error messages

When you generate the test data of a schema, you might encounter compile-time error messages. The schemas with compilation errors fail to generate the test data. You can view the error messages on the schema designer.

You can download the schema definition file (.mmc) to troubleshoot the compile-time errors from the following location of the HCL® OneTest[™] Data pod:

/opt/hcl/hip-rest/maps/<genMapPath>

The following table lists the compile-time errors that can occur when you generate the test data:



Note: In the following messages, the characters ${\bf x}$ and ${\bf y}$ are used as variables:



- \mathbf{x} = the map where the error occurred
- + $_{\rm Y}$ = the output that displays the rule with error

Compile-time Error Message	Description
Map:x Output:y Output argument of rule does not match output item sub-class	 This error appears when you enter an invalid regular expression for an item type in Item Properties of the Properties dialog. For example, If you select Number as Item subclass in Item Properties of the Properties dialog and enter text as the value of the Regular Expression field, then you encounter this error. To resolve this error, enter the valid values for the regular expression.
No such file or directory	This error appears when you enter an incorrect filename for the Values file field while you set up the restrictions for an item type in the Properties dialog. To resolve this error, enter the correct filename that you want HCL® OneTest [™] Data to use to import the values of the item type.
Map:x Output:y Rule references unknown	This error appears when you apply an invalid function for any item type. To resolve this error, apply the correct function.
Group <component_name> Root does not have any components (or subtypes if it is a partitioned group).</component_name>	This error appears when you define an invalid schema. To resolve this error, ensure that you correctly define the type defini- tions of the schema and its properties.
There is a missing component in group <component_name> Root</component_name>	This error appears when the reference of any type definitions exists in the Structure dialog and the definition of that type is missing in the Dictionary of the schema. For example, if in the Structure dialog, you have a reference of an item type Age , and the definition of this item type is missing in the Dictionary , then you encounter this error.
	To resolve this error, you must delete the reference of the type from the Structure dialog that does not exist in the dictionary.

Configuring log files

When you run into issues to trace the log files or the log files end abruptly without the complete information about the action, you must configure settings for the log file in the configMap file.

Before you begin

- You must have installed HCL OneTest[™] Server.
- You must have access to the Secure Shell (SSH) console.

About this task

To troubleshoot the issue, you can configure the following settings:

- The maximum number of log files.
- The maximum file size of each log file.



Note: The default value of the maximum number of log files is 5 and the maximum file size of each log file is 10 MB.

 Open the HCL® OneTest[™] Data configMap file to edit by using the following command: kubectl edit configmap -n {namespace} {my-ots}-data-config -o yaml.



Note: You can use the following command to get the list of the configMap files: kubectl get configmaps

- 2. Modify the values of the following parameters that you want to change: log_file_size and max_no_of_log_files
- 3. Save the changes.
- 4. Restart the onetestdata pod by using the following command: kubectl delete pod {my-ots}-data-app-0.

Results

You have configured the settings for the log files. You have modified the maximum number of log files and the maximum size of each log file.

Audit log overview

When execution of a map to generate the test data fails, HCL® OneTest[™] Data creates an audit log. The audit log records the detailed information about the execution of the failed job.

You can download the audit log of the failed job from the Jobs page by clicking the Download Log File button.

Audit log contents

The audit log provides an execution summary of the following information:

ExecutionSummary Fields	Description
CommandLine	Specifies the name and the location of the compiled map.
Elapsedsec	Specifies the total time spent on the map execution. The time spent is presented in seconds only (rounded). For example, ElapsedSec="25".
mapreturn	Returns a code to specify the result of map execution. For example, mapreturn="0".
MapStatus	Specifies the status of the map executed.
Message	Notifies the map execution result.
ObjectsBuilt	Specifies the number of objects generated based on the data. Each type in a schema represents an object.
ObjectsFound	Specifies the number of objects identified based on the data read. Each type in a schema represents an object.
SourceReport	Provides a detailed report about the source adapter.

Note: Some of the execution information is optional, and are not always displayed in the ExecutionSummary of the audit log.

Source data report

The source data report provides the following information:

- Value of the source adapter
- Byte count of the source data
- Return code of the source adapter with a message
- Adapter command line or file path
- Time stamp of the data source

Sample of an execution summary in an audit log file

The following sample is the execution summary of the audit log file.

<ExecutionSummary MapStatus="Valid" mapreturn="0" ElapsedSec="0.0373" BurstRestartCount="0"> <Message>Map completed successfully</Message> <CommandLine>'install_dir\examples\CallsSummary.mmc'</CommandLine> <ObjectsFound>18</ObjectsFound> <ObjectsBuilt>12</ObjectsBuilt> <SourceReport card="1" adapter="File" bytes="52" adapterreturn="0"> <Message>Data read successfully</Message> <Settings>install_dir\examples \stores.txt</Settings> <TimeStamp>18:10:04 December 26, 2019</TimeStamp> </SourceReport> <SourceReport card="2" adapter="File" bytes="69" adapterreturn="0"> <Message>Data read successfully</Message> <Settings>install_dir \examples\CALLS.TXT</Settings> <TimeStamp>18:10:04 December 26, 2019</TimeStamp> </SourceReport> <TargetReport
card="1" adapter="File" bytes="119" adapterreturn="0"> <Message>Data written successfully</Message>
<Settings>install_dir\examples\summary.txt</Settings> <TimeStamp>10:14:34 Dec 27, 2019</TimeStamp>
</TargetReport> <WorkArea type="File"> <inputarea card="1" Path="install_dir\examples\CallsSummary.I01"
TimeStamp="10:14:34 Dec 27, 2019" bytes="65695"/> <inputarea card="2" Path="install_dir\examples
\CallsSummary.I02" TimeStamp="10:14:34 Dec 27, 2019" bytes="65695"/> <outputarea card="1" Path="install_dir\examples
\CallsSummary.O01" TimeStamp="10:14:34 Dec 27, 2019" bytes="65695"/> </WorkArea> </ExecutionSummary>

Disabling audit logs

As a default configuration, HCL® OneTest[™] Data generates audit logs for each failed test data generation job. However, you might want to disable the audit logs when you no longer require them. In such case, you must change the default configuration.

Before you begin

- You must have cluster-admin permissions.
- You must have the IP address of the computer where HCL OneTest™ Server is installed.

About this task

You must set the value of the **AUDIT_ENABLED** property in the configmap file to disable the audit log for all the failed test data generation jobs.

- 1. Log in to the SSH console of HCL OneTest[™] Server.
- 2. Run the following command to edit the configuration file:

kubectl edit configmap -n test-system {my-ots}-data-config -o yaml

3. Search for the AUDIT_ENABLED property in the configuration file, and then set the value as false.



Note: The default value of AUDIT_ENABLED is true.

- 4. Save your changes, and then exit from the configuration file.
- 5. Run the following command to delete and restart the *<onetest data>* pod:

kubectl delete pod {my-ots}-data-app-0

Results

You have successfully disabled the audit logs for all the failed test data generation jobs.

Commands used in HCL OneTest Data

When you want to view the list of HCL® OneTest[™] Data pods and to manage each of these pods, you can run the kubectl or oc commands on an SSH console.

The following table provides you the list of commands that you can use to manage the pods on the Kubernetes environment (k3s):

Commands	Purpose	Examples
kubectl get pods	Shows the list of all pods with the status of each pod.	-
kubectl get configmaps	Shows the list of all configuration files.	-
kubectl exec -it <podname> bash</podname>	Helps to access the pod.	<pre>kubectl exec -it {my-ots}-data-app -0 bash</pre>
kubectl edit configmap -n <name- space> <configmapname> -o yaml</configmapname></name- 	Edits the configuration file.	kubectl edit configmap -n test- system {my-ots}-data-config -o yaml
kubectl delete pod <podname></podname>	Deletes and restart the pod.	kubectl delete pod {my-ots}-da- ta-app-0
kubectl logs <podname></podname>	Shows the logs of any specific pod.	kubectl logs {my-ots}-data-app-0

The following table provides you the list of commands that you can use to manage the pods on the Red Hat OpenShift server:

Commands	Purpose	Examples
oc get pods	Shows the list of all pods with the status of each pod.	-
oc get configmaps	Shows the list of all configuration files.	-
oc exec -it <podname> bash</podname>	Helps to access the pod.	oc exec -it {my-ots}-data-app -0 bash
oc edit configmap -n <namespace> <configmapname> -o yaml</configmapname></namespace>	Edits the configuration file.	oc edit configmap -n test-system {my-ots}-data-config -o yaml
oc delete pod <podname></podname>	Deletes and restart the pod.	oc delete pod {my-ots}-data-app-0
oc logs <podname></podname>	Shows the logs of any specific pod.	oc logs {my-ots}-data-app-0

Troubleshooting installation issues

You might encounter issues when you access HCL® OneTest[™] Data after you install HCL OneTest[™] Server for the first time. You can find details about the issues, their causes, and resolutions to fix those issues.

Problem	Cause	Solution
When you access HCL® OneTest [™] Data after you install HCL OneTest [™] Server on the Kubernetes environ- ment (k3s) or Red Hat OpenShift server for the first time, you might en- counter an error stating that the page cannot be loaded.	The pods such as <i>HIP Server</i> and <i>Da-ta app</i> might have failed to run successfully.	You must restart the pods by using the following commands: For <i>HIP Server</i> on k3s environment kubect1 delete pod {my-ots}-hip- server-0 For <i>HIP Server</i> on Red Hat OpenShift server oc delete pod {my-ots}-hip-serv- er-0 For <i>Data app</i> on k3s environment kubect1 delete pod {my-ots}-da- ta-app-0 For <i>Data app</i> on Red Hat OpenShift server oc delete pod {my-ots}-data-app-0 Where {my-ots} is the name of the re- lease that is provided during the in- stallation of the server software.
When you generate a test data af- ter you install HCL OneTest [™] Server on the k3s environment or Red Hat OpenShift server for the first time, you might get a page that displays <i>Er</i> - <i>ror</i> .	The pod such as <i>HIP Rest</i> might have failed to run successfully.	You must restart the pod on the k3s environment by using the following command: kubectl delete pod {my-ots}-hip- rest-0 Use the following command to restart the pod on the Red Hat OpenShift server: oc delete pod {my-ots}-hip-rest-0 Where {my-ots} is the name of the re- lease that is provided during the in- stallation of the server software.

Security Considerations

This document describes the actions that you can take to ensure that your installation is secure, customize your security settings, and set up user access controls.

- Enabling secure communication between multiple applications on page mclxxi
- Ports, protocols, and services on page mclxxi
- Customizing your security settings on page mclxxi
- Setting up user roles and access on page mclxxii

Enabling secure communication between multiple applications

The majority of communications are sent over TLS to port 443 (see Ports, protocols, and services on page mclxxi). During the installation, an X.509 certificate is generated for the user provided DNS name, which is used to connect to the server. This certificate is self-signed and hence untrusted by other applications.

This self-signed certificate must be replaced by a certificate signed by a certificate authority trusted by your organization. For more information, see X.509 Certificate User Authentication in the Keycloak documentation.

For information about how the self-signed certificate was created, see the ssl.sh file in the <install-directory>/ prepare/ directory.

For information about importing a certificate authority trusted by your organization, see Certificate authority: Importing and extending lists on page 97.

Ports, protocols, and services

TCP port 443 is used by the majority of communications with the server.

The port 7085 is the default port for communications with agents registered with HCL OneTest™ Server.

The ports starting from 7085, are used in pairs such as 7085 and 7086, and are allotted for the Schedule that is executed first. The next Schedule is allotted the next pair (7087,7088), and so on for the Schedules that are running simultaneously.

You must open the required ports in pairs for each of the Schedules that you want to run simultaneously.

Customizing your security settings

You can customize your security settings through user registration.

User registration

By default, users can sign up themselves with the server. In some environments, this self sign-up might be undesirable. It can be changed by switching off user registration. For more information, see User Registration in the Keycloak documentation.

By default, user email addresses are not verified. This verification must be enabled in production environments. For more information, see Email settings on page 86.

Setting up user roles and access

You can manage user roles and access through single sign on (SSO) and administration only accounts.

Single sign-on

By default, Keycloak manages users and passwords locally. In production environments, it is normally appropriate to use single sign-on. For more information, see LDAP user administration on page 87.

Administration only accounts

Users in the Administrator group can manage the team space where they can configure licenses and notifications and add a repository to store the System model. For more information, see Team space overview on page 108.

Users in the Administrator group can also discover all projects stored on the server (including private ones) and assign themselves and others roles in those projects.

For this reason, users who use the server to perform both administration and non-administration tasks must have two different accounts, one for each purpose. For more information, see Default user administration on page 85.

Notices

This document provides information about copyright, trademarks, terms and conditions for the product documentation.

© Copyright IBM Corporation 2000, 2016 / © Copyright HCL Technologies Limited 2016, 2022

This information was developed for products and services offered in the US.

HCL® may not offer the products, services, or features discussed in this document in other countries. Consult your local HCL® representative for information on the products and services currently available in your area. Any reference to an HCL® product, program, or service is not intended to state or imply that only that HCL® product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any HCL® intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-HCL® product, program, or service.

HCL® may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

HCL 330 Potrero Ave. Sunnyvale, CA 94085 USA Attention: Office of the General Counsel

For license inquiries regarding double-byte character set (DBCS) information, contact the HCL® Intellectual Property Department in your country or send inquiries, in writing, to:

HCL 330 Potrero Ave. Sunnyvale, CA 94085 USA Attention: Office of the General Counsel

HCL TECHNOLOGIES LTD. PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some jurisdictions do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. HCL® may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-HCL® websites are provided for convenience only and do not in any manner serve as an endorsement of those websites. The materials at those websites are not part of the materials for this HCL® product and use of those websites is at your own risk.

HCL® may use or distribute any of the information you provide in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

HCL 330 Potrero Ave. Sunnyvale, CA 94085 USA Attention: Office of the General Counsel

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by HCL® under terms of the HCL® Customer Agreement, HCL® International Program License Agreement or any equivalent agreement between us.

The performance data discussed herein is presented as derived under specific operating conditions. Actual results may vary.

Information concerning non-HCL® products was obtained from the suppliers of those products, their published announcements or other publicly available sources. HCL® has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-HCL® products. Questions on the capabilities of non-HCL® products should be addressed to the suppliers of those products.

Statements regarding the future direction or intent of HCL® are subject to change or withdrawal without notice, and represent goals and objectives only.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to actual people or business enterprises is entirely coincidental.

COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to HCL®, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. HCL®, therefore, cannot guarantee or imply reliability,

serviceability, or function of these programs. The sample programs are provided "AS IS", without warranty of any kind. HCL® shall not be liable for any damages arising out of your use of the sample programs.

Each copy or any portion of these sample programs or any derivative work must include a copyright notice as follows:

© (your company name) (year). Portions of this code are derived from HCL Ltd. Sample Programs. © Copyright HCL Ltd. 2000, 2022.

Trademarks

HCL®, the HCL® logo, and hcl.com® are trademarks or registered trademarks of HCL Technologies Ltd., registered in many jurisdictions worldwide. Other product and service names might be trademarks of HCL® or other companies.

Terms and conditions for product documentation

Permissions for the use of these publications are granted subject to the following terms and conditions.

Applicability

These terms and conditions are in addition to any terms of use for the HCL® website.

Personal use

You may reproduce these publications for your personal, noncommercial use provided that all proprietary notices are preserved. You may not distribute, display or make derivative work of these publications, or any portion thereof, without the express consent of HCL®.

Commercial use

You may reproduce, distribute and display these publications solely within your enterprise provided that all proprietary notices are preserved. You may not make derivative works of these publications, or reproduce, distribute or display these publications or any portion thereof outside your enterprise, without the express consent of HCL®.

Rights

Except as expressly granted in this permission, no other permissions, licenses or rights are granted, either express or implied, to the publications or any information, data, software or other intellectual property contained therein.

HCL® reserves the right to withdraw the permissions granted herein whenever, in its discretion, the use of the publications is detrimental to its interest or, as determined by HCL®, the above instructions are not being properly followed.

You may not download, export or re-export this information except in full compliance with all applicable laws and regulations, including all United States export laws and regulations.

HCL® MAKES NO GUARANTEE ABOUT THE CONTENT OF THESE PUBLICATIONS. THE PUBLICATIONS ARE PROVIDED "AS-IS" AND WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING BUT NOT LIMITED TO IMPLIED WARRANTIES OF MERCHANTABILITY, NON-INFRINGEMENT, AND FITNESS FOR A PARTICULAR PURPOSE.

Index

Special Characters

[] reserved symbol 885 @ reserved symbol 887 < > reserved symbol 885 \$ in a component rule 888

Numerics

1 776

Α

ABS function 1052 **ABSENT function 996** accessibility HCL OneTest Server disability 35 keyboard 35 Accessing secrets 747 ACOSINE function 1053 adapter commands list for R/3 776 adapter commands See R/3 adapter commands 776 ADDDAYS function 952 ADDHOURS function 953 **ADDMINUTES function 954** administration default security HCL OneTest Server 85 administration Idap security HCL OneTest Server 87 ALE (Application Link Enabling) interface definition 775 overview 778 ALL function 1011 AMS (Message Handler) interface See Message Handler (AMS) interface 775 analyzer schemas 863 Application Link Enabling (ALE) interface See ALE (Application Link Enabling) interface 775 arguments of a function 896 arithmetic operators 893 ASIN function 1053 ATAN function 1054 ATAN2 function 1054 attributes identifier 853 restart 853 sized 853

В

backing up and restoring user data HCL OneTest Server 71, 72 BAPI (Business Application Programming Interface) definition 776, 779

overview 779 **BCDTOHEX** function 921 **BCDTOINT function 922** BCDTOTEXT function 923, 1067 bidirectional type property 818 big endian 794, 794 binary values 793, 815 BCD 794 float 793 integer 793 packed 793 **BINDABS** function 1011 BOR (Business Object Repository) 779 bound objects in an expression 892 bound types 864 **Business Application Programming** Interface (BAPI) See BAPI (Business Application Programming Interface) 776, 779 business framework 779 Business Object Repository (BOR) 779 business objects 779 byte order property 794

С

card name in an expression 885 category definition of 782 inheritance 859, 859 when not to use 860 CDATA 843 Change Classification 754 Dataset 754 Encrypt 754 Change Classification Dataset 161 character size constraints 792 character values 793, 815 decimal 795 integer 794 zoned 795 character zoned numbers places 795 sign 795 size (content) 795 choice group objects 881 CHOOSE function 1020 class changing 784 definition of 784 **CLONE function 907** code pages 1127 colon in a component path 886 comment name 887 common item properties NONE 814, 817, 827 pad 801, 816 Required on input 814, 818, 827 Special Value 814, 817, 827 Zero 814, 827 comparison operators 894 component in a component list 886

in an expression 886 component path 884, 885 components 845 definina 847 defining rules for 850 distinguishable 870 implicit group 835 entering rules 851 guidelines 847 inheritance 859 optional 849 order of 845 range 845, 846 required 849 Configure Dataset 161 CONTAINSERRORS function 966, 997 content distinguishable components 871 control records for IDoc mapping 778 **CONVERT** function 924 **COSINE function 1054 COSINEH function 1055** COUNT function 1055 **COUNTABS function 1056 COUNTSTRING function 1068** Create **Classification 754** Create Dataset 142 Creating secrets 747 CSERIESTOTEXT function 1127 CSIZE function 1070 CTEXT function 1071 CURRENTDATE function 955 **CURRENTDATETIME function 956** CURRENTTIME function 957

D

data objects subtypes 781 size of 815 data records of IDocs 779 data segments of IDocs 779 Data Transfer Object (DXOB) See DXOB (Data Transfer Object) 779 Dataset 161 datasets encrypting 157 removing encryption 159 date & time subclass properties custom date format 822 custom time format 823 examples 826 format 821 presentation 819 time 820 date format custom 822 DATETONUMBER function 925, 958 DATETOTEXT function 926, 959, 1072 DBLOOKUP function 974, 1021 DBQUERY function 977, 1024 DDEQUERY function 980, 1027 **DEFAULT function 907** Delete Classification 754 Deleting secrets 747

delimiter 837 literal 836 location of 836 variable 836 description types 785 distinguishable data explicit group 881 implicit group 879 distinguishable objects 863 components 871 implicit group 835 of same component 870 types 871 document type 789 document verification 789 DXOB (Data Transfer Object) 779 definition 776 Е **ECHOIN function 908** EDI (Electronic Data Interchange) interface definition 775 overview 778 Edit Classification 754 Editing secrets 747 **EITHER function 1012** Electronic Data Interchange (EDI) interfaceSee EDI (Electronic Data Interchange) interface 775 element type declarations 843 Empty type property 788 errors messages 863 evaluation of component rules 888 of expressions 888 of functions 896 of map rules 883, 889 influence of card order 889 influence of functions 890 influence of object names 892 of operands 896 examples using AcceptAllPads type property 804 using Empty type property 788 **EXIT** function 981 EXP function 1056 explicit format 832 explicit group distinguishable data 881 expressions bound objects in 888 definition of 882 evaluating 888 operators in 893 shorthand notation in 888 external systems 774, 776, 779 EXTRACT function 1028

F

FACTORIAL function 1057 FAIL function 967 FILLLEFT function 1073 FILLRIGHT function 1074 FIND function 1075 fixed syntax 833 floating component 834 floating component type in an expression 887 format

date & time 821 custom 822, 823 group explicit 832, 833 implicit 835 FROMBASETEN function 927, 1057 FROMDATETIME function 928, 960 FROMNUMBER function 929 Function used to convert output item value 901 functions arguments 896 creating custom 1110 custom 1110 evaluation of 896

G

GETANDSET function 1029 **GETDIRECTORY function 1030 GETFILENAME** function 1032 **GETLOCALE** function 1032 **GETRESOURCEALIAS function 1034 GETRESOURCENAME function 1035** aettina started guide 19 GETTXINSTALLDIRECTORY function 1036 Grant access 754 Classification 754 group components 845 definition of 782 formats explicit 832, 833 implicit 835 group subclass 830 choice 830 sequence 830 unordered 831 guide getting started 19

н

I

HANDLEIN function 909 HCL OneTest Server accessibility 35 backing up and restoring user data 71, 72 default security administration 85 disability 35 keyboard 35 Idap security administration 87 managing account settings 96 managing secrets 747 offline user tokens 708 repository considerations 725 test assets 724 HCL OneTest Serve project overview test assets statistics 738 hex values 852 HEXTEXTTOSTREAM function 930, 1076 hierarchy of a schema 781 identifier attribute 853 specifying a component 858

IDocs (Intermediate Documents) control records 778 data records 779 data segments 779 definition 775 formats 778 overview 778 types 778 IF function 1013 implicit group distinguishable data 879 IN in component path 887 reserved word 884, 893 **RESOLVETYPE function 913** INDEX function 1036 **INDEXABS function 1037** indexing an input 885 inheritance category 859 components 859 initiator 785 input indexing 885 INT function 931, 1058 Intermediate Documents (IDocs) See IDocs (Intermediate Documents) 775 interpret as 793 introduction 774 ISALPHA function 999, 1014 ISERROR function 969, 999 ISLOWER function 1000, 1015 ISNUMBER function 1001, 1016 ISUPPER function 1002, 1017 item definition of 782 restrictions 843 item properties 792 interpret as 793 item subclass 792 number item subclass 793 syntax objects 828 text item subclass properties 815 item subclass 792

J

JEXIT function 987

L

language options 807, 817, 836 LAST reserved word 886 LASTERRORCODE function 1038 LASTERRORMSG function 1039 LEAVEALPHA function 1077 LEAVEALPHANUM function 1077 LEAVENUM function 1078 **LEAVEPRINT** function 1079 LEFT function 1080 length property bytes 794 literal delimiter value 836 literals definition of 883 in expressions 883 little endian 794, 794 local type name 885 location property 836 log file, generating 1106, 1110 LOG function 1058 LOG10 function 1059

logic errors type tree analysis 1146 logic warnings schema analysis 1159 logical operators 894 LOOKDOWN function 1041 LOOKUP function 1042 LOWERCASE function 1081

Μ

Manage encrypted dataset 754 managing account settings HCL OneTest Server 96 managing project secrets HCL OneTest Server 747 map rules evaluation 883 master data 776 for IDocs 778 mathlib functions ACOSINE 1053 ASIN 1053 ATAN 1054 ATAN2 1054 **COSINE 1054** COSINEH 1055 EXP 1056 FACTORIAL 1057 LOG 1058 LOG10 1059 **POWER 1061** RAND 1061 SIN 1063 SINH 1063 MAX function 961, 1059, 1081 MEMBER function 1003, 1043 Message Handler (AMS) interface definition 775 message transaction IDs (TIDs) 776 messages errors 863 warnings 863 MID function 1082 MIN function 961, 1060, 1083 MOD function 1060

Ν

name type 847 names data object 884 in a component rule 884 in a map rule 884 namespaces 842 national language 807, 817, 836 native 794, 794 no syntax group 835 NONE reserved word 898 assigned to an output number 901 when an input argument of a function evaluates to 899 when an input argument of a functional map evaluates to 900 when an operand evaluates to 899 NORMXML function SIZE function 1008, 1085

number item subclass property 793 byte order 794 length (bytes) 794 places 814 separators 796 numbers as literal 883 NUMBERTODATE function 931, 962 NUMBERTOTEXT function 932, 1085 0 object names 884 objects distinguishable 863, 870 Offline tokens 708 Offline user token 708 offline user tokens HCL OneTest Server 708 **OFFSET** function 1005 **ONERROR** function 970 operands evaluation of 896 operators arithmetic 893 comparison 894 in expressions 893 logical 894

order of evaluation 895 optional component 849 output items conversion of 901 overview server 19

P

Overview 774

PACK function 933 PACKAGE function 934, 1086 pad character specifying 862 pad property 801, 803, 816 PARTITION function 1006 partitioning 854, 854 benefits of 855 convenience 855 groups 857, 858, 858 component rules 859 items 856, 856, 857 required 854 types 785, 856, 881 partitions in an expression 885 PCDATA 843 places property 814 POWER function 1061 PRESENT function 1007 presentation property 819 properties item 818 national language 807, 817, 836 where used 789 PUT function 991

0

QUIT function 972

R

R/3 adapter commands list See adapter commands list for R/3 776

R/3 adapters 776 overview 776 R/3 interfaces 774 RAND function 1061 **RANDDATA function 1087** range default 846 examples of 849 **REFORMAT** function 912 **REJECT function 971** release characters definition of 786 guidelines 787, 787 Remove Classification 754 Dataset 754 Encrypt 754 **RENAMEFILE function 994** repository considerations HCL OneTest Server 725 required component 849 reserved symbol 886 reserved words and symbols 885, 886, 888 @ 887 < > 885 \$888 **COMPONENT 885** LAST 886 **RESOLVETYPE function 913** resourcelib functions **GETLOCALE 1032 GETRESOURCEALIAS 1034 GETTXINSTALLDIRECTORY 1036** restart attribute 853 restrictions settings 843 **REVERSEBYTE function 1088** Revoke access 754 **Classification 754** RFCs adapters 776 **RIGHT function 1088 ROUND function 1062** rules component 850, 851 defining 850 entering 851 RUN function 992, 1123 SAP

R/3 interfaces 775 SAP Integration Pack R/3 interfaces 776 SAP Integration Package about 774 components 776 R/3 interfaces 774 SAP R/3 interfaces 776, 779 SAP R/3 systems exchanging data 775 schema analysis logic errors 1146 structure errors 1161 structure warnings 1161 schema analyzer 862 schemas

S

analyzer 862 hierarchy 781 SEARCHDOWN function 1044 SEARCHUP function 1045 Secrets accessing 747 creating 747 deleting 747 editing 747 viewing 747 security considerations overview mclxxi separators 796 decimal 798 integer 796 SERIESTOTEXT function 935, 1090 server overview 19 task flows 31 Set Current row 161 Dataset 161 SETOFF function 918 SETON function 919 shorthand notation 888 in a map rule 888 sign property 795 SIN function 1063 SINH function 1063 size 815 command include self 854 digits 795 SIZE function 1008, 1070 NORMXML function 1008, 1085 sized attribute guidelines 853 SORTDOWN function 1046 SORTDOWNBY function 1048 SORTUP function 1049 SORTUPBY function 1050 SQRT function 1063 STREAMTOHEXTEXT function 937 structure errors schema analysis 1161 structure warnings schema analysis 1161 subtree 784, 847, 858, 858 subtypes 781 order 785 SUM function 1064 supertype definition of 781 SYMBOL function 938 syntax initiator 785 none 835 objects 828 data 829 release character 786 terminator 786

Т

task flows server 31 terminator 786 test assets HCL OneTest Server 724

test assets statistics HCL OneTest Server project overview 738 TESTOFF function 919, 1008 TESTON function 920, 1009 tests datasets 157, 159 text as a literal 883 TEXT function 1093 text functions RANDDATA 1087 **RENAMEFILE 994** text item subclass properties 815 interpret as 793, 815 TEXTTOBCD function 939, 1094 TEXTTODATE function 940, 963 time format custom 823 time property 820 time zones 824 TIMETOTEXT function 943, 965, 1097 TOBASETEN function 944, 1065 TODATETIME function 945, 966, 1097 TONUMBER function 946, 1098 trace log file, generating 1106, 1110 trace option about content length 803 track property 832 transaction IDs for messages 776 transactional Remote Function Calls (tRFCs) 774 tRFCsSee transactional Remote Function Calls (tRFCs) 774 **TRIMLEFT** function 1100 **TRIMRIGHT** function 1101 **TRUNCATE** function 1066 type definitions 862 type names local 885 type tree analysis logic warnings 1159 type trees analyzer 863 analyzing 862 handling large schemas 845 types bound 864 category 782 class 784 classes of 782 definition of 782 description 785 distinguishable 871 groups 782, 845 inheritance 859 item 782 name 783, 847 partitioned 785 subtypes 781 supertypes 781

U

unbound restrictions 844 UNIQUE function 1051 UNPACK function 948 UNZONE function 949 **UPPERCASE** function 1103

V

VALID function 973, 1010 VALIDATE function 1105, 1105 VALIDATEEX function 1105, 1106 variable delimiter 836 version compatibility 779 View Dataset 161, 161 Encrypt 161 Viewing secrets 747

W

warning messages 863 WHEN function 1019 where used 789 whitespace syntax build as 835 character set 835 wildcards element and attribute 843 WORD function 1103

Х

XML identity constraints 842 Location setting for metadata 840 metadata location 840 properties in the type tree 839 time zone formats 825 using Empty property 788 wildcards 843 Xerces 840 XML DTD Importer 843 XML functions 1105 XML Schema datatypes and type tree constructs 840 XML Schema Importer 842, 843 XML type property See document type 789 XMLLIB functions VALIDATE 1105 VALIDATEEX 1106 **XPATH 1107** XPATHEX 1108 XSLT 1109 XSLTEX 1110 XPATH function 1105, 1107, 1107 XPATHEX function 1105, 1108 XSDL hint Xerces schema 840 xsi:noNamespaceSchemaLocation Xerces XML schema 840 xsi:schemaLocation Xerces XML schema 840 XSLT function 1105, 1108, 1109 XSLTEX function 1105, 1110 XVALIDATE function 1105, 1106

Ζ

ZONE function 950